



## DMF™ 6 Administrator Guide

007-5484-016

---

## COPYRIGHT

© 2008-2015 Silicon Graphics International Corp. All Rights Reserved; provided portions may be copyright in third parties, as indicated elsewhere herein. No permission is granted to copy, distribute, or create derivative works from the contents of this electronic documentation in any manner, in whole or in part, without the prior written permission of SGI.

---

## LIMITED RIGHTS LEGEND

The software described in this document is "commercial computer software" provided with restricted rights (except as to included open/free source) as specified in the FAR 52.227-19 and/or the DFAR 227.7202, or successive sections. Use beyond license provisions is a violation of worldwide intellectual property laws, treaties and conventions. This document is provided with limited rights as defined in 52.227-14.

---

## TRADEMARKS AND ATTRIBUTIONS

CXFS, DMF, IRIX, SGI, SGI InfiniteStorage, the SGI logo, Silicon Graphics, and XFS are trademarks or registered trademarks of Silicon Graphics International Corp. or its subsidiaries in the United States and other countries.

AMPEX is a trademark of Ampex Corporation. DLT is a trademark of Quantum Corporation. GNOME is a trademark of the GNOME Foundation. Firefox and the Firefox logo are registered trademarks of the Mozilla Foundation. HP is a trademark of Hewlett-Packard Company. IBM and MVS are trademarks of International Business Machines Corporation, registered in many jurisdictions worldwide. Intel and Itanium are trademarks or registered trademarks of Intel Corporation in the United States and other countries. Lustre is a trademark and Oracle and Java are registered trademarks of Oracle and/or its affiliates. Internet Explorer, Microsoft, and Windows are either registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries. Linux is a registered trademark of Linus Torvalds in the U.S. and other countries. MIPSpro is a trademark of MIPS Technologies, Inc., used under license by Silicon Graphics, Inc., in the United States and/or other countries worldwide. Red Hat and Red Hat Enterprise Linux are registered trademarks of Red Hat, Inc. in the United States and other countries. Solaris, and Sun are trademarks or registered trademarks of Sun Microsystems, Inc. or its subsidiaries in the United States and other countries. SLES, SUSE, and YAST are registered trademarks of SUSE LLC in the United States and other countries. UNIX is a registered trademark of the Open Group in the United States and other countries. All other trademarks mentioned herein are the property of their respective owners.

---

## New Features in this Guide

This revision supports DMF 6.5 and includes the following changes:

- Configuration file changes:
  - New parameter in the `drivegroup` object:
    - `REDIRECT_TIME_DG_DOWN` specifies the number of seconds that DMF will wait before redirecting recalls; after all drives have been down for `REDIRECT_TIME_DG_DOWN` seconds, DMF will start forwarding every recall to the VG that holds the secondary copy.
  - New parameter in the `filesystem` object:
    - `RELEASETHREADS` specifies the number of threads in the DMF daemon that will be created to handle requests to release filesystem blocks when files are made offline (OFL).
  - New parameters in the `taskgroup` object:
    - `DMMIGRATE_MIN_OFFLINE_AGE` specifies the value used for the `-p` option (in minutes) when `dmmigrate(8)` is executed by the `run_dmmigrate.sh` task. This value is a file's minimum age in order for its data blocks to be released, making the file offline.
    - `DMMIGRATE_MIN_OFFLINE_SIZE` specifies the value used for the `-s` option (in bytes) when `dmmigrate` is executed by the `run_dmmigrate.sh` task. This value is a file's minimum size in order for its data blocks to be released, making the file offline.
    - `DMMIGRATE_QUEUE_MAX` specifies the maximum number of `dmmigrate` requests that can be outstanding in the DMF daemon queue at any given time when `dmmigrate` is executed by the `run_dmmigrate.sh` task; when this threshold is reached, the command waits before issuing more requests.

See:

- "drivegroup Object Parameters" on page 397
- "filesystem Object Parameters" on page 351
- "taskgroup Object Parameters" on page 312

- `dmmigrate(8)` man page
- Temporary files that are produced by the integrated-backup method now have a project ID of 4136. To exclude these temporary files from migration, you should add an initial `SELECT_VG` or `SELECT_MSP` parameter that is defined to exclude files with this project ID. This is required under the following conditions:
  - If `DUMP_WORKSPACE` is not set
  - If `DUMP_WORKSPACE` is explicitly set to a location inside the backup filesystem (the filesystem that has `USE_AS_DUMP_DEST` set to ON)See "policy Examples for Integrated Backups" on page 389.
- When DMF is stopped or started using the recommended `service(8)` commands (`service dmf stop` and `service dmf start`), all of the related services are now also stopped or started, irrespective of the status of DMF Manager (the `dmfman` service).
- When configuring the `ident` service, you should use the `only_from` option in the RHEL `/etc/xinetd.d/pidentd` file or SLES `/etc/xinetd.d/auth` file to specify that the service is only run on the DMF server. See step 5 of "Overview of the Installation and Configuration Steps" on page 165.
- "Ensure Quick Communication Among Nodes in the DMF Environment" on page 91:
  - "Preferred Method: Consistent `/etc/hosts` File on All Nodes and Access Local First" on page 91
  - "Acceptable Method: Reliable DNS in a Dedicated HA cluster" on page 93
- "Explicitly Specify the Server on OpenVault Commands" on page 122

---

## Record of Revision

<b>Version</b>	<b>Description</b>
001	December 2008 Original publication. Supports DMF 4.0 in SGI® InfiniteStorage Software Platform (ISSP) 1.5.
002	March 2009 Supports DMF 4.1 in ISSP 1.6.
003	June 2009 Supports DMF 4.2 in ISSP 1.7.
004	September 2009 Supports DMF 4.3 in ISSP 1.8.
005	January 2010 Supports DMF 5.0 in ISSP 2.0.
006	June 2010 Supports DMF 5.1 in ISSP 2.1.
007	September 2010 Supports DMF 5.2 in ISSP 2.2.
008	January 2011 Supports DMF 5.3 in ISSP 2.3.
009	October 2011 Supports DMF 5.5 in ISSP 2.5.
010	April 2012 Supports DMF 5.6 in ISSP 2.6.
011	April 2013 Supports DMF 6.0 in ISSP 3.0.
012	November 2013 Supports DMF 6.1 in ISSP 3.1.

Record of Revision

---

- |     |  |
|-----|--|
| 013 | May 2014<br>Supports DMF 6.2 in ISSP 3.2.      |
| 014 | October 2014<br>Supports DMF 6.3 in ISSP 3.3.  |
| 015 | July 2015<br>Supports DMF 6.4 in ISSP 3.4.     |
| 016 | November 2015<br>Supports DMF 6.5 in ISSP 3.5. |

---

# Contents

<b>About This Guide</b>	<b>li</b>
Related Publications	li
Man Pages	lii
User Commands	lii
File Formats	lii
Administrator Commands	lii
Obtaining Publications	liii
Conventions	liii
Reader Comments	liv
<b>1. Introduction</b>	<b>1</b>
DMF Features	1
Automatic Monitoring of Filesystem Space	2
Easy and Constant Availability of Data	5
Partial-State Files	5
Safety and Scalability	6
Site-Defined Migration Policies	7
A Variety of Migration Targets	7
Support for Fileserving Applications	8
DMF Manager Web Interface	9
DMF Control from Client Platforms	12
Overview of the Windows Client	12
Overview of the IRIX, Mac OS X, Linux, and Solaris Clients	12
High Availability	13
SOAP Web Service	13
<b>007-5484-016</b>	<b>vii</b>

Direct Archiving . . . . .	13
Mounting Services . . . . .	13
Out-of-Library Tapes . . . . .	14
How DMF Software Works . . . . .	14
File States . . . . .	14
DMF Methods . . . . .	15
Multiple Storage Tiers . . . . .	19
Two Tiers . . . . .	19
Three Tiers using DCM MSP . . . . .	21
Three Tiers using Fast-Mount Cache . . . . .	24
Migration Process . . . . .	27
Recall of File Data . . . . .	27
Recall from the Appropriate Location . . . . .	27
Order of Recall . . . . .	28
Freeing Data Blocks to Make Space for Recalls . . . . .	30
Fast-Mount Cache Configuration Overview . . . . .	30
Cache and Secondary-Storage Targets . . . . .	30
How Fast-Mount Cache Differs from a DCM MSP . . . . .	31
Fast-Mount Cache Implementation . . . . .	32
Appropriate Use of Fast-Mount Cache . . . . .	32
DMF Server Functions . . . . .	32
Parallel DMF Overview . . . . .	33
DMF Databases . . . . .	37
Ensuring Data Integrity . . . . .	38
DMF Architecture . . . . .	38
Migrate Groups . . . . .	42
DMF Capacity . . . . .	42
Requirements . . . . .	43



---

DMF Administrative and Store Directories . . . . .	44
PostgreSQL Database Server Requirements . . . . .	47
Server Node Requirements . . . . .	48
Parallel Data-Mover Node Requirements . . . . .	48
Mounting Service Requirements . . . . .	48
License Requirements . . . . .	48
DMAPI Requirement . . . . .	48
SAN Switch Zoning or Separate SAN Fabric Requirement . . . . .	49
DMF Manager Requirements . . . . .	49
DMF SOAP Requirements . . . . .	50
DMF Direct Archiving Requirements . . . . .	50
Fast-Mount Cache Requirements . . . . .	50
Cloud Storage Requirements . . . . .	51
Mediaflux Environment Requirements . . . . .	51
Administration Tasks . . . . .	51
Initial Planning . . . . .	52
Installation and Configuration . . . . .	52
Recurring Administrative Duties . . . . .	53
Free-Space Management . . . . .	53
File Ranking . . . . .	53
Offline Data Management . . . . .	54
Data Integrity and Reliability . . . . .	54
Run Backups . . . . .	55
Audit the Databases and Log files . . . . .	55
Protect Databases from Loss . . . . .	55
Remove Old Logs and Journals . . . . .	56
Hard-Delete Database Entries . . . . .	56

Commands Overview . . . . .	56
User Commands . . . . .	57
Licensing Commands . . . . .	58
Configuration Commands . . . . .	58
DMF Daemon and Related Commands . . . . .	59
Space Management Commands . . . . .	62
LS Commands . . . . .	63
DCM MSP Commands . . . . .	63
Disk MSP Command . . . . .	64
Other Commands . . . . .	64
<b>2. DMF Licensing . . . . .</b>	<b>67</b>
DMF License Types . . . . .	67
Anticipating Your DMF Data Capacity Requirements . . . . .	69
Displaying Current DMF Data Capacity Use . . . . .	72
Parallel Data-Mover Option and Licensing . . . . .	74
Mounting Services and Licensing . . . . .	74
Gathering the Host Information . . . . .	74
Obtaining the License Keys . . . . .	75
Installing the License Keys . . . . .	75
Verifying the License Keys . . . . .	75
DMF Manager Licenses Panel . . . . .	76
dmflicense . . . . .	77
lk_verify . . . . .	77
For More Information About Licensing . . . . .	79
<b>3. Best Practices for DMF . . . . .</b>	<b>81</b>
Best Practices for Installation, Upgrade, and Downgrade . . . . .	81
Use the Correct Mix of Software Releases . . . . .	81

---

Install DMAPI . . . . .	82
Do Not Use YAST to Configure Network Services . . . . .	83
Upgrade Nodes in the Correct Order . . . . .	83
Take Appropriate Steps when Upgrading DMF . . . . .	84
Contact SGI Support to Downgrade After Using OpenVault™ 4.0 or Later . . . . .	87
Best Practices for Configuration . . . . .	87
Plan Ahead for Disaster Recovery . . . . .	88
Best Practices to Permit Future Disaster Recovery . . . . .	89
When is Disaster Recovery Possible? . . . . .	89
What Must Be Protected . . . . .	89
Why Backups Are Needed . . . . .	90
Recovery Possibilities . . . . .	91
Best Practices for Performing Disaster Recovery . . . . .	91
Ensure Quick Communication Among Nodes in the DMF Environment . . . . .	91
Preferred Method: Consistent <code>/etc/hosts</code> File on All Nodes and Access Local First . . . . .	91
Acceptable Method: Reliable DNS in a Dedicated HA cluster . . . . .	93
Enable RSCN Suppression Appropriately . . . . .	93
Follow All DMF Requirements . . . . .	93
Use Supported Libraries and Tape Drives . . . . .	94
Use Sufficiently Fast Filesystems . . . . .	94
Configure Passwordless SSH . . . . .	94
Configure Filesystems and Directories Appropriately for DMF . . . . .	94
Do Not Place Administrative and Store Directories in a Managed Filesystem . . . . .	95
Use Different Physical Devices for <code>HOME_DIR</code> and <code>JOURNAL_DIR</code> . . . . .	95
Avoid Root Filesystem Location for a Production System . . . . .	95
Restrict Administrative and Store Directories to DMF Use . . . . .	95
Use CXFS Filesystems with the Parallel Data-Mover Option . . . . .	96

Sizing Guidelines . . . . .	96
<i>HOME_DIR</i> Size . . . . .	97
<i>JOURNAL_DIR</i> Size . . . . .	98
<i>SPOOL_DIR</i> Size . . . . .	98
<i>TMP_DIR</i> Size . . . . .	98
<i>MOVE_FS</i> Performance and Size . . . . .	98
Use the Correct Mount Options . . . . .	99
Migrate at Least Two Copies of a File . . . . .	100
Safely Make Changes to the DMF Configuration . . . . .	100
Make and Mount the Required Filesystems First . . . . .	101
Use Sample DMF Configuration Files . . . . .	101
Back Up the DMF Configuration File . . . . .	102
Stop DMF Before Making Changes . . . . .	102
Always Validate Your Changes . . . . .	103
Use Inode-Resident Extended Attributes and 256-byte Inodes . . . . .	104
Limit Path Segment Extension Records . . . . .	104
Do Not Change Script Names . . . . .	104
Configure DMF Appropriately with CXFS™ . . . . .	104
Improve Drive Performance with an Appropriate VG Zone Size . . . . .	105
Appropriately Force Small Files to Migrate . . . . .	107
Add HBA Drivers to the <i>initrd</i> Image . . . . .	107
Set <i>RECALL_NOTIFICATION_RATE</i> to 0 if CXFS Range Tokens are Disabled . . . . .	107
Set the <i>xinetd tcpmux instances</i> Parameter Appropriately . . . . .	108
Avoid Unintentional File Recall by Filesystem Browsers . . . . .	108
Configure Appropriately for SGI 400 VTL or COPAN MAID Shelves . . . . .	109
Use Migrate Groups Appropriately . . . . .	111
Use Fast-Mount Cache Appropriately . . . . .	112

Use Cloud Storage Appropriately . . . . .	114
Migrate a Second Copy Outside of the Cloud . . . . .	114
Use a Firewall . . . . .	115
Whitelist Only the DMF Server in a Private Cloud . . . . .	115
Use a Dedicated S3 Bucket . . . . .	115
Improve Throughput for S3 . . . . .	115
Minimize Access Times by Using <code>NAME_FORMAT</code> . . . . .	116
Ensure that the Cache Copy is Recalled First . . . . .	116
Use a Task Group to Run <code>dmmigrate</code> Periodically . . . . .	116
Restrict the Size of the Alerts and Performance Records Databases . . . . .	117
Prevent Stalled-Recovery Timeout in a Non-HA Environment . . . . .	118
Use Appropriate Tape Barcodes . . . . .	119
Use <code>dmarchive</code> to Copy Archive File Data to Secondary Storage . . . . .	119
Use an Appropriate Filesystem for a Disk MSP . . . . .	121
Use Corresponding Drive-Group Names in OpenVault and DMF . . . . .	121
Use a Private Network Interface in a Parallel Environment . . . . .	121
Modify Partial-State Capability with Care . . . . .	122
Use the Correct Child-Process Constraints for a DCM MSP . . . . .	122
Explicitly Specify the Server on OpenVault Commands . . . . .	122
Best Practices for Administration . . . . .	123
Stop and Start DMF Using the <code>service</code> Command . . . . .	124
Use a Time Synchronization Application . . . . .	124
Monitor DMF Daily . . . . .	125
Run Certain Commands Only on a Copy of the DMF Databases . . . . .	125
Be Aware of Differences in an HA Environment . . . . .	125
Start Site-Specific Configuration Parameters and Stanzas with “ <code>LOCAL_</code> ” . . . . .	125
Use TMF Tracing . . . . .	126

Run <code>dmccollect</code> If You Suspect a Problem . . . . .	126
Modify Settings If Providing File Access via Samba . . . . .	127
Export from the Active CXFS Metadata Server . . . . .	128
Disable Journaling When Loading an Empty Database . . . . .	128
Use Sufficient Network Bandwidth for Socket Merges . . . . .	128
Temporarily Disable Components Before Maintenance . . . . .	128
Gracefully Stop the COPAN Disks and JBFS Disks . . . . .	129
Reload STK ACSLS Cartridges Properly . . . . .	129
Disable Zone Reclaim to Avoid System Stalls . . . . .	129
Set Volume Size If You Want to Use Capacity Features . . . . .	129
Monitor the Size of the PCP Metrics Archive . . . . .	130
Be Aware that API Commands Change Without Notice . . . . .	130
Be Aware of Memory-Mapping Issues . . . . .	131
Use a Task to Perform Hard-Deletes Periodically . . . . .	131
Enable the Enhanced-NFS RPC Corruption Workaround Parameter if Needed . . . . .	131
Use the Appropriate Tool to Load Volumes to an Existing Environment . . . . .	132
Configure Fibre Channel Switches and Zones Appropriately . . . . .	132
Ensure that You Follow the Switch Requirements . . . . .	133
Segregate Tape and Disk HBAs . . . . .	133
Suppress Change Notification for Switch Ports Connected to Nodes . . . . .	133
Use <code>N-port</code> Topology for LSI Ports Used with Tape Drives . . . . .	133
Avoid Bottlenecks when Tape Drives and Host Port Speeds Do Not Match . . . . .	134
Use <code>dmmove(8)</code> Safely . . . . .	136
RHEL: Disable SELinux or Increase the Inode Size . . . . .	136
Apply Appropriate PostgreSQL Updates . . . . .	136
Best Practices for Backups . . . . .	137
Back Up Migrated Filesystems and DMF Databases . . . . .	137

Migrate All Files Before Performing a Backup . . . . .	137
Use the Integrated Backup Method . . . . .	138
Use a Remote Location for the Disaster-Recovery Bundle . . . . .	138
Retain Log and Journal Files Between Full Backups . . . . .	138
Best Practices for Optional Tasks . . . . .	138
Balance Data Among Libraries . . . . .	139
Prevent Recalls From Waiting for a Busy Volume . . . . .	140
Use the Immutable Bit if You Want to Prevent File Modification . . . . .	140
<b>4. Backups and DMF . . . . .</b>	<b>141</b>
DMF Requirement for Backups . . . . .	141
Dump Scripts . . . . .	141
run_full_dump.sh . . . . .	142
run_partial_dump.sh . . . . .	143
Site-Specific Factors to Consider . . . . .	144
Media-Specific Requirements . . . . .	144
Backups using Physical Tapes and SGI 400 VTL Tapes . . . . .	144
Backups using COPAN MAID . . . . .	145
Considerations for Optimizing Backups . . . . .	145
Migrate All Files First . . . . .	146
Consistent Backup Completing Times via DUMP_MAX_FILESPACE . . . . .	147
DUMP_MAX_FILESPACE Requires UPDATE_CTIME for Incremental Backups . . . . .	148
Integrated-Backup Method . . . . .	148
Overview of Integrated Backup . . . . .	149
Contents of the Integrated Backup . . . . .	149
Size of the Backup Filesystems . . . . .	153
DR Bundle Locations . . . . .	154

Configuring Integrated Backups . . . . .	154
Precedence of Objects for Integrated Backups . . . . .	154
Procedure to Configure Objects for Integrated Backups . . . . .	156
Converting to Integrated Backups . . . . .	157
Consideration for Integrated Backups: Restored Database May Point to Freed Space . . . . .	160
Monitoring Backup Reports for Integrated Backups . . . . .	160
Other Backup Methods . . . . .	161
Report Monitoring for Nonintegrated Tape Backups . . . . .	161
Storage Used by an FTP MSP or a Standard Disk MSP for Nonintegrated Backups . . . . .	161
Filesystems Used by a DCM MSP for Nonintegrated Backups . . . . .	161
DMF's Private Filesystems and Nonintegrated Backups . . . . .	163
<b>5. Installing and Configuring the DMF Environment . . . . .</b>	<b>165</b>
Overview of the Installation and Configuration Steps . . . . .	165
Installation and Configuration Considerations . . . . .	169
ISSP DMF Software . . . . .	169
Mounting Service Considerations . . . . .	170
Inode Size Configuration . . . . .	171
Daemon Database Record Length . . . . .	173
Interprocess Communication Parameters . . . . .	175
Automated Maintenance Tasks . . . . .	175
Networking Considerations for Parallel Data-Mover Option . . . . .	176
Passwordless SSH Configuration for DMF . . . . .	176
Suppressing RSCN on Host Port HBAs . . . . .	177
QLogic® Fibre Channel Switch . . . . .	178
IPv6 . . . . .	181
Starting and Stopping the DMF Environment . . . . .	181



Automatic Start After Reboot . . . . .	182
Preventing Automatic Start After Reboot . . . . .	182
Explicit Start . . . . .	183
Explicit Stop . . . . .	183
Using Out-of-Library Tapes . . . . .	184
TMF and Out-of-Library Tapes . . . . .	185
OpenVault and Out-of-Library Tapes . . . . .	185
Customizing DMF . . . . .	186
File Tagging . . . . .	186
Site-Defined Policies . . . . .	187
Site-Defined Client Port Assignment in a Secure Environment . . . . .	188
Importing Data From Other HSMs . . . . .	189
<b>6. DMF Manager . . . . .</b>	<b>191</b>
Accessing DMF Manager . . . . .	192
Getting Started with DMF Manager . . . . .	192
Running Observer Mode or admin Mode . . . . .	195
Observer Mode Functionality . . . . .	195
admin Mode Functionality . . . . .	196
Admin Mode Access . . . . .	198
Getting More Information in DMF Manager . . . . .	198
Setting Panel Preferences . . . . .	201
Refreshing the View . . . . .	202
Managing Licenses and Data Capacity with DMF Manager . . . . .	203
Adding New Licenses . . . . .	203
Deleting Existing Licenses . . . . .	204
Viewing the Installed Licenses . . . . .	205

Showing Current DMF Usage and Licensed Capacity . . . . .	205
Showing Remaining Storage Capacity . . . . .	206
Configuring DMF with DMF Manager . . . . .	210
Limitations to the DMF Configuration Capability . . . . .	211
Showing All Configured DMF Objects . . . . .	211
Setting Up a New DMF Configuration File . . . . .	212
Copying an Object . . . . .	215
Modifying an Object . . . . .	217
Creating a New Object . . . . .	217
Deleting an Object . . . . .	218
Validating Your Changes . . . . .	218
Saving Your Configuration Changes . . . . .	218
Exiting the Temporary Configuration without Saving . . . . .	219
Displaying DMF Configuration File Parameters . . . . .	219
Starting and Stopping DMF and the Mounting Service . . . . .	220
Discovering DMF Problems . . . . .	221
Filtering Alerts . . . . .	225
Seeing Relationships Among DMF Components . . . . .	227
Managing Volumes . . . . .	229
Managing Libraries . . . . .	232
Displaying DMF Manager Tasks . . . . .	233
Monitoring DMF Performance Statistics . . . . .	233
Using the Statistics Panels . . . . .	234
Metrics Collection . . . . .	235
DMF Activity . . . . .	235
Overview of DMF Activity Reports . . . . .	235

---

Key to DMF Activity Reports . . . . .	236
Example of DMF Activity Report . . . . .	237
DMF Resources . . . . .	238
Programs that Update the DMF Resources Reports . . . . .	239
Filesystem Folder . . . . .	239
Libraries Report . . . . .	242
Drive Group Folder . . . . .	242
Volume Group Folder . . . . .	244
DCM MSP Folder . . . . .	246
DMF I/O . . . . .	248
Displaying Node Status . . . . .	252
Restoring Filesystems in DMF Manager . . . . .	255
Restore a Filesystem Component (Integrated Backups) . . . . .	255
Example: Restoring to the Original Location . . . . .	258
Example: Restoring to a New Location . . . . .	260
Restore a Filesystem Component (Nonintegrated Backups) . . . . .	260
Stop a Restoration Process . . . . .	261
View Restoration Logs . . . . .	262
Disaster Recovery in DMF Manager for Basic DMF . . . . .	262
Viewing the DMF Queue . . . . .	263
LTFS in DMF Manager . . . . .	263
Showing LTFS Information in DMF Manager . . . . .	263
Showing LTFS Progress in DMF Manager . . . . .	264
Configuring LTFS using DMF Manager . . . . .	265
Mounting an Unassigned Tape for LTFS Use in DMF Manager . . . . .	267
Unmounting an LTFS Tape in DMF Manager . . . . .	269

<b>7. DMF Configuration File</b>	<b>271</b>
Configuration File Overview	272
Object Definitions	272
Stanza Format	274
Units of Measure	275
Device Block-Size Defaults and Bandwidth	276
base Object	277
base Object Name	277
base Object Summary	278
base Object Parameters	278
base Object Examples	286
base Object for Basic DMF	287
base Object for Parallel DMF	287
base Object for Parallel DMF in an HA Cluster	288
dmdaemon Object	289
dmdaemon Object Name	289
dmdaemon Object Summary	289
dmdaemon Object Parameters	290
dmdaemon Object Example	293
node Object	294
node Object Name	294
node Object Summary	294
node Object Parameters	294
node Object Examples	297
node Objects for Parallel DMF	297
node Objects for Parallel DMF in an HA Cluster	298
services Object	299

services Object Name . . . . .	299
services Object Summary . . . . .	299
services Object Parameters . . . . .	300
services Object Examples . . . . .	301
services object for Parallel DMF . . . . .	301
services Object for Parallel DMF in an HA Cluster . . . . .	303
taskgroup Object . . . . .	304
Overview of the Tasks . . . . .	304
Backup Tasks . . . . .	309
taskgroup Object Name . . . . .	310
taskgroup Object Summary . . . . .	310
taskgroup Object Parameters . . . . .	312
taskgroup Object Examples . . . . .	332
taskgroup Object Example for Integrated Backups . . . . .	332
taskgroup Object Example for Tape Backups . . . . .	333
taskgroup Object Example for Disk Backups . . . . .	335
taskgroup Object Example for Disk Backups Using NFS . . . . .	335
taskgroup Object Example for Daemon Tasks . . . . .	336
taskgroup Object Example for Node Tasks . . . . .	339
taskgroup Object Example for Fast-Mount Cache Tasks . . . . .	339
taskgroup Object Example for Fast-Mount Cache Tasks Using File Retention . . . . .	340
taskgroup Object Example for Periodic dmmigrate Tasks . . . . .	341
taskgroup Object Example for Removing Alerts and Performance Records . . . . .	341
dumpgroup Object . . . . .	342
dumpgroup Object Name . . . . .	342
dumpgroup Object Summary . . . . .	343

dumpgroup Object Parameters . . . . .	343
dumpgroup Object Example for Integrated Backups . . . . .	345
device Object . . . . .	347
device Object Name . . . . .	348
device Object Summary . . . . .	348
device Object Parameters . . . . .	348
filesystem Object . . . . .	350
filesystem Object Name . . . . .	350
filesystem Object Summary . . . . .	351
filesystem Object Parameters . . . . .	351
filesystem Object Examples . . . . .	360
filesystem Object Example for a Managed Filesystem . . . . .	361
filesystem Object Example for Integrated Backups . . . . .	362
filesystem Object Example for Incremental Backups that Restrict File Size . . . . .	362
filesystem Object for DMF Direct Archiving . . . . .	363
policy Object . . . . .	364
Functions of policy Parameters . . . . .	365
Automated Space-Management Overview . . . . .	365
File Weighting Overview . . . . .	365
MSP/VG Selection Overview . . . . .	366
Rules for policy Parameters . . . . .	366
Managed Filesystem Rules . . . . .	366
DCM MSP STORE_DIRECTORY Rules . . . . .	367
policy Object Name . . . . .	368
Managed Filesystem policy Parameters . . . . .	368
policy Object Summary for a Managed Filesystem . . . . .	368
Automated Space-Management Parameters for a Managed Filesystem . . . . .	369

File Weighting Parameters for a Managed Filesystem . . . . .	371
MSP/VG Selection Parameters for a Managed Filesystem . . . . .	374
DCM MSP STORE_DIRECTORY policy Parameters . . . . .	375
policy Object Summary for a DCM MSP . . . . .	376
Automated Space-Management Parameters for a DCM MSP STORE_DIRECTORY . . . . .	376
File Weighting Parameters for a DCM MSP STORE_DIRECTORY . . . . .	378
VG Selection Parameters for a DCM MSP STORE_DIRECTORY . . . . .	380
when Clause . . . . .	380
ranges Clause . . . . .	383
policy Configuration Examples . . . . .	385
Automated Space-Management Example . . . . .	386
Automated Space-Management Using Ranges Example . . . . .	387
MSP/VG Selection Example . . . . .	388
policy Examples for Integrated Backups . . . . .	389
fastmountcache Object . . . . .	390
fastmountcache Object Name . . . . .	390
fastmountcache Object Summary . . . . .	390
fastmountcache Object Parameters . . . . .	390
fastmountcache Object Examples . . . . .	391
fastmountcache with an MG . . . . .	391
fastmountcache with a Mix of Members . . . . .	391
Objects Related to an LS . . . . .	392
libraryserver Object . . . . .	392
libraryserver Object Name . . . . .	393
libraryserver Object Summary . . . . .	393
libraryserver Object Parameters . . . . .	393
drivegroup Object . . . . .	395

drivegroup Object Name . . . . .	396
drivegroup Object Summary . . . . .	396
drivegroup Object Parameters . . . . .	397
volumegroup Object . . . . .	410
volumegroup Object Name . . . . .	410
volumegroup Object Summary . . . . .	410
volumegroup Object Parameters . . . . .	411
volumegroup Object Example with an AG . . . . .	423
volumegroup Object Example Overriding drivegroup Settings . . . . .	426
migrategroup Object . . . . .	426
migrategroup Object Name . . . . .	427
migrategroup Object Summary . . . . .	427
migrategroup Object Parameters . . . . .	427
migrategroup Object Example with Multiple MGs . . . . .	431
<b>Single migrategroup Object Example Using the ROUND_ROBIN_BY_BYTES Strategy</b> . . . . .	431
migrategroup Object Example Using the ROUND_ROBIN_BY_FILES Strategy . . . . .	431
resourcescheduler Object . . . . .	432
resourcescheduler Object Name . . . . .	432
resourcescheduler Object Summary . . . . .	432
resourcescheduler Object Parameters . . . . .	432
resourcewatcher Object . . . . .	433
resourcewatcher Object Name . . . . .	434
resourcewatcher Object Summary . . . . .	434
resourcewatcher Object Parameters . . . . .	434
allocationgroup Object . . . . .	434
allocationgroup Object Name . . . . .	435



allocationgroup Object Summary . . . . .	435
allocationgroup Object Parameters . . . . .	435
Examples of Configuring an LS . . . . .	436
Example: LS with a Resource Watcher, Two DGs, and an AG . . . . .	436
Example: LS for Fast-Mount Cache . . . . .	439
LS Tasks . . . . .	441
Overview of LS Tasks . . . . .	442
LS taskgroup Object with One VG . . . . .	443
LS taskgroup Object with Multiple VGs . . . . .	444
LS Database Records . . . . .	444
m <sub>SP</sub> Objects . . . . .	446
m <sub>SP</sub> Object Name . . . . .	446
NAME_FORMAT Details . . . . .	446
m <sub>SP</sub> Object for a Cloud MSP . . . . .	448
m <sub>SP</sub> Object Summary for a Cloud MSP . . . . .	449
m <sub>SP</sub> Object Parameters for a Cloud MSP . . . . .	449
m <sub>SP</sub> Object Example for an S3 Cloud MSP . . . . .	453
m <sub>SP</sub> Object Example for a Scalify Cloud MSP . . . . .	454
m <sub>SP</sub> Object for an FTP MSP . . . . .	455
m <sub>SP</sub> Object Summary for an FTP MSP . . . . .	455
m <sub>SP</sub> Object Parameters for an FTP MSP . . . . .	455
m <sub>SP</sub> Object Example for an FTP MSP . . . . .	458
m <sub>SP</sub> Object for a DCM MSP . . . . .	459
m <sub>SP</sub> Object Summary for a DCM MSP . . . . .	460
m <sub>SP</sub> Object Parameters for a DCM MSP . . . . .	460
m <sub>SP</sub> Object Example for a DCM MSP . . . . .	465
m <sub>SP</sub> Object for a Disk MSP . . . . .	466

m <sub>SP</sub> Object Summary for a Disk MSP . . . . .	467
m <sub>SP</sub> Object Parameters for a Disk MSP . . . . .	467
m <sub>SP</sub> Object Example for a Disk MSP . . . . .	470
Summary of the Configuration-File Parameters . . . . .	472
<b>8. Parallel DMF Configuration . . . . .</b>	<b>485</b>
Parallel DMF Configuration Procedure . . . . .	485
Determining the State of Parallel Data-Mover Nodes . . . . .	488
Disabling Parallel Data-Mover Nodes . . . . .	489
Reenabling Parallel Data-Mover Nodes . . . . .	489
<b>9. Mounting Service Configuration Tasks . . . . .</b>	<b>491</b>
OpenVault Configuration Tasks . . . . .	491
Configure the OpenVault Server . . . . .	492
Configure OpenVault for DMF Use . . . . .	494
Configure OpenVault for Each Parallel Data-Mover Node . . . . .	498
Configure OpenVault on the DMF Server If on a Different Host . . . . .	502
Configure OpenVault for a Drive Group . . . . .	502
TMF Configuration Tasks . . . . .	505
<b>10. Message Log Files . . . . .</b>	<b>507</b>
<b>11. Automated Space Management . . . . .</b>	<b>509</b>
The dmfsmon Daemon and dmfsfree Command . . . . .	509
Generating the Candidate List . . . . .	510
Selection of Migration Candidates . . . . .	511
Space Management and the DCM MSP . . . . .	513
Automated Space Management Log File . . . . .	513

<b>12. The DMF Daemon</b>	<b>515</b>
Daemon Processing	515
Daemon Database and dmdadm	517
Overview of the Daemon Database and dmdadm	517
dmdadm Directives	518
dmdadm Field and Format Keywords	520
dmdadm Text Field Order	524
Daemon Logs and Journals	525
<b>13. The DMF Lock Manager</b>	<b>527</b>
dmlockmgr Communication and Log Files	527
dmlockmgr Individual Transaction Log Files	529
<b>14. Library Servers and Media-Specific Processes</b>	<b>531</b>
LS Operations	532
LS Overview	532
LS Directories	533
Media Concepts	534
CAT Records	536
VOL Records	537
LS Journals	538
LS Logs	539
Volume Merging	543
dmcatadm Command	544
dmcatadm Directives	545
dmcatadm Keywords	548
dmcatadm Text Field Order	553
dmvoladm Command	554
dmvoladm Overview	554

dmvoladm Directives . . . . .	555
dmvoladm Field Keywords . . . . .	557
dmvoladm Text Field Order . . . . .	563
dmvoladm Examples . . . . .	564
dmatread Command . . . . .	567
dmatsnf Command . . . . .	568
dmaudit verifymsp Command . . . . .	568
Cloud MSP . . . . .	569
Cloud MSP Overview . . . . .	569
Cloud MSP Processing of Requests . . . . .	569
Cloud MSP Activity Log . . . . .	571
Cloud MSP Messages . . . . .	571
Cloud MSP Limitations and Considerations . . . . .	572
FTP MSP . . . . .	573
FTP MSP Overview . . . . .	573
FTP MSP Processing of Requests . . . . .	573
FTP MSP Activity Log . . . . .	575
FTP MSP Messages . . . . .	576
FTP MSP Limitations and Considerations . . . . .	576
Disk MSP . . . . .	576
Disk MSP Overview . . . . .	577
Disk MSP Processing of Requests . . . . .	577
Disk MSP Activity Log . . . . .	578
DCM MSP . . . . .	579
dmdskvfy Command . . . . .	579
Moving Migrated Data . . . . .	579
LS Error Analysis and Avoidance . . . . .	580
LS Drive Scheduling . . . . .	582

LS Status Monitoring . . . . . 582

**15. DMF Maintenance . . . . . 585**

Retaining Old DMF Daemon Log Files . . . . . 585

Retaining Old DMF Daemon Journal Files . . . . . 586

Cleaning Up Obsolete Database Entries . . . . . 586

Using `dmfill` . . . . . 587

Viewing Drive Statistics . . . . . 587

Temporarily Disabling Components . . . . . 589

    Disable an OpenVault DCP . . . . . 590

    Disable an OpenVault Drive . . . . . 591

    Disable an OpenVault Library . . . . . 592

    Disable a TMF Drive . . . . . 594

    Stop the COPAN VTL . . . . . 595

**16. DMF SOAP Server . . . . . 597**

Overview of DMF SOAP . . . . . 597

Accessing the DMF SOAP and WSDL . . . . . 599

Starting and Stopping the DMF SOAP Service . . . . . 600

    Starting the `dmfsoap` Service . . . . . 601

    Preventing Automatic Start of `dmfsoap` After Reboot . . . . . 601

    Explicitly Stopping `dmfsoap` . . . . . 601

Security/Authentication . . . . . 601

DMF SOAP Sample Client Files . . . . . 601

**17. DMF Queue Viewing . . . . . 605**

QView Tab and the `dmqview` Command . . . . . 605

Taking a Snapshot of the DMF Requests . . . . . 606

Queue Reports . . . . .	606
Summary Report and Corresponding State Reports . . . . .	606
Composite Reports . . . . .	609
Canceling a Request . . . . .	613
Reprioritizing a Request . . . . .	615
Modifying the Report Output . . . . .	615
Modifying the QView Display . . . . .	615
Modifying the dmqview Output . . . . .	617
Example of Queue-Related Tasks . . . . .	619
Database Tables and Fields . . . . .	620
PostgreSQL Database Tables . . . . .	621
Fields for the Chunk Database Table . . . . .	624
Fields for the Connect Database Table . . . . .	625
Fields for the Daemon Request Database Table . . . . .	626
Fields for the Filesys Database Table . . . . .	627
Fields for the Mover Database Table . . . . .	628
Fields for the MSP Request Database Table . . . . .	629
<b>18. SGI LTFS . . . . .</b>	<b>631</b>
SGI LTFS Features . . . . .	631
SGI LTFS Requirements . . . . .	632
Best Practices for SGI LTFS . . . . .	632
Avoid Parallel Use . . . . .	632
Verify Copies are Present Before Deleting Originals . . . . .	632
Ensure that Files are Online Before Copying to LTFS . . . . .	633
SGI LTFS Configuration . . . . .	633
sgi-ltfs.conf File Format . . . . .	633
sgi-ltfs.conf Parameters . . . . .	634

<code>sgi-ltfs.conf</code> Examples . . . . .	635
Borrowing Drives (Simple) . . . . .	635
Borrowing Drives (More Complex) . . . . .	636
Using the LTFS Drive . . . . .	636
<code>sgi-ltfs</code> Command Examples . . . . .	637
Reading an LTFS Tape . . . . .	637
Reserving a Drive and Preparing a New LTFS Tape . . . . .	638
Reading a T10000C-Formatted Tape on a T10000D Drive . . . . .	639
Reformatting a T100002 Tape . . . . .	639
<b>19. Troubleshooting . . . . .</b>	<b>641</b>
Replacing a Bad DMF Copy with a Good DMF Copy . . . . .	642
Restoring Files from Backups . . . . .	643
Overview of Restoring Files . . . . .	643
Ensuring Accuracy with <code>xfsdump</code> . . . . .	645
Backing Up and Restoring Files without the DMF Scripts . . . . .	645
Filesystem Consistency with <code>xfsrestore</code> . . . . .	646
Recovery and Restoration of DMF Database . . . . .	646
Database Backups . . . . .	647
Database Recovery Procedure . . . . .	647
Database Restore Procedure for Integrated Backups . . . . .	650
Backup Consistency Errors . . . . .	650
Disaster Recovery Procedures . . . . .	650
Disaster Recovery for Basic DMF without HA . . . . .	651
Disaster Recovery for Parallel DMF . . . . .	655
Disaster Recovery for DMF with HA . . . . .	657
Filesystem Errors . . . . .	658

Unable to Use the <code>dmi</code> Mount Option . . . . .	660
EOT Error . . . . .	660
Tape Drive Not Claimed by <code>ts</code> . . . . .	660
Drive Entry Does Not Correspond to an Existing Drive (OpenVault) . . . . .	660
Drive Does Not Exist (TMF) . . . . .	661
No Usable Drives . . . . .	661
DMF Manager Errors . . . . .	666
DMF Statistics are Unavailable Error Message . . . . .	666
DMF Statistics Graphs are Empty . . . . .	668
OpenVault Library Is Missing . . . . .	668
Delay In Accessing Files in an SMB/CIFS Network Share . . . . .	668
Operations Timeout or Abort on Windows . . . . .	669
Windows Explorer Hangs . . . . .	669
Poor Migration Performance . . . . .	669
Poor Recall Performance . . . . .	669
Remote Connection Failures . . . . .	670
<code>yast2</code> Disk Space Warning . . . . .	670
Linux CXFS Clients Cannot Mount Managed Filesystems . . . . .	670
Mount Errors for a Drive . . . . .	671
Verifying the Integrity of Library Server Volumes . . . . .	672
<code>dmemptytape</code> Process Did Not Complete . . . . .	674
DMF Database Server Startup Issues . . . . .	674
Using SGI Knowledgebase . . . . .	675
Reporting Problems to SGI . . . . .	675
<b>Appendix A. Messages . . . . .</b>	<b>677</b>
<code>dmcatadm</code> Message Interpretation . . . . .	677



dmvoladm Message Interpretation . . . . . 679

**Appendix B. DMF User Library libdmfusr.so . . . . . 681**

Overview of the Distributed Command Feature and libdmfusr.so . . . . . 681

Considerations for IRIX® . . . . . 684

libdmfusr.so Library Versioning . . . . . 684

libdmfusr.so.2 Data Types . . . . . 686

    DmuAllErrors\_t . . . . . 686

    DmuAttr\_t . . . . . 687

    DmuByteRange\_t . . . . . 688

    DmuByteRanges\_t . . . . . 689

    DmuCompletion\_t . . . . . 692

    DmuCopyRange\_t . . . . . 693

    DmuCopyRanges\_t . . . . . 693

    DmuErrorHandler\_f . . . . . 694

    DmuErrInfo\_t . . . . . 695

    DmuError\_t . . . . . 695

    DmuEvents\_t . . . . . 696

    DmuFhandle\_t . . . . . 696

    DmuFsysInfo\_t . . . . . 696

    DmuFullRegbuf\_t . . . . . 697

    DmuFullRegion\_t . . . . . 698

    DmuFullstat\_t . . . . . 698

    DmuFullstat\_2\_t . . . . . 699

    DmuOperandType\_t . . . . . 700

    DmuPriority\_t . . . . . 701

    DmuRegion\_t . . . . . 701

    DmuRegionbuf\_t . . . . . 701

    DmuReplyOrder\_t . . . . . 702

DmuReplyType_t . . . . .	702
DmuSeverity_t . . . . .	702
DmuVolGroup_t . . . . .	703
DmuVolGroups_t . . . . .	703
<b>User-Accessible API Subroutines for libdmfusr.so.2 . . . . .</b>	<b>705</b>
<b>Context-Manipulation Subroutines . . . . .</b>	<b>705</b>
DmuCreateContext() Subroutine . . . . .	705
DmuChangedDirectory() Subroutine . . . . .	707
DmuDestroyContext() Subroutine . . . . .	707
<b>Filesystem-Information Subroutine . . . . .</b>	<b>708</b>
<b>DMF File-Request Subroutines . . . . .</b>	<b>709</b>
Copy File Requests . . . . .	710
Archive File Requests . . . . .	712
Fullstat Requests . . . . .	714
Put File Requests . . . . .	717
Get File Requests . . . . .	720
Setprojid File Requests . . . . .	723
Settag File Requests . . . . .	725
<b>Request-Completion Subroutines . . . . .</b>	<b>727</b>
DmuAwaitReplies() Subroutine . . . . .	728
DmuFullstatCompletion() Subroutine . . . . .	729
DmuGetNextReply() Subroutine . . . . .	730
DmuGetThisReply() Subroutine . . . . .	732
<b>Appendix C. Site-Defined Policy Subroutines and the sitelib.so Library . . . . .</b>	<b>735</b>
Overview of Site-Defined Policy Subroutines . . . . .	735
Getting Started with Custom Subroutines . . . . .	736
Considerations for Writing Custom Subroutines . . . . .	738

---

<b>sitelib.so Data Types</b>	739
DmaContext_t	739
DmaFrom_t	740
DmaIdentity_t	740
DmaLogLevel_t	742
DmaRealm_t	742
DmaRecallType_t	742
SiteFncMap_t	743
<b>Site-Defined Policy Subroutines</b>	743
SiteArchiveFile()	743
SiteCreateContext()	745
SiteDestroyContext()	746
SiteKernRecall()	746
SitePutFile()	748
SiteWhen()	750
<b>Helper Subroutines for sitelib.so</b>	752
DmaConfigStanzaExists()	752
DmaGetConfigBool()	753
DmaGetConfigFloat()	754
DmaGetConfigInt()	755
DmaGetConfigList()	756
DmaGetConfigStanza()	757
DmaGetConfigString()	758
DmaGetContextFlags()	759
DmaGetCookie()	759
DmaGetDaemonMigGroups()	760
DmaGetDaemonVolAndMigGroups()	760
DmaGetDaemonVolGroups()	761

DmaGetMigGroupMembers()	761
DmaGetProgramIdentity()	762
DmaGetUserIdentity()	762
DmaSendLogFmtMessage()	763
DmaSendUserFmtMessage()	764
DmaSetCookie()	765
<b>Appendix D. Third-Party Backup Package Configuration</b>	<b>767</b>
Using Third-Party Backup Packages	767
Overview of Using Third-Party Backup Packages	767
do_predump.sh Script	768
DUMP_DATABASE_COPY Configuration File Parameter in the taskgroup Object	768
Hard Deletes and Third-Party Backup	769
Unprivileged Users	769
Procedure to Use a Third-Party Backup Package	769
ASG-Time Navigator	769
taskgroup Object Example for Third-Party Backups	770
<b>Appendix E. Converting from IRIX DMF to Linux<sup>®</sup> DMF</b>	<b>773</b>
<b>Appendix F. Converting from TMF to OpenVault</b>	<b>777</b>
<b>Appendix G. Considerations for Partial-State Files</b>	<b>779</b>
Performance Cost Due to Lack of Linux Kernel Support	779
Inability to Fulfill Exact Byte Range Requests	780
<b>Appendix H. Case Study: Impact of Zone Size on Tape Performance</b>	<b>781</b>
<b>Appendix I. Historical Feature Information</b>	<b>783</b>

End of Life for the Tape Autoloader API with DMF 2.6.3 . . . . . 783

DMF Directory Structure Prior to DMF Release 2.8 . . . . . 783

End of Life for the Tape MSP after DMF 3.0 . . . . . 784

DMF User Library (libdmfusr.so) Update in DMF 3.1 . . . . . 784

Downgrading and the Site-Tag Feature Introduced in DMF 3.1 . . . . . 785

Downgrading and the Partial-State File Feature Introduced in DMF 3.2 . . . . . 786

dmaudit(8) Changes in DMF 3.2 . . . . . 787

Logfile Changes in DMF 3.2 . . . . . 787

Possible DMF Database Lock Manager Incompatibility On Upgrades as of DMF 3.8.3 . . . 788

**Appendix J. Using `dmmaint` to Install Licenses and Configure DMF . . . 789**

Overview of `dmmaint` . . . . . 789

Installing the DMF License . . . . . 791

Using `dmmaint` to Define the Configuration File . . . . . 791

**Glossary . . . . . 793**

**Index . . . . . 853**



---

## Figures

<b>Figure 1-1</b>	DMF Cycle . . . . .	2
<b>Figure 1-2</b>	Free-Space Minimum Threshold . . . . .	4
<b>Figure 1-3</b>	DMF Manager . . . . .	11
<b>Figure 1-4</b>	DMF Methods: Before Migrating . . . . .	17
<b>Figure 1-5</b>	DMF Methods: After Migrating Data and Freeing Space . . . . .	18
<b>Figure 1-6</b>	Two Tiers: Migrating File Data . . . . .	20
<b>Figure 1-7</b>	Two Tiers: Freeing and Recalling File Data . . . . .	21
<b>Figure 1-8</b>	DCM MSP: Migrating File Data . . . . .	22
<b>Figure 1-9</b>	DCM MSP: Freeing and Recalling File Data . . . . .	23
<b>Figure 1-10</b>	Fast-Mount Cache: Migrating File Data . . . . .	25
<b>Figure 1-11</b>	Fast-Mount Cache: Freeing and Recalling File Data . . . . .	26
<b>Figure 1-12</b>	Recall Order . . . . .	29
<b>Figure 1-13</b>	Basic DMF Product in an NFS Environment . . . . .	34
<b>Figure 1-14</b>	Basic DMF Product in a CXFS Environment . . . . .	34
<b>Figure 1-15</b>	Parallel DMF in a CXFS Environment . . . . .	36
<b>Figure 1-16</b>	Basic DMF Architecture . . . . .	39
<b>Figure 1-17</b>	LS Architecture . . . . .	40
<b>Figure 2-1</b>	DMF Licenses . . . . .	69
<b>Figure 2-2</b>	Data that Counts Towards the Capacity License . . . . .	71
<b>Figure 2-3</b>	Licenses . . . . .	76
<b>Figure 3-1</b>	Components Required by the DMF System . . . . .	90
<b>Figure 3-2</b>	Archiving Files from an Archive Filesystem to Secondary Storage . . . . .	120
<b>Figure 3-3</b>	DMF Direct Archiving . . . . .	120

<b>Figure 4-1</b>	DMF Integrated Backups . . . . .	152
<b>Figure 4-2</b>	Integrated Backup Directory Structures . . . . .	153
<b>Figure 4-3</b>	Order of Precedence for Dump Parameters . . . . .	155
<b>Figure 6-1</b>	DMF Manager Overview Panel . . . . .	194
<b>Figure 6-2</b>	Overview Key to Symbols . . . . .	199
<b>Figure 6-3</b>	Displaying Information About an Icon . . . . .	200
<b>Figure 6-4</b>	“What Is ...” Information . . . . .	201
<b>Figure 6-5</b>	DMF Manager Overview Preferences Panel . . . . .	202
<b>Figure 6-6</b>	Adding a License Key in DMF Manager . . . . .	204
<b>Figure 6-7</b>	Data Under Management and Data Charged to the Licenses . . . . .	206
<b>Figure 6-8</b>	DMF Capacity . . . . .	207
<b>Figure 6-9</b>	Remaining DMF Capacity . . . . .	209
<b>Figure 6-10</b>	Temporary Workspace for a Preconfigured DCM MSP Sample . . . . .	213
<b>Figure 6-11</b>	Naming a Copied Object . . . . .	216
<b>Figure 6-12</b>	DMF Configuration Parameters in DMF Manager . . . . .	220
<b>Figure 6-13</b>	DMF Manager Showing Problems in the DMF System . . . . .	221
<b>Figure 6-14</b>	Alerts Key . . . . .	222
<b>Figure 6-15</b>	Unfiltered Alerts . . . . .	223
<b>Figure 6-16</b>	DMF Manager Alerts Panel and Help Information . . . . .	224
<b>Figure 6-17</b>	Define Filters for Alerts . . . . .	225
<b>Figure 6-18</b>	Adding Another Filter Rule . . . . .	226
<b>Figure 6-19</b>	Filtered Alerts . . . . .	227
<b>Figure 6-20</b>	Relationships Among DMF Components . . . . .	228
<b>Figure 6-21</b>	DMF Manager Volumes Panel . . . . .	229
<b>Figure 6-22</b>	Changing Hold Flags in DMF Manager . . . . .	231
<b>Figure 6-23</b>	DMF Activity . . . . .	238



<b>Figure 6-24</b>	Filesystem Resource Graph . . . . .	241
<b>Figure 6-25</b>	Drive Group Resource Information . . . . .	243
<b>Figure 6-26</b>	Volume Group Resource Graph . . . . .	245
<b>Figure 6-27</b>	DCM MSP Resource Graph . . . . .	247
<b>Figure 6-28</b>	DMF I/O Custom Chart Creation . . . . .	250
<b>Figure 6-29</b>	DMF I/O . . . . .	251
<b>Figure 6-30</b>	Node State . . . . .	252
<b>Figure 6-31</b>	Node Details . . . . .	254
<b>Figure 6-32</b>	Restoring a File from <b>Available Dumps (Integrated Method)</b> . . . . .	256
<b>Figure 6-33</b>	Restoring a Filesystem Component using DMF Manager (Integrated Backups)	259
<b>Figure 6-34</b>	Restoring a Filesystem Component using DMF Manager (Nonintegrated Backups) . . . . .	261
<b>Figure 6-35</b>	LTFS Information . . . . .	264
<b>Figure 6-36</b>	LTFS Messages . . . . .	265
<b>Figure 6-37</b>	Configuring LTFS in DMF Manager . . . . .	266
<b>Figure 6-38</b>	Mounting an LTFS Tape . . . . .	268
<b>Figure 6-39</b>	Unmounting an LTFS Tape . . . . .	270
<b>Figure 7-1</b>	Concepts of Free-Space Minimum and Target . . . . .	370
<b>Figure 11-1</b>	Relationship of Automated Space Management Targets . . . . .	512
<b>Figure 14-1</b>	Media Concepts . . . . .	536
<b>Figure 16-1</b>	DMF SOAP Operation Documentation . . . . .	598
<b>Figure 16-2</b>	WSDL Definition . . . . .	600
<b>Figure 17-1</b>	QView: Summary Reports . . . . .	607
<b>Figure 17-2</b>	Processing Report . . . . .	612
<b>Figure 17-3</b>	Canceling a Request . . . . .	613
<b>Figure 17-4</b>	Fields Available for Display by a QView <b>Active</b> Report . . . . .	616
<b>Figure 19-1</b>	Disaster Recovery . . . . .	652



---

## Tables

<b>Table 1-1</b>	DMF Administrative and Store Directories . . . . .	45
<b>Table 2-1</b>	Data-Capacity License Amounts . . . . .	68
<b>Table 3-1</b>	DMF Exclusive Use of Filesystems . . . . .	96
<b>Table 3-2</b>	Minimum Sizes for DMF Directories . . . . .	97
<b>Table 3-3</b>	Required and Suggested Mount Options . . . . .	99
<b>Table 3-4</b>	Tools to Load Volumes to an Existing DMF/OpenVault Environment . . . . .	132
<b>Table 5-1</b>	Default Maximum File Regions for XFS and CXFS Filesystems . . . . .	172
<b>Table 6-1</b>	DMF Manager Panel Menus . . . . .	193
<b>Table 7-1</b>	Automated Maintenance Task Summary . . . . .	305
<b>Table 7-2</b>	Dump Parameters According to DMF Backup Method . . . . .	309
<b>Table 7-3</b>	NAME_FORMAT Strings . . . . .	447
<b>Table 7-4</b>	Configuration Parameters . . . . .	472
<b>Table 10-1</b>	Message Types and Levels . . . . .	508
<b>Table 13-1</b>	dmlockmgr Token Files . . . . .	528
<b>Table 17-1</b>	Summary Reports . . . . .	608
<b>Table 17-2</b>	Composite Reports . . . . .	609
<b>Table 17-3</b>	PostgreSQL Database Tables . . . . .	622
<b>Table 17-4</b>	Chunk Fields . . . . .	624
<b>Table 17-5</b>	Connect Fields . . . . .	625
<b>Table 17-6</b>	Daemon Request Fields . . . . .	626
<b>Table 17-7</b>	Filesys Fields . . . . .	627
<b>Table 17-8</b>	Mover Fields . . . . .	628
<b>Table 17-9</b>	MSP Request Fields . . . . .	629



---

## Examples

<b>Example 7-1</b>	base Object for Basic DMF . . . . .	287
<b>Example 7-2</b>	base Object for Parallel DMF . . . . .	287
<b>Example 7-3</b>	base Object for Parallel DMF in an HA Cluster . . . . .	288
<b>Example 7-4</b>	dmdaemon object . . . . .	293
<b>Example 7-5</b>	node Objects for Parallel DMF . . . . .	297
<b>Example 7-6</b>	node Objects for Parallel DMF in an HA Cluster . . . . .	298
<b>Example 7-7</b>	services object for Parallel DMF . . . . .	301
<b>Example 7-8</b>	services Object for Parallel DMF in an HA Cluster . . . . .	303
<b>Example 7-9</b>	taskgroup Object for Integrated Backups . . . . .	332
<b>Example 7-10</b>	taskgroup Object for Tape Backups . . . . .	333
<b>Example 7-11</b>	taskgroup Object for Disk Backups . . . . .	335
<b>Example 7-12</b>	taskgroup Object for Disk Backups Using NFS . . . . .	335
<b>Example 7-13</b>	taskgroup Object for Daemon Tasks . . . . .	336
<b>Example 7-14</b>	taskgroup Object for Node Tasks with Parallel DMF . . . . .	339
<b>Example 7-15</b>	taskgroup Object for Fast-Mount Cache . . . . .	339
<b>Example 7-16</b>	taskgroup Object for Fast-Mount Cache Using File Retention . . . . .	340
<b>Example 7-17</b>	taskgroup Object for Periodic dmmigrate Example . . . . .	341
<b>Example 7-18</b>	taskgroup Object for Removing Alerts and Performance Records . . . . .	341
<b>Example 7-19</b>	dumpgroup Object Example for Integrated Backups . . . . .	345
<b>Example 7-20</b>	filesystem Object for a Managed Filesystem . . . . .	361
<b>Example 7-21</b>	filesystem Object for Integrated Backups . . . . .	362
<b>Example 7-22</b>	filesystem Objects for Incremental Backups that Restrict File Size . . . . .	362
<b>Example 7-23</b>	filesystem Object for DMF Direct Archiving . . . . .	364

<b>Example 7-24</b>	<code>policy</code> Object for Automated Space Management . . . . .	386
<b>Example 7-25</b>	<code>policy</code> Object for Automated Space Management Using Ranges . . . . .	387
<b>Example 7-26</b>	<code>policy</code> Object for an MSP/VG . . . . .	388
<b>Example 7-27</b>	<code>policy</code> Objects for Integrated Backups . . . . .	389
<b>Example 7-28</b>	<code>fastmountcache</code> with an MG . . . . .	391
<b>Example 7-29</b>	<code>fastmountcache</code> with a Mix of Members . . . . .	391
<b>Example 7-30</b>	<code>volume</code> group example with an AG . . . . .	424
<b>Example 7-31</b>	<code>migrate</code> group Object with Multiple MGs . . . . .	431
<b>Example 7-32</b>	Single <code>migrate</code> group Using the <code>ROUND_ROBIN_BY_BYTES</code> Strategy . . . . .	431
<b>Example 7-33</b>	<code>migrate</code> group Using the <code>SEQUENTIAL</code> Strategy . . . . .	431
<b>Example 7-34</b>	<code>library</code> server Object with a Resource Watcher, Two DGs, and an AG . . . . .	436
<b>Example 7-35</b>	<code>library</code> server and Associated Objects for Fast-Mount Cache . . . . .	439
<b>Example 7-36</b>	<code>task</code> group Object for LS with One VG . . . . .	443
<b>Example 7-37</b>	<code>m</code> sp Object for an S3 Cloud MSP . . . . .	453
<b>Example 7-38</b>	<code>m</code> sp Object for a Scality Cloud MSP . . . . .	454
<b>Example 7-39</b>	<code>m</code> sp Object for an FTP MSP . . . . .	458
<b>Example 7-40</b>	Configuration Stanzas Associated with a DCM MSP . . . . .	465
<b>Example 7-41</b>	<code>m</code> sp Object for a Disk MSP . . . . .	470
<b>Example 14-1</b>	LS Statistics Messages . . . . .	541
<b>Example 14-2</b>	<code>dmcatadm list</code> Directive . . . . .	552
<b>Example 14-3</b>	<code>dmvoladm update</code> Directive . . . . .	564
<b>Example 14-4</b>	<code>dmvoladm list</code> Directive to Show Information for Multiple VSNs . . . . .	564
<b>Example 14-5</b>	<code>dmvoladm list</code> Directive to Show Volumes with a Specific Flag . . . . .	564
<b>Example 14-6</b>	<code>dmvoladm list</code> Directive to Customize a List of Fields . . . . .	565
<b>Example 14-7</b>	<code>dmvoladm list</code> Directive to Show Multiple Flags . . . . .	566
<b>Example 14-8</b>	<code>dmvoladm list</code> Directive to Display Volumes Assigned to a VG . . . . .	567
<b>Example 14-9</b>	Restoring Hard-deleted Files Using <code>dmatread</code> . . . . .	567

**Example 19-1** Database Recovery . . . . . 649

**Example D-1** taskgroup Object for Third-Party Backups . . . . . 770

**Example E-1** IRIX to Linux Conversion (Single LS) . . . . . 776





---

## Procedures

<b>Procedure 5-1</b>	Configuring the DMF Environment . . . . .	165
<b>Procedure 5-2</b>	Configuring the Daemon Database Record Length . . . . .	173
<b>Procedure 7-1</b>	Creating LS Database Records . . . . .	445
<b>Procedure 8-1</b>	Configuring Parallel DMF . . . . .	485
<b>Procedure 9-1</b>	Configuring OpenVault for a Drive Group . . . . .	502
<b>Procedure 19-1</b>	Recovering the Databases . . . . .	648
<b>Procedure E-1</b>	Converting from IRIX DMF to Linux DMF . . . . .	773



---

## About This Guide

This guide tells you how to configure and administer the SGI® DMF tiered-storage virtualization environment.

### Related Publications

For information about this release, see the SGI InfiniteStorage™ Software Platform (ISSP) release notes (`README.txt`) and the DMF release notes (`README_DMF.txt`).

The *DMF 6 Filesystem Audit Guide* describes how to solve problems with DMF should you encounter them.

Also see:

- *COPAN MAID for DMF Quick Start Guide*
- *CXFS 7 Administrator Guide for SGI InfiniteStorage*
- *CXFS 7 Client-Only Guide for SGI InfiniteStorage*
- *High Availability Guide for SGI InfiniteStorage*
- *OpenVault Administrator Guide for SGI InfiniteStorage*
- *SGI 400 VTL for DMF Quick Start Guide*
- *TMF 6 Administrator Guide for SGI InfiniteStorage*
- *XVM Volume Manager Administrator Guide*
- Scality RING documentation provided at:

[docs.scality.com](http://docs.scality.com)

---

**Note:** You must enter your Scality username and password

---

- Amazon Simple Storage Service (S3) documentation provided at:  
<http://aws.amazon.com/s3/>

## Man Pages

DMF provides man pages for user commands, file formats, and administrator commands.

### User Commands

Man pages are available for the following DMF user commands:

dmarchive(1)	dmdu(1)	dmls(1)	dmversion(1)
dmattr(1)	dmfind(1)	dmput(1)	sgi_dmdu(1)
dmcapacity(1)	dmget(1)	dmtag(1)	sgi_dmfind(1)
dmcopy(1)			sgi_dmls(1)

### File Formats

Man pages are available for the following DMF file formats:

dmf.conf(5)  
trxj(5)

### Administrator Commands

Man pages are available for the following DMF administrator commands:

dmatread(8)	dmdbrecover(8)	dmfsfree(8)	dmscanfs(8)
dmatsnf(8)	dmdidle(8)	dmfsmon(8)	dmselect(8)
dmatvfy(8)	dmdskfree(8)	dmhdelete(8)	dmsnap(8)
dmaudit(8)	dmdskvfy(8)	dmlockmgr(8)	dmsort(8)
dmcatadm(8)	dmdstat(8)	dmmigrate(8)	dmstat(8)
dmcheck(8)	dmdstop(8)	dmmove(8)	dmtapestat(8)
dmclrip(8)	dmdump(8)	dmmvtree(8)	dmunput(8)
dmcollect(8)	dmdumpj(8)	dmnode_admin(8)	dmusage(8)
dmconfig(8)	dmemptytape(8)	dmov_keyfile(8)	dmusrcmd(8)
dmcopan(8)	dmfdaemon(8)	dmov_loadtapes(8)	dmvoladm(8)
dmdadm(8)	dmfill(8)	dmov_makecarts(8)	dmxfsprune(8)
dmdate(8)	dmflicense(8)	dmqview(8)	dmxfsrestore(8)
dmdbcheck(8)			sitelibverify(8)

There is also the `sgi-ltfs(8)` man page.

## Obtaining Publications

You can obtain SGI documentation as follows:

- Log in to the SGI Customer Portal at <http://support.sgi.com>. Click the following:

**Support by Product**

> *productname*

> **Documentation**

If you do not find what you are looking for, click **Search Knowledgebase**, enter a document-title keyword, select the category **Documentation**, and click **Search**.

- The `/docs` directory on the ISSP DVD or in the online download directory contains the following:
  - The ISSP release note: `/docs/README.txt`
  - DMF release notes: `/docs/README_DMF.txt`
  - A complete list of the packages and their location on the media:  
`/docs/RPMS.txt`
  - The packages and their respective licenses: `/docs/PACKAGE_LICENSES.txt`
- The release notes and manuals are provided in the `noarch/sgi-isspdocs` RPM and will be installed on the system into the following location:

`/usr/share/doc/packages/sgi-issp-ISSPVERSION/TITLE`

## Conventions

The following conventions are used throughout this document:

<b>Convention</b>	<b>Meaning</b>
<code>command</code>	This fixed-space font denotes literal items such as commands, files, routines, path names, signals, messages, and programming language structures.
manpage (x)	Man page section identifiers appear in parentheses after man page names.
<i>variable</i>	Italic typeface denotes variable entries and words or concepts being defined.

<b>user input</b>	This bold, fixed-space font denotes literal items that the user enters in interactive sessions. (Output is shown in nonbold, fixed-space font.)
[ ]	Brackets enclose optional portions of a command or directive line.
...	Ellipses indicate that a preceding element can be repeated.

## Reader Comments

If you have comments about the technical accuracy, content, or organization of this publication, contact SGI. Be sure to include the title and document number of the publication with your comments. (Online, the document number is located in the front matter of the publication. In printed publications, the document number is located at the bottom of each page.)

You can contact SGI in either of the following ways:

- Send e-mail to the following address:  
[techpubs@sgi.com](mailto:techpubs@sgi.com)
- Contact your customer service representative and ask that an incident be filed in the SGI incident tracking system:  
<http://www.sgi.com/support/supportcenters.html>

SGI values your comments and will respond to them promptly.

## Introduction

This chapter provides an overview of SGI® DMF tiered-storage virtualization software. It discusses the following:

- "DMF Features" on page 1
- "How DMF Software Works" on page 14
- "Requirements" on page 43
- "Administration Tasks" on page 51

## DMF Features

DMF software transparently moves file data from high-performance but expensive disk to levels of decreased-performance but inexpensive media known as *secondary storage*. This lets you cost-effectively maintain a seemingly infinite amount of data without sacrificing accessibility for users.

This section discusses the following features of DMF software:

- "Automatic Monitoring of Filesystem Space" on page 2
- "Easy and Constant Availability of Data" on page 5
- "Partial-State Files" on page 5
- "Safety and Scalability" on page 6
- "Site-Defined Migration Policies" on page 7
- "A Variety of Migration Targets" on page 7
- "Support for Fileserving Applications" on page 8
- "DMF Manager Web Interface" on page 9
- "DMF Control from Client Platforms" on page 12
- "High Availability" on page 13
- "SOAP Web Service" on page 13

- "Direct Archiving" on page 13
- "Mounting Services" on page 13
- "Out-of-Library Tapes" on page 14

### Automatic Monitoring of Filesystem Space

A *managed filesystem* is an XFS or CXFS filesystem mounted with the *Data Management Application Programming Interface* (DMAPI) enabled and for which DMF software can migrate and/or recall migrated data. DMF software continuously monitors managed filesystems on high-performance disk so that it can maintain a certain amount of free space in those filesystems. This free space permits the creation of new files and the recall of previously migrated files. Figure 1-1 describes the concept of the DMF migration cycle between the managed filesystem and the secondary storage.




Figure 1-1 DMF Cycle



DMF software automatically detects a drop below the free-space threshold. DMF software then transparently moves file data from the managed filesystem to the secondary storage by freeing the data blocks of files that have already been migrated. File migration occurs in two stages:

- Stage One: A file's data is copied (*migrated*) to secondary storage.
- Stage Two: After the copy is secure, the file is eligible to have its data blocks released. This occurs only after a minimum free-space threshold is reached or when a manual request to free a file's disk blocks is made via the `dmpuut -r` command. DMF software chooses file data to free according to site-defined policies involving size and access time.

For example, Figure 1-2 shows a configuration where DMF software will free the data blocks of less-recently accessed files (such as represented by the letter "A") to empty the managed filesystem well below the threshold as new files are added or as previously migrated files (such as represented by the letters "B" and "E") are recalled. Despite the movement of data, all content is accessible all of the time.

---

**Note:** When configured according to best practices, DMF software makes two copies of migrated data for safety reasons. Data will be recalled from a second copy only if necessary. For simplicity, Figure 1-2 does not show the second copy of file data.

---




Figure 1-2 Free-Space Minimum Threshold

## Easy and Constant Availability of Data

In general, only the most timely data resides on the higher-performance disk; DMF software automatically migrates less timely data to secondary storage. However, all of the data always appears to be online to users and applications using normal access methods, regardless of the data's actual location.

Although DMF software moves file **data**, it leaves file **metadata** in place so that users can access files without knowing the actual location of the data. *Metadata* consists of items such as index nodes (*inodes*) and directory structure. Migrated files appear as normal files to users and are always easily accessible via high-performance network connections.

Because migrated files remain cataloged in their original directories, users and applications never need to know where the data actually resides; they can access any migrated file using normal processes. In fact, when drilling into directories or listing their contents using standard POSIX-compliant commands, a user cannot determine the location of file data within the storage tier; determining the data's actual residence requires special commands or command options.

A file whose data blocks have been freed is considered from the **DMF software perspective** to be *offline* and its data blocks are therefore available for new active data, either new files or recalled files. However, from the **user perspective**, the file always appears to be online because the inodes and directories remain in the managed filesystem, allowing users to access the file by normal means.

The only difference users might notice when accessing a file whose data blocks have been freed is a delay in response time, because the data must be retrieved from secondary storage. From the user's perspective, all data always appears to be available online, regardless of its actual location.

## Partial-State Files

Managed files can have multiple distinct file regions with different residency states. A *region* is a contiguous range of bytes that have the same residency state. A file that has more than one region is called a *partial-state* file. A file that is in a *static state* (that is, not currently being migrated or unmigrated) can have one region that is online in the managed filesystem for immediate access and another region that is offline and must be recalled in order to be accessed.

Partial-state files provide the following capabilities:

- *Accelerated access to first byte*, which allows you to access the beginning of an offline file before the entire file has been recalled.
- *Partial-state file online retention*, which allows you to keep a specific region of a file online while freeing the rest of it (for example, if you wanted to keep just the beginning of a file online). See "ranges Clause" on page 383.
- *Partial-state file recall*, which allows you to recall a specific region of a file without recalling the entire file. For more information, see the `dmpout(1)` and `dmget(1)` man pages.

For additional details, see:

- "Modify Partial-State Capability with Care" on page 122
- "dmdaemon Object Parameters" on page 290
- Appendix G, "Considerations for Partial-State Files" on page 779

## Safety and Scalability

DMF software transports large volumes of data on behalf of many users and has evolved to satisfy customer requirements for scalability and the safety of data:

- When you configure the DMF environment using best practices, DMF software creates at least two secondary-storage copies of the data in order to prevent file data loss in the event that a migrated copy is lost. See "Ensuring Data Integrity" on page 38.
- Because system interrupts and occasional storage device failures cannot be avoided, it is essential that the integrity of data be verifiable. Therefore, DMF software also provides tools necessary to validate your storage environment. See "Commands Overview" on page 56.
- DMF with the *Parallel Data-Mover Option* (referred to as *Parallel DMF*) lets you scale the DMF I/O capacity in cost-effective increments. A *data mover* is a node running processes that migrate and recall data to secondary storage. In the basic DMF product, the DMF server incorporates the functionality of an integrated data-mover node. Parallel DMF allows the DMF system to reside on a single server and minimizes the cost of a DMF implementation. For users with higher throughput requirements, this option allows multiple data movers to operate in parallel, increasing data throughput and enhancing resiliency. The parallel

data-mover node's dedicated function is to move data to and from secondary storage. See "Parallel DMF Overview" on page 33.

## Site-Defined Migration Policies

As a DMF administrator, you determine how disk space capacity is handled by doing the following:

- Selecting the filesystems that DMF software will manage
- Specifying the amount of free space that will be maintained on each filesystem
- Ranking file-selection criteria, such as file size and file age

DMF software selects files for migration and frees data blocks of already migrated files based on site-defined criteria that are specified in a *migration policy*. For example, a migration policy does the following:

- Makes the specified number of copies of migrated data. DMF software places those copies on separate secondary-storage targets. SGI strongly recommends that you create at least two secondary-storage copies in order to prevent file data loss in the event that one copy is damaged.
- Migrates the data at the times specified or when the specified free-space minimum threshold is exceeded.
- Optionally keeps a small amount of data in the managed filesystem for each file, even after migration (for use by file managers, in order to avoid unnecessary recall of a file due to directory browsing).
- Maintains a specified percentage of the managed filesystem free for new data (either new files or recalled files). When the filesystem reaches this threshold, DMF software will free the already-migrated data blocks until the specified percentage of the filesystem is free, normally selecting files by size and last-access time.

## A Variety of Migration Targets

DMF software can migrate data to the following media:

- Cloud storage
- Fibre Channel tapes and tape libraries that are supported by the OpenVault or TMF mounting services

- SCSI low-voltage differential (LVD) tapes and tape libraries

---

**Note:** If you have a high-voltage differential (HVD) tape or tape library that you want to use for the DMF environment, you must contact SGI Professional Services for assistance in obtaining the appropriate HVD-LVD converter.

The LVD requirement is only for tapes and tape libraries. It does not apply to HVD disk.

---

- Disk
- COPAN RAID sets:
  - COPAN massive array of idle disks (MAID)
  - SGI 400 virtual tape library (VTL)
- JBFS configurations
- Another server (via NFS or FTP)

You can also use disk or COPAN RAID sets as a cache in conjunction with another migration target to provide multiple levels of migration; see "Multiple Storage Tiers" on page 19.

## Support for Fileserving Applications

DMF software supports a range of storage-management applications. In some environments, DMF software is used strictly to manage highly stressed online disk resources. In other environments, it is also used as an organizational tool for safely managing large amounts of data. In all environments, DMF software scales to the storage application and to the characteristics of the available storage devices.

DMF software interoperates with the following:

- Standard data export services such as NFS and FTP
- XFS<sup>®</sup> filesystems
- CXFS<sup>™</sup> clustered filesystems
- Microsoft<sup>®</sup> SMB (also known as the CIFS) as used by Samba when fileserving to Windows<sup>®</sup> systems

By combining these services with DMF software, you can configure an SGI system as a high-performance fileserver.

## DMF Manager Web Interface

DMF software provides a set of graphical and command-line tools to help you configure, monitor, and manage the DMF system. *DMF Manager* is a web-based tool you can use to do the following:

- Configure the DMF environment
- Install DMF licenses
- Display status of the DMF environment
- Display reports about internal DMF processing queues, allowing you to cancel and reprioritize specific requests
- Start and stop DMF processes
- Deal with day-to-day DMF operational issues
- Display performance metrics, including filesystem throughput and volume usage
- Create custom statistics reports
- Accommodate tape volumes that are physically not in the tape library
- Show SGI Linear Tape File System (LTFS) information, configure LTFS, and mount/unmount LTFS tapes
- Restore filesystems and filesystem components

For details, see:

- "DMF Manager Requirements" on page 49
- Chapter 6, "DMF Manager" on page 191
- Chapter 17, "DMF Queue Viewing" on page 605

Also see:

- "Using Out-of-Library Tapes" on page 184
- Chapter 18, "SGI LTFS" on page 631

DMF Manager is useful for all DMF customers from enterprise to high-performance computing and is available via the Firefox® and Internet Explorer® web browsers.

At a glance, you can see if the DMF environment is operating properly. An icon in the upper-right corner indicates if the DMF environment is up (green) or down (upside down and red). If something requires, DMF Manager makes actions available to identify and resolve problems. The tool volunteers information and provides context-sensitive online help. DMF Manager also displays performance statistics, allowing you to monitor DMF activity, filesystems, and hardware.

Figure 1-3 is an example of the **Overview** panel. It shows status of the DMF environment, including the following:

- The DMF environment is up (green icon)
- There are some warnings that may require action (yellow icon)
- The `/dmi_fs2` filesystem is related to the `volume1` and `volume2` volume groups (VGs)






Figure 1-3 DMF Manager

## DMF Control from Client Platforms

This section discusses the following:

- "Overview of the Windows Client" on page 12
- "Overview of the IRIX, Mac OS X, Linux, and Solaris Clients" on page 12

### Overview of the Windows Client

The DMF client for Windows systems lets users and administrators control DMF via file shares configured on the Samba server. The Samba server must have SGI enhanced Samba installed, and may be either the DMF server or a CXFS client-only node.

Using Windows Explorer, you can do the following for files on which you have the appropriate permission, depending upon site-specific configuration:

- View DMF file properties
- Execute the following DMF user operations:
  - Recall files, similar to the functionality of the `dmget(1)` command
  - Migrate files, similar to the functionality of the `dmput(1)` command
  - Set site tags, similar to the functionality of the `dmtag(1)` command
- Set a project ID, similar to functionality of the `dmprojid(8)` command

See *DMF 6 Client Guide for Windows Systems*.

### Overview of the IRIX, Mac OS X, Linux, and Solaris Clients

Several DMF user commands are available natively on DMF clients running any of the following operating systems (see the DMF release notes for the specific versions that are supported):

- SGI IRIX®
- Apple® Mac OS X®
- Red Hat® Enterprise Linux® (RHEL)
- SUSE® Linux® Enterprise Server (SLES)
- Sun™ Solaris™

For more details, see "User Commands" on page 57.

## High Availability

You can run DMF software in a high-availability (HA) cluster.



---

**Caution:** This will require some configuration requirements and administrative procedures (such as starting/stopping DMF services) that differ from the information in this DMF guide. For more information about DMF and HA, see *High Availability Guide for SGI InfiniteStorage*.

---

## SOAP Web Service

DMF software provides access to a subset of the DMF client functions via the DMF Simple Object Access Protocol (SOAP) web service. For more information, see Chapter 16, "DMF SOAP Server" on page 597.

## Direct Archiving

You can use the *direct archiving* feature to manually copy file data between a POSIX filesystem (such as a Lustre™ filesystem) directly to DMF secondary storage by configuring the POSIX filesystem for archive use in the DMF configuration file and using the `dmarchive(1)` command. The POSIX filesystem cannot be DMAPi-enabled (that is, it cannot be mounted with the `dmi` mount option) and is known as an *archive filesystem*. When using this feature, DMF software copies the file data to DMF secondary storage while placing the metadata in a filesystem that is managed by DMF. See "Use `dmarchive` to Copy Archive File Data to Secondary Storage" on page 119.

## Mounting Services

When you purchase DMF software, you also receive the following mounting services:

- OpenVault storage library management facility, applicable to SLES or RHEL. See *OpenVault Administrator Guide for SGI InfiniteStorage*.
- Tape Management Facility (TMF), applicable to SLES only. See *TMF 6 Administrator Guide for SGI InfiniteStorage*.

## Out-of-Library Tapes

When OpenVault is the mounting service, DMF software will try to retrieve data from an in-library volume before requesting that an out-of-library tape be imported. See "Using Out-of-Library Tapes" on page 184.

## How DMF Software Works

This section discusses the following:

- "File States" on page 14
- "DMF Methods" on page 15
- "Multiple Storage Tiers" on page 19
- "Migration Process" on page 27
- "Recall of File Data" on page 27
- "Fast-Mount Cache Configuration Overview" on page 30
- "DMF Server Functions" on page 32
- "Parallel DMF Overview" on page 33
- "DMF Databases" on page 37
- "Ensuring Data Integrity" on page 38
- "DMF Architecture" on page 38
- "Migrate Groups" on page 42
- "DMF Capacity" on page 42

## File States

DMF software uses the following terminology with regard to the state of a file in a managed filesystem:

- *Regular file* (REG) is a file residing only on the high-performance disk in the managed filesystem.

- *Migrating file* (MIG) is a file whose copies on secondary storage are in progress.
- *Migrated file* is a file that has one or more complete copies on secondary storage and no pending or incomplete offline copies. A migrated file is one of the following from the perspective of DMF software:
  - *Dual-state file* (DUL) is a file whose data resides both on the high-performance disk and on secondary storage
  - *Offline file* (OFL) is a file whose data is no longer on the high-performance disk (the data is offline from the DMF perspective, but from the user perspective the data always appears to be available online)
  - *Unmigrating file* (UNM) is a previously offline file in the process of being recalled to the high-performance disk
  - *Partial-state file* (PAR) is a file with some combination of dual-state, offline, and/or unmigrating regions

When a file is first migrated, DMF software copies the data to secondary storage but may not immediately free the data in the managed filesystem on the high-performance disk. During this period, the file is considered to be *dual-state* because it resides in both locations. Like a regular file, a migrated file has an inode. An offline file or a partial-state file requires the intervention of the DMF daemon to access its offline data; a dual-state file is accessed directly from the original that still exists in the managed filesystem.

The operating system informs the DMF daemon when a migrated file is modified. If anything is written to a migrated file, the offline copy is no longer valid, and the file becomes a regular file until it is migrated again.

If you are using DMF direct archiving to copy files from a filesystem that is not managed, *archiving files* are files where the original resides on an archive filesystem (one not managed by DMF software, such as Lustre) and whose offline copies are in progress. When the process completes, the files are offline files.

## DMF Methods

The migration process is managed by a daemon-like component called a *library server (LS)* or *media-specific process (MSP)*:

- *LS* (dmatls) transfers data to and from the following types of volumes:
  - Magnetic tape in a tape library (also known as a *robotic library* or *silo*)

- RAID sets in a COPAN MAID system<sup>1</sup>
- Virtual tapes in an SGI 400 VTL system
- JBFS configurations
- *Cloud MSP* (`dmcloudmsp`) transfers data to and from a cloud storage system accessible via a network (local or Internet).
- *FTP MSP* (`dmftpmmsp`) uses the File Transfer Protocol to transfer data to and from disks of another system on the network.
- *Disk MSP* (`dmdiskmsp`) uses a filesystem mounted on the DMF server itself as the location on which to store/recall file data. See "Use an Appropriate Filesystem for a Disk MSP" on page 121.
- *Disk cache manager (DCM) MSP* is the disk MSP configured for *n*-tier capability by using a dedicated filesystem as a cache. DMF software can manage the disk MSP's storage filesystem and further migrate it to secondary storage, thereby using a slower and less-expensive dedicated filesystem as a cache to improve the performance when recalling files. DCM MSP configuration generally first migrates data to cache on (for example) serial ATA (SATA) disk and then at a later time migrates the data from the SATA disk to secondary-storage on physical tape. The filesystem used by the DCM MSP must be a local XFS or CXFS filesystem.
- *Fast-mount cache configuration* is a special configuration of an LS volume group that simultaneously migrates data to a copy on the cache target (such as COPAN MAID or JBFS configurations) with rapid mount and positioning characteristics and to secondary-storage copies on the other targets (such as physical tape). This configuration provides similar functionality to a DCM MSP but does not downwardly migrate data from the cache tier; in this configuration, an entire volume on the cache can be freed immediately when the fullness threshold is reached. See "Fast-Mount Cache Configuration Overview" on page 30.


A site can use any combination of DMF methods.

Figure 1-4 and Figure 1-5 summarize these concepts and "Multiple Storage Tiers" on page 19 provides more details and illustrations.

---

<sup>1</sup> For historical reasons, these volumes are sometimes referred to as *tapes* in command output and documentation.

**Before DMF**  
DMF perspective: **regular** file  
User perspective: **online** file



**Figure 1-4** DMF Methods: Before Migrating

After DMF  
 DMF perspective: offline file  
 User perspective: online file




Figure 1-5 DMF Methods: After Migrating Data and Freeing Space



## Multiple Storage Tiers

The various DMF methods provide multiple storage tiers:

- "Two Tiers" on page 19
- "Three Tiers using DCM MSP" on page 21
- "Three Tiers using Fast-Mount Cache" on page 24

The figures in the following subsections show the use of multiple tiers and the concepts of DMF data migration (in which file data is copied from the managed filesystem to the secondary storage, but the inode remains in place in the managed filesystem) and data recall.

---

**Note:** For simplicity, the figures in this chapter do not address a second copy of secondary storage. Data will be recalled from a second copy only if necessary.


---

### Two Tiers


LS and *non-cache MSPs* (cloud MSP, disk MSP, or FTP MSP) provide two tiers of storage media:

- Tier-1: Managed filesystem on high-performance disk
- Tier-2: Secondary storage on cloud storage, disk (including COPAN MAID, COPAN VTL, and JBFS configurations), FTP server, or tape

Figure 1-6 and Figure 1-7 show an example of the process using two tiers.



**Figure 1-6** Two Tiers: Migrating File Data



**Figure 1-7** Two Tiers: Freeing and Recalling File Data

### Three Tiers using DCM MSP

Adding a DCM MSP provides three tiers of storage media:

- Tier-1: Managed filesystem on high-performance disk
- Tier-2: Cache on high-capacity, low-cost disk that will downwardly migrate and free data on a file basis
- Tier-3: Secondary storage on cloud storage, FTP server, or tape

Figure 1-8 and Figure 1-9 show an example of the process using three tiers of storage with a DCM MSP, where data moves first to a cache on lower-performance but less-expensive disk, then to inexpensive storage. The file will be recalled from disk cache as long as it resides there because it is faster than recalling from the third tier.




Figure 1-8 DCM MSP: Migrating File Data




Figure 1-9 DCM MSP: Freeing and Recalling File Data

### Three Tiers using Fast-Mount Cache

Adding a fast-mount cache provides three tiers of storage media:

- Tier-1: Managed filesystem on high-performance disk
- Tier-2: Fast-mount cache (such as COPAN MAID or JBFS configurations) that will be freed on a volume basis (no downward migration)
- Tier-3: Secondary storage on cloud storage, FTP server, JBFS configurations, and tape

Figure 1-10 and Figure 1-11 show an example of the process using three tiers of storage, where a copy of the data is simultaneously placed in tier-2 fast-mount cache (such as COPAN MAID or JBFS configurations) and in tier-3 secondary storage (such as tape). The file will be recalled from the cache as long as it resides there because it is faster than recalling from tier-3 storage.

---

**Note:** Unlike the DCM MSP, this method does not migrate data from the cache to tier-3; therefore, volumes on the cache can be freed immediately when the fullness threshold is reached.

---

For more information, see "Fast-Mount Cache Configuration Overview" on page 30.




Figure 1-10 Fast-Mount Cache: Migrating File Data




Figure 1-11 Fast-Mount Cache: Freeing and Recalling File Data



## Migration Process

You choose both the percentage of the filesystem to migrate and the amount of free space. You as the administrator can manually trigger file migration or file owners can issue manual migration requests.

A file is migrated when the automated space-management controller `dmfsfree(8)` selects the file or when an owner requests that the file be migrated by using the `dmput(1)` command.

When the daemon receives a request to migrate a file, it does the following:

1. Adjusts the state of the file.
2. Ensures that the necessary MSPs/VGs are active.
3. Sends a request to the MSPs/VGs, who in turn copy data to the secondary storage media.

When the MSPs/VGs have completed the offline copies, the daemon marks the file as migrated in its database and changes the file to dual-state. If the user specifies the `dmput -r` option, or if `dmfsfree` requests that the file's space be released, the daemon releases the data blocks and changes the file state to offline. For more information, see the `dmput(1)` man page.

---

**Note:** DMF software does not migrate pipes, directories, or UNIX® or Linux special files.

---

## Recall of File Data

This section discusses the following:

- "Recall from the Appropriate Location" on page 27
- "Order of Recall" on page 28
- "Freeing Data Blocks to Make Space for Recalls" on page 30

### Recall from the Appropriate Location

Data is provided to the user from the appropriate location:

- If a user accesses a dual-state file, the data comes directly from the high-performance disk as normal, providing the fastest access.
- After the data blocks on the managed filesystem are freed, DMF software automatically recalls the file's data from the secondary storage when the user accesses the file, placing the data back on the managed filesystem; at this point, the file once again becomes a dual-state file. (If the user then changes the file, it returns to being a regular file.)

### Order of Recall

When a migrated file must be recalled, a request is made to the DMF daemon. The daemon selects an MSP/VG from its internal list and sends that MSP/VG a request to recall a copy of the file. If more than one MSP/VG has a copy, the first one in the list is used. The list is created from the configuration file.

For illustration purposes, suppose that the DMF configuration file contains the following definitions for an environment using a single library server with two drive groups that each have two volume groups to specify the location of file copies:

- The `dmdaemon` object contains the following parameter to identify the library server:

```
LS_NAMES          myls
```

- The `libraryserver` object defined for `mysls` contains the following parameter to identify the drive groups and their order of selection:

```
DRIVE_GROUPS      fruits veggies
```

- The `drivegroup` objects defined for `fruits` and `vegetables` identify their respective volume groups and their order of selection:

- For `fruits`:


```
VOLUME_GROUPS    oranges apples
```

- For `veggies`:

```
VOLUME_GROUPS    carrots peas
```

The order in which volumes are chosen for recall is decided by the order in which drive groups and then volume groups are listed in their respective definitions. Given the above, `oranges` will be tried first and `peas` will be tried last. If you stopped

DMF, reordered the list in `DRIVE_GROUPS`, and restarted DMF, then `carrots` would be tried first and `apples` be tried last, as shown in Figure 1-12.



**Figure 1-12** Recall Order

---

**Note:** You must not change these parameters while DMF is running.

---

For more details, see Chapter 7, "DMF Configuration File" on page 271, specifically:

- "dmdaemon Object Parameters" on page 290
- "libraryserver Object Summary" on page 393
- "drivegroup Object Parameters" on page 397

### Freeing Data Blocks to Make Space for Recalls

If you recall more files than the managed filesystem can currently contain, DMF software migrates other files and will free the data blocks of already-migrated files (according to site-specific policies) until the filesystem is once again well below the free-space minimum threshold.

---

**Note:** A file's data blocks on the managed filesystem can only be freed **after** the data has been copied to secondary storage.

---

### Fast-Mount Cache Configuration Overview

This section discusses the following:

- "Cache and Secondary-Storage Targets" on page 30
- "How Fast-Mount Cache Differs from a DCM MSP" on page 31
- "Fast-Mount Cache Implementation" on page 32
- "Appropriate Use of Fast-Mount Cache" on page 32

### Cache and Secondary-Storage Targets

You can use a cache migration target with rapid mount and positioning characteristics in conjunction with other secondary-storage targets in a fast-mount cache configuration. For example, consider the following:

- COPAN MAID and JBFS configurations are faster than physical tapes, but their storage size is finite
- A physical tape library has an effectively unlimited storage capacity because you can eject full tapes and replace them with empty tapes, but recalling data from tape is slower than recalling data from COPAN MAID or JBFS configurations

The combination of these two targets in a fast-mount cache configuration results in faster recall performance for recently created offline files while also providing secure long-term storage.

### How Fast-Mount Cache Differs from a DCM MSP

A fast-mount cache is similar to a DCM MSP in that both provide fast recall of migrated files in the cache tier (tier-2). However, they have following important differences:

- DCM MSP:
  - Can be configured to downwardly migrate data from tier-2 to tier-3 as the data ages
  - Only requires that one initial copy be made, although two copies are recommended to prevent data loss (the copy in cache can be downwardly migrated to secondary storage on tier-3)
  - Deletes data from tier-2 on an individual file basis
  - Data on tier-2 may not be immediately recoverable when space is needed if the data does not already have a copy in tier-3 (causing a delay if space is needed quickly)
- Fast-mount cache:
  - Does not downwardly migrate data from tier-2 to tier-3
  - Always requires that at least two initial copies be made (a copy to the cache and a copy to the secondary storage on tier-3)
  - Deletes data from tier-2 on a volume basis (that is, all files in the volume are deleted at the same time)
  - Tier-2 can be freed immediately when the free-space threshold is reached, without further operational effort

---

**Note:** SGI strongly recommends that you migrate at least two copies to secondary-storage targets in order to prevent file data loss in the event that a migrated copy is damaged. When using a fast-mount cache, SGI therefore recommends that you migrate at least three copies (one copy to the cache on tier-2 and two copies to secondary-storage targets at the tier-3 level).

---

## Fast-Mount Cache Implementation

To implement a fast-mount cache, you must configure the DMF environment to make all secondary-storage copies of the data (tier-3 storage on other MSPs/VGs) at the same time as the cache copy (tier-2 storage on the MGs/VGs in the fast-mount cache).

You must also configure a task to empty the fast-mount cache when it reaches the configurable free-space threshold. DMF software immediately empties the oldest full volumes, defined as those with the oldest write dates. Because at least one copy of the data exists elsewhere (most likely on a physical tape), there is no need to wait for the data in the disk cache to migrate to a lower tier (unlike a DCM MSP). Therefore, the freeing of space on the fast-mount cache is very fast because it requires no movement of data.

Figure 1-10 on page 25 and Figure 1-11 on page 26 summarize the concepts of migrating and recalling file data in a fast-mount cache configuration using COPAN MAID as an example.

Also see "Use Fast-Mount Cache Appropriately" on page 112.

## Appropriate Use of Fast-Mount Cache

The fast-mount cache configuration is most appropriate for sites that have a high turnover of often-accessed data, where the most recently migrated files are also the most likely to be recalled.

All files on a volume being freed are deleted without regard to their size or last access time. That might mean that a file that is still being actively recalled on a fairly regular basis must be recalled from a VG with slower mount and position characteristics. You can minimize this issue by setting optional configuration parameters so that recently accessed files are copied to another volume within the fast-mount cache before any volumes are freed, using a separate scratch directory, but there may be an associated performance impact.

## DMF Server Functions

The DMF server always provides the following services:

- DMF administration (see "Administration Tasks" on page 51)
- Backups

- All I/O for data transfer to and from disks that is associated with cloud, FTP, disk, or DCM MSPs (see "How DMF Software Works" on page 14)
- By default, a portion of I/O for data transfer to and from secondary storage (using its integrated data-mover functionality)

## Parallel DMF Overview

The individual processes that migrate and recall data are known as *data-mover processes*. Nodes that run data-mover processes are *data movers*; this may include the DMF server node if it is configured to use the *integrated data-mover functionality* and, if you have purchased the *Parallel Data-Mover Option*, the *parallel data-mover nodes*. The DMF server and the parallel data-mover nodes can each run multiple data-mover processes.

As shown in Figure 1-13, the *basic DMF* product (that is, without the Parallel Data-Mover Option) runs data-mover processes on the DMF server. This allows the DMF control system to reside on a single server and minimizes the cost of a DMF implementation. Additional nodes can be installed with DMF client software (see "DMF Control from Client Platforms" on page 12).

Figure 1-14 shows the DMF product in a CXFS clustered filesystem environment.

---

**Note:** All nodes connect to a network. For simplicity, the network and DMF clients are not shown in the following figures.

---




Figure 1-13 Basic DMF Product in an NFS Environment




Figure 1-14 Basic DMF Product in a CXFS Environment



For users with higher throughput requirements, Parallel DMF allows additional data movers to operate in parallel with the integrated data-mover functionality on the DMF server, increasing data throughput and enhancing resiliency.

The parallel data-mover node's dedicated function is to move data from the managed filesystem to *volume-based media* (COPAN MAID, COPAN VTL, JBFS configurations, or tape) back into the managed filesystem, using an LS. Offloading the majority of I/O from the integrated data-mover functionality on the DMF server improves I/O throughput performance.

Because multiple parallel data-mover nodes can be used to move data, DMF software can scale its I/O throughput capabilities. When one parallel data-mover node hits its peak throughput capabilities, you can add more parallel data-mover nodes to the configuration as needed to improve I/O performance. Each parallel data-mover node can improve overall DMF performance by up to its maximum performance. For example, if you have parallel data-mover nodes that each provide up to a 2-GB/s increase, then having a configuration with three of these parallel data-mover nodes would provide a net increase of up to 6 GB/s. Additional drives and filesystem bandwidth may be required to realize the benefit from additional parallel data-mover nodes.

The basic DMF product can run in an environment with or without CXFS. If DMF software is managing a CXFS filesystem, DMF software will ensure that the filesystem's CXFS metadata server is on the same machine as the DMF server and will use metadata server relocation if necessary to achieve that configuration (see "Configure DMF Appropriately with CXFS™" on page 104). Parallel DMF must always run in a CXFS environment. The parallel data-mover nodes are SGI x86\_64 machines that are installed with the **SGI DMF Parallel Data Mover** software package, which includes the required underlying CXFS software.

---


**Note:** From the CXFS cluster point of view, a DMF parallel data-mover node is a CXFS client-only node and therefore counts towards the total number of CXFS cluster nodes. However, the parallel data-mover nodes must be dedicated to DMF data-mover activities; they cannot perform any other functions that would be normal for CXFS client-only nodes.

---

The parallel data-mover node has specific hardware requirements and must access volume-based media on a port that is not used by CXFS. See "SAN Switch Zoning or Separate SAN Fabric Requirement" on page 49.

If you choose the Parallel DMF, you must use OpenVault for those drive groups (DGs) that contain drives on parallel data-mover nodes.

Figure 1-15 shows the concept of the DMF product using parallel data-mover nodes in a CXFS cluster with only one server-capable administration node. The parallel data-mover nodes only write data to secondary storage on volume-based media in an LS.



**Figure 1-15** Parallel DMF in a CXFS Environment

In a configuration with Parallel DMF, the DMF server still provides the services listed in "DMF Server Functions" on page 32.

For more information, see Chapter 8, "Parallel DMF Configuration" on page 485.

## DMF Databases

The DMF daemon keeps track of migrated files in the *daemon database*. The key to each file is its *bit-file identifier (BFID)*. For each migrated file, the daemon assigns a BFID that is stored in the file's inode. There is a daemon database record for each copy of a migrated file.

The daemon database also contains information such as the following:

- The MSP/VG name
- The MSP/VG key for each copy of a migrated file

When you use an MSP, the daemon database contains all of the information required to track a migrated file.

If you use an LS, there is also the *LS database*, which contains two tables of records:

- *Catalog (CAT) records* track the location of migrated data on volumes. There is one CAT record for each migrated copy of a file. If a migrated copy is divided between multiple volumes, there will be a CAT record for each portion or *chunk*.
- *Volume (VOL) records* contain information about the volumes. There is one VOL record for each volume.

Detailed information about the daemon and LS databases and their associated utilities is provided in "CAT Records" on page 536 and "VOL Records" on page 537.

---

**Note:** The databases consist of multiple files. However, these are not text files and cannot be updated by standard utility programs. See "Database Backups" on page 647.

---

There are also databases for DMF Manager performance records and alerts.

For information about the OpenVault database, see *OpenVault Administrator Guide for SGI InfiniteStorage*.

## Ensuring Data Integrity

DMF software provides capabilities to ensure the integrity of offline data. For example, you can have multiple MSPs/VGs with each managing its own pool of volumes. Therefore, you can configure the DMF environment to copy filesystem data to multiple offline locations.

DMF software stores data that originates in a CXFS or XFS filesystem. Each object stored corresponds to a file in the native filesystem. When a user deletes a file, the inode for that file is removed from the filesystem. Deleting a file that has been migrated begins the process of invalidating the offline image of that file. In the LS, this eventually creates a gap in the volume. To ensure effective use of media, the LS provides a mechanism for reclaiming space lost to invalid data. This process is called *volume merging*.

Much of the work done by DMF software involves transaction processing that is recorded in databases. The DMF databases provide for full transaction journaling and employ two-phase commit technology. The combination of these two features ensures that DMF software applies only whole transactions to its databases. Additionally, in the event of an unscheduled system interrupt, it is always possible to replay the database journals in order to restore consistency between the DMF databases and the filesystem. DMF utilities also allow you to verify the general integrity of the DMF databases themselves. See "Administration Tasks" on page 51 for more information.

## DMF Architecture


DMF software consists of the DMF daemon and one or more MSPs or LSs. The DMF daemon accepts requests to migrate filesystem data from the DMF administrator or from users. It also communicates with the operating system kernel to maintain a file's migration state in that file's inode.

The DMF daemon is responsible for dispensing a unique bit-file identifier (BFID) for each file that is migrated. The daemon also determines the destination of migration data and forms requests to the appropriate MSP/LS to make offline copies.


The MSP/LS accepts requests from the DMF daemon. For outbound data, the LS accrues requests until the amount of data justifies a volume mount. Requests for data retrieval are satisfied as they arrive. When multiple retrieval requests involve the same volume, all file data is retrieved in a single pass across the volume.

DMF software uses the DMAPI kernel interface defined by the Data Management Interface Group (DMIG). DMAPI is also supported by X/Open, where it is known as the *XDSM standard*.

Figure 1-16 illustrates the basic DMF architecture. Figure 1-17 shows the architecture of the LS.



**Figure 1-16** Basic DMF Architecture



**Figure 1-17** LS Architecture

There is one LS process (`dmats`) per library, which maintains a database that all of its components share. The entities in the shaded boxes in Figure 1-17 are internal components of the `dmats` process. Their functions are as follows:

**Drive group (DG)**

The DG is responsible for the management of a group of interchangeable drives located in the library. These drives can be used by multiple VGs (see *volume group* below) and by other processes, such as backups and interactive users. However, in the latter cases, the DG has no management involvement; the mounting service (TMF or OpenVault) is responsible for ensuring that these possibly competing uses of the drives do not interfere with each other.

The main tasks of the DG are to:

- Monitor I/O for errors
- Attempt to classify the errors as volume, drive, or mounting service problems
- Take preventive action

Volume group (VG)	The VG holds at most one copy of a migrated file in a pool of volumes, of which it has exclusive use. It can use only the drives managed by a single DG.
Allocation group (AG)	An AG is a pool of volumes that are transferred to a VG as needed and are returned to the pool when empty, subject to VG configuration parameters. Normally, an AG is configured to serve multiple VGs. Use of an AG is optional. When empty volumes are added to the DMF environment, they may be assigned to an AG via the <code>dmvoladm(8)</code> command.
Resource scheduler	In a busy environment, it is common for the number of drives requested by VGs to exceed the number available. The purpose of the resource scheduler is to decide which VGs should have first access to drives as they become available and to advise the DG of the result. The DMF administrator can configure the resource scheduler to meet site requirements.
Standard resource scheduler algorithm	This routine is an internal component of the <code>dmatis</code> process. Standard algorithms are provided with DMF software.
Resource watcher	The resource watcher monitors the activity of the other components and frequently updates files that contain data of use to the administrator. These are usually HTML files viewable by a web browser, but can also be text files designed for use by <code>awk</code> or <code>perl</code> scripts.

The `dmatrc` and `dmatwc` processes are called the *read children* and *write children*. They are created by VGs to perform the actual reading and writing of volumes. Unlike most of the other DMF processes that run indefinitely, these processes are created as needed, and are terminated when their specific work has been completed.

Media transports and robotic automounters are also key components of all DMF installations. Generally, DMF software can be used with any transport and automounter that is supported by either OpenVault or TMF. Additionally, DMF software supports *absolute block positioning*, a media transport capability that allows rapid positioning to an absolute block address on the volume. When this capability is provided by the transport, positioning speed is often three times faster than that obtained when reading the volume to the specified position.

## Migrate Groups

A *migrate group (MG)* is a logical collection of MSPs and VGs that you combine into a set in order to have a single destination for a migrate request. A migration request to the MG will result in the copying of the file to exactly one MSP/VG that is a member of the MG.

You define an MG by adding the `migrategroup` object to the DMF configuration file. You can use the defined name of the MG in DMF policies and commands, similar to the way in which you use the names of VGs/MSPs. See:

- "Use Migrate Groups Appropriately" on page 111
- "Balance Data Among Libraries" on page 139
- "migrategroup Object" on page 426

## DMF Capacity

The capacity of the DMF environment is measured in several ways, as follows:

- Total number of files. The daemon database can contain approximately 4 billion entries, and there is one database entry for each copy of a file that DMF software manages. Therefore, if there are two copies of each managed file, DMF software can theoretically manage approximately 2 billion files. The number of files that can be supported with best performance will vary depending upon the workload.
- Total amount of data. The capacity is limited only by the amount of secondary storage available to DMF software.
- Total amount of data moved between online and offline media. The number of drives configured for the DMF environment, the number of tape channels, and the number of disk channels all figure highly in the effective bandwidth. In general, DMF software provides full-channel performance to both tape and disk.



- File size. DMF software can support any file that can be created on the CXFS or XFS filesystem being managed.

DMF software has evolved in production-oriented, customer environments. It is designed to make full use of parallel and asynchronous operations, and to consume minimal system overhead while it executes, even in busy environments in which files are constantly moving online or offline. Exceptions to this rule will occasionally occur during infrequent maintenance operations when a full scan of filesystems or databases is performed.

For information about the DMF capacity license, see Chapter 2, "DMF Licensing" on page 67.

## Requirements

---

**Note:** See the InfiniteStorage Software Platform (ISSP) release note and the DMF release note for the supported kernels, update levels, service pack levels, software versions, libraries, and tape devices.

---

This section discusses the following:

- "DMF Administrative and Store Directories" on page 44
- "PostgreSQL Database Server Requirements" on page 47
- "Server Node Requirements" on page 48
- "Parallel Data-Mover Node Requirements" on page 48
- "Mounting Service Requirements" on page 48
- "License Requirements" on page 48
- "DMAPI Requirement" on page 48
- "SAN Switch Zoning or Separate SAN Fabric Requirement" on page 49
- "DMF Manager Requirements" on page 49
- "DMF SOAP Requirements" on page 50
- "DMF Direct Archiving Requirements" on page 50

- "Fast-Mount Cache Requirements" on page 50
- "Cloud Storage Requirements" on page 51
- "Mediaflux Environment Requirements" on page 51

## **DMF Administrative and Store Directories**

The DMF server uses the *DMF administrative and store directories* to store its databases, log files, journal files, and temporary files. Table 1-1 summarizes the configuration parameters used to define these directories, the variable that represents the value of the parameter in this guide, and the purpose of the directories. For configuration details, see Chapter 7, "DMF Configuration File" on page 271.

Table 1-1 DMF Administrative and Store Directories

Configuration Parameter	Variable that Represents the Parameter Value	Example Value	Purpose
HOME_DIR	<i>HOME_DIR</i>	/dmf/home	Specifies the base pathname for directories in which the DMF daemon database, library server (LS) database, and related files reside. Minimum permission requirement: 711
SPOOL_DIR	<i>SPOOL_DIR</i>	/dmf/spool	Specifies the base pathname for directories in which DMF log files are kept. Minimum permission requirement: 711
JOURNAL_DIR	<i>JOURNAL_DIR</i>	/dmf/journals	Specifies the base pathname for directories in which the journal files for the daemon database and LS database will be written. Minimum permission requirement: 711
TMP_DIR	<i>TMP_DIR</i>	/dmf/tmp	Specifies the base pathname for directories in which DMF puts temporary files for its own internal use. Minimum permission requirement: 711
DATABASE_COPIES	<i>DATABASE_COPIES</i>	/dir1/database_copies and /dir2/database_copies	Specifies one or more directories into which the <code>run_copy_databases.sh</code> task will place a copy of the DMF databases.

Configuration Parameter	Variable that Represents the Parameter Value	Example Value	Purpose
DUMP_DESTINATION for integrated backups	<i>DUMP_DESTINATION</i>	/dmf/backups	Specifies the location in which to store backups and must be a dedicated filesystem mount point
DUMP_DESTINATION for disk backups (nonintegrated)	<i>DUMP_DESTINATION</i>	/dmf/backups	Specifies the location in which to store backups.
STORE_DIRECTORY for a DCM MSP	<i>STORE_DIRECTORY</i>	/dmf/ <i>dcmmname_store</i>	Specifies the directory that holds files for a DCM MSP. There is one STORE_DIRECTORY parameter for each DCM MSP.
STORE_DIRECTORY for a disk MSP	<i>STORE_DIRECTORY</i>	/dmf/ <i>diskmsname_store</i>	Specifies the directory that holds files for a disk MSP (there is one STORE_DIRECTORY parameter for each disk MSP).
CACHE_DIR	<i>CACHE_DIR</i>	/dmf/cache	<i>(Optional)</i> Specifies the directory in which the VG stores chunks while merging them from sparse volumes.
MOVE_FS	<i>MOVE_FS</i>	/move	<i>(Optional)</i> Specifies one or more scratch directories that are used by <code>dmmove(8)</code> to move files between media-specific processes (MSPs) or volume groups (VGs). You must specify a value for MOVE_FS if you intend to use the <code>dmmove</code> command. The best practice when using <i>MOVE_FS</i> is for it to be dedicated to the <code>dmmove</code> function.

For more information about DMF administrative directories, see "DMF Administrative and Store Directories" on page 44.

## PostgreSQL Database Server Requirements

The PostgreSQL database is required by DMF for various purposes, including the queue-viewing tools:

- DMF requires the 9.3.X version of PostgreSQL. See "Apply Appropriate PostgreSQL Updates" on page 136.
- The PostgreSQL database server is the DMF server
- The PostgreSQL database server depends upon the `ident` service. See "Overview of the Installation and Configuration Steps" on page 165.
- 

The PostgreSQL database server runs as the `postgres` user. The `postgres` user must have at least 711 permission to the following directories:

- `HOME_DIR/pg_data`
- `JOURNAL_DIR/pg_xlog`
- `TMP_DIR/pg_tmp`
- `SPOOL_DIR/pglogs`
- The firewall must allow access to port 5432 for `localhost`
- SLES: The `postgres` user must be set to use a shell in `/etc/password`. (By default, the `postgres` user's shell is set to `/bin/false`.)

For configuration parameters specific to Postgres, see "base Object Parameters" on page 278.

For more information about DMF administrative directories, see "DMF Administrative and Store Directories" on page 44.

## Server Node Requirements

A DMF server node requires the following:

- SGI x86\_64 hardware
- One of the following operating systems as documented in the ISSP release note:
  - Red Hat Enterprise Linux (RHEL)
  - SUSE Linux Enterprise Server (SLES)
- DMF server software and associated products distributed with the ISSP release

## Parallel Data-Mover Node Requirements

DMF parallel data-mover nodes require the following:

- SGI x86\_64 hardware
- Same operating system as the DMF server and CXFS metadata server
- DMF parallel data-mover node software (which includes the required underlying CXFS client-only software)

If you use Parallel DMF, you must use OpenVault for those DGs that contain drives on parallel data-mover nodes. See "Parallel DMF Overview" on page 33.

## Mounting Service Requirements

OpenVault requires `ksh`, not `pdksh`.

TMF has no requirements specific to DMF software.

## License Requirements

DMF software is licensed. See Chapter 2, "DMF Licensing" on page 67.

## DMAPI Requirement

For filesystems to be managed by DMF software, they must be mounted with the DMAPI interface enabled. See "Install DMAPI" on page 82.

## SAN Switch Zoning or Separate SAN Fabric Requirement

Drives must be visible only from the active DMF server, the passive DMF server (if applicable), and the parallel data-mover nodes. The drives must not be visible to any other nodes. You must use one of the following:

- Independent switches (in a separate SAN fabric)
- Independent switch zones for CXFS/XVM volume paths and DMF drive paths



---

**Warning:** If the drives are visible to any other nodes, such as CXFS client-only nodes (other than those that are dedicated to being parallel data-mover nodes), data can become corrupted or overwritten.

---

DMF software requires independent paths to drives so that they are not fenced by CXFS. The ports for the drive paths on the switch must be masked from fencing in a CXFS configuration.

XVM must not fail over CXFS filesystem I/O to the paths visible through the tape/disk HBA ports when Fibre Channel port fencing occurs.

## DMF Manager Requirements

DMF Manager has the following requirements:

- The DMF Manager software is installed on the DMF server node.
- One of the following web browsers:
  - Firefox 3.6 and later (*Firefox is the preferred browser*)
  - Internet Explorer versions supported under Windows 7 (ensure that the latest security patches are installed)

---

**Note:** DMF Manager might also work other browsers, but its functionality is not tested.

---

- Before saving or applying configuration changes, you must make and mount the filesystems used for the DMF administrative directories. See "Configure Filesystems and Directories Appropriately for DMF" on page 94.

## DMF SOAP Requirements

To use the DMF SOAP service capability, the software must be installed on the DMF server node.

## DMF Direct Archiving Requirements

DMF direct archiving has the following requirements:

- The archive filesystem must be visible and mounted in the same location on the DMF server and any DMF parallel data-mover nodes. (The DMF server need not be the server of the archive filesystem; for example, the DMF server need not be the Lustre server.)
- The archive filesystem must be visible to DMF clients from which you want to run the `dmarchive(1)` command, but may have the filesystem mounted on a different mount point.
- The archive filesystem must be mounted on the DMF server and any DMF parallel data-mover nodes so that the `root` user is able to access the filesystem with `root` privileges (that is, with `root squashing` disabled).
- The archive filesystem must be fast enough to permit efficient streaming to/from secondary storage. If this is not the case, the speed could be so slow as to render DMF software useless; in that situation, copying the file to a managed filesystem via `cp(1)` and migrating the file may be a better option.

If a filesystem does not meet these requirements, do not add it to the DMF configuration file as an archive filesystem.

## Fast-Mount Cache Requirements

The fast-mount cache feature requires the following at a minimum:

- Migrating at least two copies simultaneously, one copy to the cache (such as COPAN MAID) and at least one copy to a secondary-storage target (such as physical tape).
- Configuring a task to empty the cache.

However, SGI always recommends that you migrate at least two copies to secondary-storage targets in order to prevent file data loss in the event that a migrated



copy is damaged. When using a fast-mount cache, SGI therefore recommends that you migrate at least three copies (one to the cache and two to secondary-storage targets).

See "Use Fast-Mount Cache Appropriately" on page 112.

## Cloud Storage Requirements

DMF software supports the following cloud systems as secondary storage:

- Scality RING private cloud
- Amazon Simple Storage Service (S3) public cloud

---

**Note:** Amazon Glacier is not supported.

---

- Other products that present a service interface that is compatible with S3, in a private cloud

SGI strongly recommends that you migrate at least two copies to secondary-storage targets in order to prevent file data loss in the event that a migrated copy is damaged. A given cloud can be a single point of failure, therefore redundant copies within one cloud do not sufficiently protect against data loss. SGI therefore highly recommends that you migrate data to a second location (to another cloud instance, tape, or disk).

## Mediaflux Environment Requirements

See Arcitecta's Mediaflux documentation for information about using DMF in a Mediaflux environment. In particular, there are certain requirements for configuring DMF and for using `dmaudit(8)` when restoring files in a managed filesystem.

## Administration Tasks

This section discusses the following aspects of DMF administration:

- "Initial Planning" on page 52
- "Installation and Configuration" on page 52
- "Recurring Administrative Duties" on page 53

- "Commands Overview" on page 56

## Initial Planning

DMF software manages two primary resources:

- Free space on managed filesystems
- Pools of secondary-storage media

You can configure those resources in a variety of environments, including the following:

- Support of interactive processing in a general-purpose environment with limited disk space
- Dedicated file servers
- Lights-out operations

You must do the following:

- Evaluate the environment in which DMF software will run.
- Plan for a certain capacity, both in the number of files and in the amount of data
- Estimate the rate at which you will be moving data between the DMF store of data and the native filesystem
- Select autoloaders and media transports that are suitable for the data volume and delivery rates you anticipate

## Installation and Configuration

You will install the DMF server software (which includes the software for TMF and OpenVault) from the ISSP media.

To configure the DMF environment, you must define a set of parameters in the DMF configuration file, typically by using a sample file as a starting point. See:

- "Best Practices for Configuration" on page 87
- Chapter 5, "Installing and Configuring the DMF Environment" on page 165

To make site-specific modifications, see "Customizing DMF" on page 186.

For a detailed example of configuring using COPAN cabinets, see:

- *COPAN MAID for DMF Quick Start Guide*
- *SGI 400 VTL for DMF Quick Start Guide*

## Recurring Administrative Duties

DMF software requires that you perform recurring administrative duties in the following areas:

- "Free-Space Management" on page 53
- "File Ranking" on page 53
- "Offline Data Management" on page 54
- "Data Integrity and Reliability" on page 54

---

**Note:** You can use tasks that automate these duties. A *task* is a process initiated on a time schedule that you determine, similar to a `cron(1)` job. Tasks are defined with configuration file parameters and are described in detail in "taskgroup Object" on page 304 and "LS Tasks" on page 441.

---

### Free-Space Management

You must decide how much free space to maintain on each managed filesystem. DMF software has the ability to monitor filesystem capacity and to initiate file migration and the freeing of space when free space falls below the prescribed thresholds. See Chapter 11, "Automated Space Management" on page 509.

### File Ranking

You must decide which files are most important as migration candidates. When DMF software migrates and frees files, it selects files based on criteria you chose. The ordered list of files is called the *candidate list*. Whenever DMF software responds to a critical space threshold, it builds a new migration candidate list for the filesystem that reached the threshold. See "Generating the Candidate List" on page 510.

## Offline Data Management

DMF software offers the ability to migrate data to multiple locations. Each location is managed by a separate MSP/VG and is usually constrained to a specific type of medium.

Complex strategies are possible when using multiple MSPs, LSs, or VGs. For example, short files can be migrated to a device with rapid mount times, while long files can be routed to a device with extremely high density.

You can describe criteria for MSP/VG selection. When setting up a VG, you assign a pool of volumes for use by that VG. The `dmvoladm(8)` utility provides management of the VG media pools.

You can configure DMF software to automatically merge volumes that are becoming sparse. With this configuration (using the `run_merge_tapes.sh` task for either disk or tape), the media pool is merged on a regular basis in order to reclaim unusable space.

Recording media eventually becomes unreliable. Sometimes, media transports become misaligned so that a volume written on one cannot be read from another. The following utilities support management of failing media:

- `dmatread(8)` recovers data
- `dmatsnf(8)` verifies LS volume integrity

Additionally, the volume merge process built into the LS is capable of effectively recovering data from failed media.

Chapter 14, "Library Servers and Media-Specific Processes" on page 531, provides more information on administration.

## Data Integrity and Reliability

This section discusses the following things that you must do maintain the integrity and reliability of data managed by DMF software:

- "Run Backups" on page 55
- "Audit the Databases and Log files" on page 55
- "Protect Databases from Loss" on page 55
- "Remove Old Logs and Journals" on page 56

- "Hard-Delete Database Entries" on page 56

### Run Backups

DMF software moves only the data associated with files, not the file inodes or directories, so you must still run filesystem backups in order to preserve the metadata associated with migrated files and their directories. You can configure DMF software to automatically run backups of your managed filesystems. See "Back Up Migrated Filesystems and DMF Databases" on page 137.

The `xfsdump(8)` and `xfrestore(8)` utilities are aware of migrated files. The `xfsdump` utility can be configured to dump the data blocks for a file only if it has not yet been migrated. Files that are dual-state, partial-state, or offline have only their inodes backed up.

You can establish a policy of migrating 100% of the files in the managed filesystems before starting a backup, thereby leaving only a small amount of data that must be dumped. This practice can greatly increase the availability of the machine on which DMF software is running because, generally, backup commands must be executed in a quiet environment.

You can configure the `run_full_dump.sh` and `run_partial_dump.sh` tasks to ensure that all files have been migrated. These tasks can be configured to run when the environment is quiet.

See Chapter 4, "Backups and DMF" on page 141.

### Audit the Databases and Log files

Configure DMF software to automatically run `dmaudit` to examine the consistency and integrity of the databases it uses. DMF databases record all information about stored data. The DMF databases must be synchronized with the filesystems that DMF software manages. Much of the work done by DMF software ensures that the DMF databases remain aligned with the filesystems.

### Protect Databases from Loss

You can configure DMF software to periodically copy the databases to other devices on the system to protect them from loss (using the `run_copy_databases.sh` task). This task also uses the `dmdbcheck` utility to ensure the integrity of the databases before saving them.

### Remove Old Logs and Journals

DMF software uses journal files to record database transactions. Journals can be replayed in the event of an unscheduled system interrupt that causes database corruption. You must ensure that journals are retained in a safe place until a full backup of the DMF databases can be performed.

You can configure the `run_remove_logs.sh` and `run_remove_journals.sh` tasks to automatically remove old logs and journals, which will prevent the DMF `SPOOL_DIR` and `JOURNAL_DIR` directories from overflowing.

### Hard-Delete Database Entries

You can configure the `run_hard_deletes.sh` task to automatically remove database entries whose files will never be restored from backup media. See "Cleaning Up Obsolete Database Entries" on page 586.

## Commands Overview

The DMF administrator has access to a wide variety of commands for controlling the DMF environment. This section discusses the following:

- "User Commands" on page 57
- "Licensing Commands" on page 58
- "Configuration Commands" on page 58
- "DMF Daemon and Related Commands" on page 59
- "Space Management Commands" on page 62
- "LS Commands" on page 63
- "DCM MSP Commands" on page 63
- "Disk MSP Command" on page 64
- "Other Commands" on page 64

---

**Note:** The functionality of some of these commands can be affected by site-defined policies; see "Customizing DMF" on page 186.

---

The FTP MSP uses no special commands, utilities, or databases.

## User Commands

End users can run the following commands on DMF clients to affect the manual storing and retrieval of their data:

Command	Description
<code>dmarchive(1)</code>	Directly copies data between DMF secondary storage and a POSIX filesystem that is not managed by DMF software, such as Lustre. It is intended to streamline a work flow in which users work in an archive filesystem and later want to archive a copy of their data via DMF software. For more information about the <code>MIN_ARCHIVE_SIZE</code> parameter, see "filesystem Object Parameters" on page 351.
<code>dmattr(1)</code>	Displays whether files are migrated or not by returning a specified set of DMF attributes (for use in shell scripts).
<code>dmcapacity(1)</code>	Displays an estimate of the remaining storage capacity for each VG in each LS. You can optionally choose to report the data formatted into XML or HTML.
<code>dmcopy(1)</code>	Copies all or part of the data from a migrated file to an online file.
<code>dmdu(1)</code>	Displays the number of blocks contained in specified files and directories on a managed filesystem.
<code>dmfind(1)</code>	Displays whether files are migrated or not by searching through files in a directory hierarchy.
<code>dmget(1)</code>	Recalls the specified files.
<code>dm ls(1)</code>	Displays whether files are migrated or not by listing the contents of a directory.
<code>dmoper(1)</code>	Displays outstanding requests for operator intervention.
<code>dmput(1)</code>	Migrates the specified files.
<code>dmtag(1)</code>	Allows a site-assigned 32-bit integer to be associated with a specific file (which can be tested in the <code>when</code>

clause of particular configuration parameters and in site-defined policies).

`dmversion(1)` Displays the version number of the currently installed DMF software.

The DMF `libdmfusr.so` user library lets you write your own site-defined DMF user commands that use the same application program interface (API) as the above DMF user commands. See Appendix B, "DMF User Library `libdmfusr.so`" on page 681.

Also see Chapter 16, "DMF SOAP Server" on page 597.

## Licensing Commands

The following commands help you to manage DMF licenses:

Command	Description
<code>dmusage(8)</code>	Displays information about the capacity allowed by the DMF licenses and the amount of data that DMF software is currently managing against those licenses.
<code>dmflicense(8)</code>	Prints DMF license information.

## Configuration Commands

The DMF configuration file (`/etc/dmf/dmf.conf`) contains *configuration objects* and associated *configuration parameters* that control the way DMF software operates. By changing the values associated with these objects and parameters, you can control the behavior of DMF software. To modify the configuration file, you can use DMF manager. For information about configuration, see:

- Chapter 5, "Installing and Configuring the DMF Environment" on page 165
- Chapter 6, "DMF Manager" on page 191
- Chapter 7, "DMF Configuration File" on page 271
- Chapter 8, "Parallel DMF Configuration" on page 485

The following man pages are also related to the configuration file:



Man page	Description
<code>dmf.conf(5)</code>	Describes the DMF configuration objects and parameters in detail.
<code>dmconfig(8)</code>	Prints DMF configuration parameters to standard output.

For detailed examples of configuring using COPAN cabinets, see:

- *COPAN MAID for DMF Quick Start Guide*
- *SGI 400 VTL for DMF Quick Start Guide*

### DMF Daemon and Related Commands

The DMF daemon, `dmfdaemon(8)`, communicates with the kernel through a device driver and receives backup and recall requests from users through a socket. The daemon activates the appropriate MSPs and LSs for file migration and recall, maintaining communication with them through unnamed pipes. It also changes the state of inodes as they pass through each phase of the migration and recall process. In addition, the daemon maintains a database containing entries for every migrated file on the system. Updates to database entries are logged in a journal file for recovery. See Chapter 12, "The DMF Daemon" on page 515, for a detailed description of the DMF daemon.



**Caution:** If used improperly, commands that make changes to the daemon database can cause data to be lost.

---

The following administrator commands are related to `dmfdaemon` and the daemon database:

<b>Command</b>	<b>Description</b>
<code>dmaudit(8)</code>	Reports discrepancies between filesystems and the daemon database. This command is executed automatically if you configure the <code>run_audit.sh</code> task.
<code>dmcheck(8)</code>	Checks the DMF installation and configuration and reports any problems.
<code>dmdadm(8)</code>	Performs daemon database administrative functions, such as viewing individual database records.
<code>dmdbcheck(8)</code>	Checks the consistency of a database by validating the location and key values associated with each record and key in the data and key files (also an LS command). If you configure the <code>run_copy_database.sh</code> task, this command is executed automatically as part of the task. The consistency check is completed before the DMF databases are saved.
<hr/> <b>Note:</b> See "Run Certain Commands Only on a Copy of the DMF Databases" on page 125. <hr/>	
<code>dmdbrecover(8)</code>	Applies journal records to a restored backup copy of the daemon database or LS database in order to create an up-to-date sane database.
<code>dmdidle(8)</code>	Causes files in pending requests to be flushed to secondary storage, even if this means forcing only a small amount of data to a volume.
<code>dmdstat(8)</code>	Indicates to the caller the current status of <code>dmfdaemon</code> .
<code>dmdstop(8)</code>	Stops the DMF daemon without consideration for related services.

---

**Note:** To stop DMF, you should normally use the `service(8)` command. See "Starting and Stopping the DMF Environment" on page 181.

For instructions about stopping DMF in an HA environment, see *High Availability Guide for SGI InfiniteStorage*.

---

`dmfdaemon(8)`

Starts the DMF daemon without consideration for related services.

---

**Note:** To start DMF, you should normally use the `service(8)` command. See "Starting and Stopping the DMF Environment" on page 181.

For instructions about starting DMF in an HA environment, see *High Availability Guide for SGI InfiniteStorage*.

---

`dmhdelete(8)`

Deletes expired daemon database entries and releases corresponding MSP/VG space, resulting in logically less active data. This command is executed automatically if you configure the `run_hard_deletes.sh` task.

`dmmigrate(8)`

Migrates regular files that match specified criteria in the specified filesystems, leaving them as dual-state. This utility is often used to migrate files before running backups of a filesystem, hence minimizing the size of the backup image. It may also be used in a DCM MSP environment to force cache files to be copied to secondary storage if necessary.

`dmsnap(8)`

Copies the daemon database and the LS database to a specified location. If you configure the

`run_copy_database.sh` task, this command is executed automatically as part of the task.

### Space Management Commands

The following commands are associated with automated space management, which allows DMF software to maintain a specified level of free space on a filesystem through automatic file migration:

<b>Command</b>	<b>Description</b>
<code>dmfsfree(8)</code>	Attempts to bring the free space and migrated space of a filesystem into compliance with configured values.
<code>dmfsmon(8)</code>	Monitors the free space levels in filesystems configured with automated space management enabled ( <code>auto</code> ) and lets you maintain a specified level of free space.
<code>dmscanfs(8)</code>	Scans DMF filesystems or DCM MSP caches and prints status information to <code>stdout</code> .

See Chapter 11, "Automated Space Management" on page 509, for details.

## LS Commands

The following commands manage the CAT and VOL records for the LS:

<b>Command</b>	<b>Description</b>
<code>dmcatadm(8)</code>	Provides maintenance and recovery services for the CAT records in the LS database.
<code>dmvoladm(8)</code>	Provides maintenance and recovery services for the VOL records in the LS database, including the selection of volumes for merge operations.

Most data transfers to and from secondary storage are performed by components internal to the LS. However, the following commands can read LS volumes directly:

<b>Command</b>	<b>Description</b>
<code>dmatread(8)</code>	Copies data directly from LS volumes to disk.
<code>dmatsnf(8)</code>	Audits and verifies the format of LS volumes.

The following commands check for inconsistencies in the LS database:

<b>Command</b>	<b>Description</b>
<code>dmatvfy(8)</code>	Verifies the contents of the LS database against the daemon database. This command is executed automatically if you configure the <code>run_audit.sh</code> task.
<code>dmdbcheck(8)</code>	Checks the consistency of a database by validating the location and key values associated with each record and key in the data and key files.

## DCM MSP Commands

The following commands support the DCM MSP:

<b>Command</b>	<b>Description</b>
<code>dmdskfree(8)</code>	Manages file space within the disk cache and as needed migrates files to a lower tier and/or removes them from the disk cache.

<code>dmdskvfy(8)</code>	Verifies disk MSP file copies against the daemon database.
--------------------------	--

### Disk MSP Command

The following command supports the disk MSP:

<b>Command</b>	<b>Description</b>
<code>dmdskvfy(8)</code>	Verifies disk MSP file copies against the daemon database.

### Other Commands

The following commands are also available:

<b>Command</b>	<b>Description</b>
<code>dmcancel(8)</code>	Cancels some types of DMF requests by request ID.
<code>dmclripc(8)</code>	Frees system interprocess communication (IPC) resources and token files used by <code>dmlockmgr</code> and its clients when abnormal termination prevents orderly exit processing.
<code>dmc collect(8)</code>	Collects relevant details for problem analysis when DMF software is not functioning properly. You should run this command before submitting a bug report to SGI Support, should this ever be necessary.
<code>dmcopan(8)</code>	Provides detail about a COPAN MAID volume serial number (VSN) and its associated metadata.
<code>dmdate(8)</code>	Performs calculations on dates for administrative support scripts.
<code>dmdump(8)</code>	Creates a text copy of an inactive database file or a text copy of an inactive complete daemon database.

---

**Note:** See "Run Certain Commands Only on a Copy of the DMF Databases" on page 125.

---

<code>dmdumpj(8)</code>	Creates a text copy of DMF journal transactions.
-------------------------	--

<code>dmfill(8)</code>	Recalls migrated files to fill a percentage of a filesystem. This command is mainly used in conjunction with backup and restore commands to return a corrupted filesystem to a previously known valid state.
<code>dmlockmgr(8)</code>	Invokes the database lock manager. The lock manager is an independent process that communicates with all applications that use the DMF databases, mediates record lock requests, and facilitates the automatic transaction recovery mechanism.
<code>dmmove(8)</code>	Moves copies of a migrated file's data to the specified MSPs/VGs.
<code>dmmvtree(8)</code>	Moves files from one managed filesystem to another without requiring that file data be recalled.
<code>dmov_keyfile(8)</code>	Creates the file of DMF OpenVault keys, ensuring that the contents of the file are semantically correct and have the correct file permissions. This command removes any DMF keys in the file for the OpenVault server system and adds new keys at the front of the file.
<code>dmov_loadtapes(8)</code>	Scans a library for volumes not imported into the OpenVault database and allows the user to select a portion of them to be used by a VG. The selected volumes are imported into the OpenVault database, assigned to the DMF application, and added to the LS database. This command can perform the equivalent actions for the filesystem backup scripts; just use the name of the associated task group instead of the name of a VG.
<code>dmov_makecarts(8)</code>	Makes the volumes in one or more LS databases accessible through OpenVault by importing into the OpenVault database any volumes unknown to it and by registering all volumes to the DMF application not yet so assigned. This command can perform the equivalent actions for the filesystem backup scripts; just use the name of the associated task group instead of the name of a VG.
<code>dmprojid(8)</code>	Sets or displays a file's site-defined project ID.

dmqview(8)	Display information about the internal DMF processing queues
dmrepri(8)	Reprioritizes recall and dmcopy request by daemon request ID.
dmrestore(8)	Restores DMF attributes to a file.
	<hr/> <p><b>Caution:</b> This command is intended to be used in certain recovery scenarios; used incorrectly, it could cause DMF file-consistency issues. You should use this command only at the direction of SGI Support.</p> <hr/>
dmselect(8)	Selects migrated files based on given criteria. The output of this command can be used as input to dmmove(8).
dmsort(8)	Sorts files of blocked records.
dmstat(8)	Displays a variety of status information about the DMF environment, including details about the requests currently being processed by the daemon, statistics about requests that have been processed since the daemon last started, and details of current drive usage by VGs.
dmtapestat(8)	Displays drive metrics for the entire DMF installation. You execute this command as root from the DMF server.
dmunput(8)	Recalls files and removes them from DMF management. You execute this command as root.
dmxfsrestore(8)	Calls the xfsrestore(8) command to restore files backed up to volumes that were produced by DMF administrative maintenance scripts.
sgi-ltfs	Manages Linear Tape File System (LTFS) cartridges and drives.
tsreport(8)	Displays information about tape drive errors, alerts, and usage when the ts tape driver is used. The tsreport command is included in the apd RPM.



## DMF Licensing

This chapter discusses the following:

- "DMF License Types" on page 67
- "Anticipating Your DMF Data Capacity Requirements" on page 69
- "Displaying Current DMF Data Capacity Use" on page 72
- "Parallel Data-Mover Option and Licensing" on page 74
- "Mounting Services and Licensing" on page 74
- "Gathering the Host Information" on page 74
- "Obtaining the License Keys" on page 75
- "Installing the License Keys" on page 75
- "Verifying the License Keys" on page 75
- "For More Information About Licensing" on page 79

### DMF License Types

DMF uses software licensing based on SGI License Keys (LK). A production DMF environment requires that the following licenses are installed on the DMF server node: <sup>1</sup>

- *DMF server capability license.*
- One or more *DMF Parallel Data-Mover Option capability licenses* (if applicable).
- One or more cumulative *DMF data-capacity licenses* (*base* and optional *incremental*), available in different amounts, as shown in Table 2-1.

---

<sup>1</sup> To support training and functional demonstrations, DMF will run on a server with no license at all up to a maximum stored capacity of 1 TB without TMF or OpenVault.

At least one base data-capacity license is required. If multiple base data-capacity licenses are installed, they are additive.

In order to install an incremental data-capacity license, the total data capacity amount already installed (base plus incremental) must equal or exceed the amount of the new incremental amount. For example, to install a new 100TB+ incremental license, the environment must already be licensed for a total of 100 TB, which could be accomplished by several licensing methods, including any of the following:

- One 100TB base license
- One 10TB base license plus nine 10TB+ incremental licenses
- Two 10TB base licenses plus eight 10TB+ incremental licenses

---

**Note:** Some combinations are more cost-effective than others. For details about acquiring the proper set of licenses for your site, contact SGI Support.

---

**Table 2-1** Data-Capacity License Amounts

Base Data-Capacity Amount	Incremental Data-Capacity Amount
10TB	10TB+
100TB	100TB+
1PB	1PB+
10PB	

In a high-availability (HA) environment, the passive DMF server requires the following licenses: a *DMF HA capability license* and a set of Parallel Data-Mover Option licenses and DMF data-capacity licenses equivalent to those on the active DMF server. For example, an HA DMF environment using two parallel data-mover nodes and an amount of managed data that requires two data-capacity licenses would require the following, as shown in Figure 2-1:

- Active DMF server:
  - 1 DMF server capability license
  - 2 Parallel Data mover Option capability licenses

- 2 DMF data-capacity licenses
- Passive DMF server:
  - 1 DMF HA capability license
  - 2 Parallel Data-Mover Option capability licenses
  - 2 DMF data-capacity licenses




Figure 2-1 DMF Licenses

## Anticipating Your DMF Data Capacity Requirements

DMF charges data against the license capacity when a file is scheduled for migration, either via a manual request (such as from a `dmput` command) or via an automated space-management operation (such as `dmfsfree`). The entire size of the file (including holes) is used in this calculation, not the amount of data in the file. DMF does not charge for files that are in regular state (`REG`).

---

**Note:** DMF only charges for the size of the original file, no matter how many copies are placed on DMF media; you can make as many copies as you like. The location of copies and their specific migration state do not affect the capacity license. For example, a dual-state file and an offline file are treated identically.


---

Therefore, you must install sufficient data-capacity licenses to cover the total size all of the files in all managed filesystems that have a state other than regular.

DMF credits data to the license capacity if the original file is deleted, modified, or removed from DMF management via a `dmunput(1)` command. The data in the DMF copies will be maintained under DMF management until the database entry for the file is hard-deleted, but its data will not count against the DMF license.

Figure 2-2 illustrates the concepts of the capacity license. In this example, 20 MB are charged against the license:

- FileA has a size of 10 MB, but it has 9 MB of data and a 1-MB hole. It has been migrated to three DMF copies in three VGs in a library server. Because the data still resides in the managed filesystem, the file is dual-state (DUL). The license is charged 10 MB for FileA.
- FileB has a size of 10 MB. It has been fully migrated to two copies, one on `msp1` and another on `msp2`. No file data resides in the managed filesystem, so the file is in offline state (OFL). The license is charged 10 MB for FileB.
- FileC has a size of 10 MB, but because it is in regular state, it is not charged at all against the license.



**Figure 2-2** Data that Counts Towards the Capacity License

## Displaying Current DMF Data Capacity Use

The `dmusage(8)` command or the **Show Usage** page in DMF Manager (see "Showing Current DMF Usage and Licensed Capacity" on page 205) will output information about the current DMF license capacity and the total number of bytes being managed by DMF.

There are two classes of DMF management displayed:

- **Data Under DMF Management** displays (for informational purposes) the total number of bytes that have been written to the following:
  - Library servers
  - Disk cache manager media-specific processes (DCM MSP)
  - Disk MSPs

---

**Note:** Cloud MSP and FTP MSP copies are not included.

---

These values are not the values charged against the DMF license.

- **Data Charged to DMF License** displays the total size of all existing files (including holes) in the managed filesystems that are under any state of DMF control, from migrating (MIG) to offline (OFL). Files in that are in regular (REG) state and the copies made by DMF **do not** apply against the license.

These values will be smaller than the first class, because they do not include the following:

- Copies made by DMF to any LS or MSP
- Previously migrated files that have since been modified (and therefore placed back into regular state) or deleted. (This type of file is considered *soft-deleted* because its data might still reside on backup media. The file's data remains under DMF management until it has been hard-deleted, in case it is eventually restored. Soft-deleted files are not charged against the license.)

---

**Note:** The values displayed may be as much as 2 minutes out of date. Actions taken to delete files to get the filesystem usage back in compliance with the license will be acted on immediately by the daemon, but there may be a delay before they appear in the output of this command.

---

For example:

```
# dmusage
```

```
          Data Under DMF Management
    (does not include cloud or FTP MSPs)
```

Store Type	Name	Bytes Managed
-----	----	-----
Library Server	ls_copan	1015263000000 (1TB)
Disk MSP	dcm	868163584 (868MB)
		-----
Total bytes managed		1016131163584 (1TB)

```
          Data Charged to DMF License by Filesystem
```

Mount Point	Bytes Managed
-----	-----
/dmiusr1	511090800000 (511GB)
/dmiusr2	480055000000 (480GB)
/dmiusr3	9277697 (9MB)
/dmiusr4	646822912 (646MB)
	-----
Total charged to license	991801900609 (991GB)
DMF license capacity	1000000000000 (10TB)
Percent of license capacity	9

The DMF daemon compares the amount of data that DMF is currently managing against the licensed capacity and takes action if the following thresholds are exceeded:

- At 95%, the daemon will send a warning alert once per day.
- At 100%, the daemon will send a critical alert once per day. DMF will continue to function and will recall any data that has already been migrated, but further migrations will not be allowed. The daemon will check once every 2 minutes to see if the usage once again becomes legal (below capacity). This can be achieved by either of the following:
  - Deleting managed data
  - Adding one or more capacity licenses in order to increase the cumulative capacity total to the new desired limit.

---

**Note:** In order to install an incremental capacity license, the total capacity amount already installed (base plus incremental) must equal or exceed the amount of the new incremental amount. See "DMF License Types" on page 67.

---

The daemon will issue another alert when the usage once again becomes legal (below capacity).

## Parallel Data-Mover Option and Licensing

Each *active parallel data-mover node* requires a corresponding license on the DMF server. DMF will allow as many DMF parallel data-mover nodes to become active at one time as there are DMF parallel data mover licenses in the DMF server's license file. (However, a parallel data mover license is not required for the DMF server's integrated data mover functionality.) No license is installed on the parallel data-mover node itself.

## Mounting Services and Licensing

Use of the TMF or OpenVault mounting service requires DMF licenses.

## Gathering the Host Information

When you order DMF, you will receive entitlement IDs for the licenses you purchased. You must submit the system host ID, host name, and entitlement IDs when requesting your permanent DMF license keys.

To obtain the host information for a server, view the **Licenses** panel in DMF Manager. See "Managing Licenses and Data Capacity with DMF Manager" on page 203.

You could also execute the following command:

```
/usr/sbin/lk_hostid
```



For example, the following shows that the serial number is 000423d5fd92 and the license ID is 23d5fd92:

```
# /usr/sbin/lk_hostid
000423d5fd92 23d5fd92 socket=1 core=2 processor=2
#-----
#The above is the default selected by lk_hostid. See below for additional
#hostid pairs.
#-----
#Interface  SN                      LI                      Driver ( Comment )
#-----
eth0        000423d5fd92                23d5fd92                e1000
eth1        000423d5fd93                23d5fd93                e1000
```

## Obtaining the License Keys

To obtain your DMF license keys, see information provided in your customer letter and the following web page:

<http://www.sgi.com/support/licensing>

## Installing the License Keys

To install the license keys, copy them into the `/etc/lk/keys.dat` file or use the **Licenses** panel in DMF Manager to add the licenses (see "Adding New Licenses" on page 203).

## Verifying the License Keys

You can verify your licenses in the following ways:

- "DMF Manager Licenses Panel" on page 76
- "dmflicense" on page 77
- "lk\_verify" on page 77

## DMF Manager Licenses Panel

You can view the **Licenses** panel in DMF Manager to determine the validity of the licenses, as shown in Figure 2-3. You must log in as the `Admin` user to DMF Manager in order to change licenses.




Figure 2-3 Licenses

For more information, see "Managing Licenses and Data Capacity with DMF Manager" on page 203.

**dmflicense**

You can use the `dmflicense(8)` command to verify the license keys. To see more output, use the `-v` option. For example:

```
# dmflicense -v
File /etc/lk/keys.dat, line 6 is a valid DMF_SERVER license
File /etc/lk/keys.dat, line 24 is a valid DMF_PDMO license
File /etc/lk/keys.dat, line 29 is a valid DMF_PDMO license
File /etc/lk/keys.dat, line 12 is a valid DMF_CAPACITY TB=100 license
File /etc/lk/keys.dat, line 18 is a valid DMF_CAPACITY TB=100+ license
Valid DMF license found.
DMF capacity is 200TB.
```

**lk\_verify**

You can use the `lk_verify(1)` command with the `-A` option to verify LK licenses. To see more output, use the `-v` option (you can use multiple times to display more output). For example:

```
# lk_verify -A -vvv
lk_check      All      All : total found=4

1 /etc/lk/keys.dat:004      product=DMF_SERVER, version=6.000, count=0, begDate=1360172384, \
  expDate=0, licenseID=48bbb244, key=QPGc978utPAnG05MJpQ518sbjgSX3QE5, \
  info='DMF 6.X Server', vendor='Silicon Graphics International', \
  ref_id='270506'
  Verdict:      SUCCESS. Nodelock. Uncounted.
                Available since today.
                No End Date.

  Attribute 1 of 3 : info=DMF 6.X Server
  Attribute 2 of 3 : vendor=Silicon Graphics International
  Attribute 3 of 3 : ref_id=270506

2 /etc/lk/keys.dat:009      product=DMF_HA, version=6.000, count=0, begDate=1360172520, \
  expDate=0, licenseID=48bbb244, key=CT7LtCI/C8vYc2JwS6k5BlYoeSVHDKsm, \
  info='DMF 6.X HA', vendor='Silicon Graphics International', ref_id='270507'
  Verdict:      SUCCESS. Nodelock. Uncounted.
                Available since today.
```

## 2: DMF Licensing

---

No End Date.

Attribute 1 of 3 : info=DMF 6.X HA  
Attribute 2 of 3 : vendor=Silicon Graphics International  
Attribute 3 of 3 : ref\_id=270507

3 /etc/lk/keys.dat:014 product=DMF\_PDMO, version=6.000, count=0, begDate=1360172608, \  
expDate=0, licenseID=48bbb244, key=C8goMD0VwCtdIa8XIsbw94gidnYs+zIC, \  
info='DMF 6.X PDMO 1',attr='NODE 1', vendor='Silicon Graphics International', \  
ref\_id='270508'

Verdict: SUCCESS. Nodelock. Uncounted.  
Available since today.  
No End Date.

Attribute 1 of 4 : info=DMF 6.X PDMO 1  
Attribute 2 of 4 : attr=NODE 1  
Attribute 3 of 4 : vendor=Silicon Graphics International  
Attribute 4 of 4 : ref\_id=270508

4 /etc/lk/keys.dat:020 product=DMF\_CAPACITY, version=6.000, count=0, begDate=1360172697, \  
expDate=0, licenseID=48bbb244, key=rn6Jiu3C2yZN8c0SNot5hq/1HSh6wuS9, \  
info='DMF 6.X 10TB Base',attr='TB=10', \  
vendor='Silicon Graphics International',ref\_id='270509'

Verdict: SUCCESS. Nodelock. Uncounted.  
Available since today.  
No End Date.

Attribute 1 of 4 : info=DMF 6.X 10TB Base  
Attribute 2 of 4 : attr=TB=10  
Attribute 3 of 4 : vendor=Silicon Graphics International  
Attribute 4 of 4 : ref\_id=270509

lk\_check All All : total matched=4

## **For More Information About Licensing**

To request software keys or information about software licensing, see the following web page:

<http://www.sgi.com/support/licensing>

If you do not have access to the web, contact your local Customer Support Center.



## Best Practices for DMF

This chapter discusses the following:

- "Best Practices for Installation, Upgrade, and Downgrade" on page 81
- "Best Practices for Configuration" on page 87
- "Best Practices for Administration" on page 123
- "Best Practices for Backups" on page 137
- "Best Practices for Optional Tasks" on page 138

### Best Practices for Installation, Upgrade, and Downgrade

This section discusses the following:

- "Use the Correct Mix of Software Releases" on page 81
- "Install DMAPi" on page 82
- "Do Not Use YAST to Configure Network Services" on page 83
- "Upgrade Nodes in the Correct Order" on page 83
- "Take Appropriate Steps when Upgrading DMF" on page 84
- "Contact SGI Support to Downgrade After Using OpenVault™ 4.0 or Later" on page 87

### Use the Correct Mix of Software Releases

In a production system, the active DMF server, the passive DMF server (in a high-availability environment), and any DMF parallel data-mover nodes should run the same versions of the following, as supported by a given InfiniteStorage Software Platform (ISSP) release:

- Operating system
- DMF

- CXFS (in a system with parallel data-mover nodes)

For details, see the ISSP release notes.

To support upgrading without having to take down the whole environment, nodes can temporarily run different releases during the upgrade process, as provided by the CXFS rolling upgrade procedure.



---

**Caution:** You must upgrade all CXFS server-capable administration nodes before upgrading any CXFS client-only nodes (including any parallel data-mover nodes, which are CXFS client-only nodes). Client-only nodes can temporarily run an earlier release than the server-capable administration nodes, during the upgrade process. Client-only nodes can never run a later release than the server-capable administration nodes.

Operating a cluster with client-only nodes running a mixture of older and newer CXFS versions may result in a performance loss. Relocation to a server-capable administration node that is running an older CXFS version is not supported.

Although CXFS client-only nodes (including DMF parallel data-mover nodes) that are not upgraded might continue to operate without problems, new functionality may not be enabled until all nodes are upgraded; SGI does not provide support for any problems encountered on the nodes that are not upgraded.

---

For details, see the section about CXFS release versions and rolling upgrades in the *CXFS 7 Administrator Guide for SGI InfiniteStorage*.

## Install DMAPI

Data Management API (DMAPI) is the mechanism between the kernel and the XFS or CXFS filesystem for passing file management requests between the kernel and DMF. Ensure that you have installed DMAPI and the appropriate patches, and that you mount filesystems with the appropriate options. See "Use the Correct Mount Options" on page 99.



## Do Not Use YAST to Configure Network Services

If you try to configure network services using YAST and you are using DHCP, YAST will modify the `/etc/hosts` file to include the following entry, where `hostname` is the name of your machine:

```
127.0.0.2 hostname hostname
```

The above line will prevent `ov_admin(8)` from working because there cannot be multiple IP addresses defined for the DMF server hostname. You will see an error such as the following:

```
The OpenVault server name "hostname" matches this host's hostname,  
but network packets for this hosts's IP address:
```

```
127.0.0.2
```

```
are not being accepted by any installed ethernet card, so there appears  
to be a problem with the configuration of /etc/hosts. Please correct  
this problem before continuing.
```

If you are using OpenVault, you should do one of the following:

- Remove the `127.0.0.2` line from the `/etc/hosts` file prior to configuring OpenVault
- Do not use YAST to configure network services

## Upgrade Nodes in the Correct Order

You should upgrade nodes in the following order:

1. Passive DMF server (if using HA)
2. OpenVault server
3. Active DMF server
4. Parallel data-mover nodes (if used)
5. DMF clients

## Take Appropriate Steps when Upgrading DMF

---

**Note:** If you are upgrading from DMF 3.9 or earlier, see the information about upgrade caveats in the ISSP release note for more information.

---

To perform an upgrade, do the following:

1. Read the ISSP release note, DMF release note, and any late-breaking caveats on the online download page. Pay particular attention to any installation and upgrade caveats.
2. Stop all applications that are writing data to the managed filesystems.
3. Save the established DMF and mounting service configurations to an external storage medium.
4. Ensure that DMF is stopped. In an HA environment, see *High Availability Guide for SGI InfiniteStorage*. In a non-HA environment, execute the following:

```
dmfserver# service dmf stop
```



**Caution:** For instructions about starting and stopping DMF and the mounting service in an HA environment, see *High Availability Guide for SGI InfiniteStorage*.

---

5. Ensure that the applicable mounting service is stopped. In a non-HA environment, execute the following (assuming for simplicity that the DMF server is also the mounting-service server):

- TMF:

```
dmfserver# service tmf stop
```

- OpenVault:

```
dmfserver# service openvault stop
```

6. If the DMF administrative directories are in XFS filesystems, make a copy of the `fstab(5)` file. For example:

```
dmfserver# cp /etc/fstab /myupgrade/fstab
```

7. Make a copy of the following:

- a. The DMF configuration file `dmf.conf`. For example:

```
dmfserver# cp /etc/dmf/dmf.conf /myupgrade/dmf.conf
```

- b. The mounting service configuration information:

- TMF: copy the `tmf.config` file to a safe location. For example:

```
dmfserver# cp /etc/tmf/tmf.config /myupgrade/tmf.config
```

- OpenVault (if the OpenVault configuration is set up on the boot partition and not under a DMF administrative directory): create a compressed file of the OpenVault configuration directory `/var/opt/openvault`. For example:

```
# cd /var/opt
# /bin/tar cf /myupgrade/somefile.tar openvault/*
# /usr/bin/compress /myupgrade/somefile.tar
```

- c. Networking files for `exports(5)`, `auto.master(5)`, and `resolve.conf(5)`. For example:

```
# cp /etc/exports /myupgrade/exports
# cp /etc/auto.master /myupgrade/auto.master
# cp /etc/resolve.conf /myupgrade/resolve.conf
```

8. Upgrade the operating system software to the level supported by the version of DMF that you are upgrading to, paying particular attention to any installation and upgrade caveats in the release notes and any late-breaking caveats on the online download page.
9. If your DMF administrative directories are in XFS filesystems, do the following:

---

**Note:** To avoid copying the `fstab` information from a previous partition, **do not copy** the saved `/myupgrade/fstab` file to the new `/etc` directory in the upgraded system.

---

- a. Use the `cat(1)` command to view the previous `fstab` file:

```
# cat /myupgrade/fstab
```

The following is an example of how DMF administrative directories and user directories that are managed by DMF (in this case, /dmfusr1 and /dmfusr3) could be set up within /etc/fstab:

```
/dev/lxvm/home      /dmf/home      xfs      defaults      0 0
/dev/lxvm/journals  /dmf/journals  xfs      defaults      0 0
/dev/lxvm/move      /move          xfs      dmi,mtpt=/move 0 0
/dev/lxvm/spool     /dmf/spool     xfs      defaults      0 0
/dev/lxvm/cache     /dmf/cache     xfs      dmi,mtpt=/dmf/cache 0 0
/dev/lxvm/tmp       /dmf/tmp       xfs      defaults      0 0
/dev/lxvm/dmfusr1   /dmfusr1      xfs      dmi,mtpt=/dmfusr1 0 0
/dev/lxvm/dmfusr3   /dmfusr3      xfs      dmi,mtpt=/dmfusr3 0 0
```

- b. Verify the existence of the matching XFS devices on the upgraded system by using the `ls(1)` command:

```
# ls -al /dev/lxvm*
```

- c. Copy and paste the DMF administrative directory entry lines (those that contain /dmf/*directoryname*) from the copy of the `fstab` file (/myupgrade/fstab) into the new /etc/fstab for the upgraded system.

10. Reestablish the files and directories copied in step 7 above to their normal locations on the upgrade system. For example:

```
# cp /myupgrade/dmf.conf /etc/dmf/dmf.conf
# cp /myupgrade/exports /etc/exports
# cp /myupgrade/auto.master /etc/auto.master
# cp /myupgrade/resolv.conf /etc/resolv.conf
```

If TME, also:

```
# cp /myupgrade/tmf.config /etc/tmf/tmf.config
```

If OpenVault (and if the OpenVault configuration is set up on the boot partition and not under a DMF administrative directory), also do the following, for example:

```
# cd /var/opt
# /bin/tar xf /myupgrade/somefile.tar.Z
```

11. Follow upgrade instructions in the ISSP release note to update the DMF and mounting service software.

12. Run the `dmcheck(8)` command, which will identify any issues with using your existing DMF configuration file with the upgraded software.

## Contact SGI Support to Downgrade After Using OpenVault™ 4.0 or Later

If you are running OpenVault and want to downgrade after using OpenVault 4.0 or later, you must contact SGI support for assistance.

## Best Practices for Configuration

This section discusses the following:

- "Plan Ahead for Disaster Recovery" on page 88
- "Ensure Quick Communication Among Nodes in the DMF Environment" on page 91
- "Enable RSCN Suppression Appropriately" on page 93
- "Follow All DMF Requirements" on page 93
- "Use Supported Libraries and Tape Drives" on page 94
- "Use Sufficiently Fast Filesystems" on page 94
- "Configure Passwordless SSH" on page 94
- "Configure Filesystems and Directories Appropriately for DMF" on page 94
- "Migrate at Least Two Copies of a File" on page 100
- "Safely Make Changes to the DMF Configuration" on page 100
- "Use Inode-Resident Extended Attributes and 256-byte Inodes" on page 104
- "Limit Path Segment Extension Records" on page 104
- "Do Not Change Script Names" on page 104
- "Configure DMF Appropriately with CXFS™" on page 104
- "Improve Drive Performance with an Appropriate VG Zone Size" on page 105
- "Appropriately Force Small Files to Migrate" on page 107

- "Add HBA Drivers to the `initrd` Image" on page 107
- "Set `RECALL_NOTIFICATION_RATE` to 0 if CXFS Range Tokens are Disabled" on page 107
- "Set the `xinetd tcpmux instances` Parameter Appropriately" on page 108
- "Avoid Unintentional File Recall by Filesystem Browsers" on page 108
- "Configure Appropriately for SGI 400 VTL or COPAN MAID Shelves" on page 109
- "Use Migrate Groups Appropriately" on page 111
- "Use Fast-Mount Cache Appropriately" on page 112
- "Use Cloud Storage Appropriately" on page 114
- "Minimize Access Times by Using `NAME_FORMAT`" on page 116
- "Ensure that the Cache Copy is Recalled First" on page 116
- "Use a Task Group to Run `dmmigrate` Periodically" on page 116
- "Restrict the Size of the Alerts and Performance Records Databases" on page 117
- "Prevent Stalled-Recovery Timeout in a Non-HA Environment" on page 118
- "Use Appropriate Tape Barcodes" on page 119
- "Use `dmarchive` to Copy Archive File Data to Secondary Storage" on page 119
- "Use an Appropriate Filesystem for a Disk MSP" on page 121
- "Use Corresponding Drive-Group Names in OpenVault and DMF" on page 121
- "Use a Private Network Interface in a Parallel Environment" on page 121
- "Modify Partial-State Capability with Care" on page 122
- "Use the Correct Child-Process Constraints for a DCM MSP" on page 122
- "Explicitly Specify the Server on OpenVault Commands" on page 122

## Plan Ahead for Disaster Recovery

This section discusses the following:

- "Best Practices to Permit Future Disaster Recovery" on page 89
- "When is Disaster Recovery Possible?" on page 89
- "What Must Be Protected" on page 89
- "Why Backups Are Needed" on page 90
- "Recovery Possibilities" on page 91
- "Best Practices for Performing Disaster Recovery" on page 91

### **Best Practices to Permit Future Disaster Recovery**

The following are best practices that will permit disaster recovery if the need arises:

- Always make multiple copies of migrated data on separate media (see "Migrate at Least Two Copies of a File" on page 100)
- Use the DMF integrated backup method, which includes a disaster-recovery bundle that includes a backup filesystem with the DMF databases and administrative files (see "Best Practices for Backups" on page 137)
- Store backups and at least one data copy off-site to permit recovery in the case of a physical disaster, such as a fire

### **When is Disaster Recovery Possible?**

Disaster recovery is possible if you are using the integrated-backup method. Careful planning and implementation will help you recover if a disaster occurs.

If the DMF database is lost or corrupt and the latest database backup file residing in the backup filesystem becomes inaccessible (either due to filesystem corruption or due the file being in an offline state), you must first restore access to the backup filesystem and subsequently to the DMF database in order to restore the server.


### **What Must Be Protected**

The DMF system is composed of the following pieces:

- DMF databases and administrative files, which store all of the details about how and where file data was migrated to secondary storage. Each file is assigned a unique key, known as a BFID. All transactions committed to the databases are also stored in external journal files for a configurable period of time.

- Filesystem inodes and directory structures, which remain in the managed filesystem. DMF stores an extended attribute in each inode with information specific to DMF, including the BFID. When files are migrated, the data moves offline but the inode remains in the managed filesystem in order to provide persistent access to the filesystem namespace. Because XFS and CXFS are journaling filesystems, all metadata operations to the filesystem are also written to an internal log area.
- File data, which is migrated to secondary storage

All of the above must be present in order for the DMF system to be whole, as depicted in Figure 3-1.



**Figure 3-1** Components Required by the DMF System

### Why Backups Are Needed

When using DMF to make multiple copies of migrated data, you must still perform regular backups in order to protect inodes, directory structures, and unmigrated files; DMF moves only the data associated with files, not the file inodes or directories.

The managed filesystems and the DMF databases should be backed up on a frequent and regular basis.



## Recovery Possibilities

If one migrated copy is lost, data is available from another migrated copy.

If just the DMF database is lost, no transactions will be lost if the journals are applied to the last good database copy that can be restored from one of the backups.

If both the DMF database and the journals are lost, transactions after the last good dump will be lost; however, with some effort, some of these lost transactions might be reconstructed from the DMF logs and the inodes.

If the filesystem is corrupted, the dump files produced in the backup would be used to restore the inodes.

## Best Practices for Performing Disaster Recovery

See "Disaster Recovery Procedures" on page 650.

## Ensure Quick Communication Among Nodes in the DMF Environment

DMF must be able to quickly communicate directly between every potential DMF server node, parallel data-mover node, and potential OpenVault server node using IP addresses (both IPv4 and IPv6) and logical names, without routing. You must therefore ensure that all nodes have a consistent mapping of hostnames to IP addresses, using one of the following methods:

- "Preferred Method: Consistent `/etc/hosts` File on All Nodes and Access Local First" on page 91
- "Acceptable Method: Reliable DNS in a Dedicated HA cluster" on page 93

Each method has advantages and disadvantages, but the `/etc/hosts` method is preferred because it is the fastest and simplest method.

---

**Note:** For simplicity, SGI recommends that you avoid the Network Information Service (NIS).

---

### Preferred Method: Consistent `/etc/hosts` File on All Nodes and Access Local First

A consistent and accurate `/etc/hosts` file provides the fastest look-up because it is cached in memory, and is therefore the preferred method to ensure quick

communication among cluster nodes. However, it requires a manual edit of static files that must be updated individually, and a given file can be accidentally corrupted.

To use the `/etc/hosts` method, do the following:

1. For each node (every potential DMF server node, parallel data-mover node, and potential OpenVault server node), decide if you want to specify the fully qualified domain name or the simple hostname. This decision usually depends upon how the clients are going to resolve names for their client/server programs (such as NFS), how their default resolution is done, and so on. If you use the fully qualified domain name for a particular node, then all of the nodes should use the fully qualified name of that node when defining the IP/hostname information for that node in their `/etc/hosts` files (IPv4 and IPv6).
2. Edit the `/etc/hosts` file so that it contains consistent entries for all nodes and their private interfaces as well. The file has the following format, where *primary\_hostname* can be the simple hostname or the fully qualified domain name:

```
IP_address    primary_hostname    aliases
```

For example:

```
10.0.3.1 priv-server1
10.0.3.2 priv-server2
10.0.3.3 priv-client1
190.0.2.1 server1.example.com server1
190.0.2.2 server2.example.com server2
190.0.2.3 client1.example.com client1
```

3. Add all of these IP addresses to the `/etc/hosts` file on each node.
4. Edit the `/etc/nsswitch.conf` file so that local files are accessed before DNS (or NIS). That is, the `hosts` line in `/etc/nsswitch.conf` must list files first.

For example:

```
hosts:      files dns nis
```

(The order of `dns` and `nis` is not significant to DMF, but `files` must be first.)

For more information, see the `hosts(5)` and `resolve.conf(5)` man pages.

**Acceptable Method: Reliable DNS in a Dedicated HA cluster**

The domain name service (DNS) lets you have a single authoritative source for mapping hostnames to IP addresses (IPv4 and IPv6) and avoids the need to manually edit and update static files on every node. However, it can reduce availability if the DNS service becomes unreliable. If you choose to use the DNS method, you must ensure that it is very reliable, which can involve more work.

To use the DNS method, do the following:

1. Use multiple DNS servers and set up a high-availability (HA) cluster specifically for the DNS IP addresses. Do not include this HA service within a DMF HA cluster; use a dedicated HA cluster.
2. Add the following line to the `/etc/resolv.conf` file so that the resolver will rotate to another DNS server if the current server does not respond within 1 second:

```
options timeout:1 rotate
```

---

**Note:** Having multiple DNS servers is not sufficient, even with the above rotation timeout. An HA cluster is required for reliability.

---

**Enable RSCN Suppression Appropriately**

See "Suppressing RSCN on Host Port HBAs" on page 177.

**Follow All DMF Requirements**

Ensure that you follow all of the requirements for DMF listed in "Requirements" on page 43:

- "Server Node Requirements" on page 48
- "Parallel Data-Mover Node Requirements" on page 48
- "Mounting Service Requirements" on page 48
- "License Requirements" on page 48
- "DMAPI Requirement" on page 48

- "SAN Switch Zoning or Separate SAN Fabric Requirement" on page 49
- "DMF Manager Requirements" on page 49
- "DMF SOAP Requirements" on page 50
- "DMF Direct Archiving Requirements" on page 50
- "Fast-Mount Cache Requirements" on page 50
- "Cloud Storage Requirements" on page 51

### **Use Supported Libraries and Tape Drives**

For the list of supported TMF and OpenVault libraries and supported tape drives, see the DMF release notes.

### **Use Sufficiently Fast Filesystems**

A filesystem on which DMF operates must be fast-enough to permit efficient streaming to/from all secondary storage media. This is particularly important for tape drives, because slow I/O can lead to increased wear on the drive and cartridges (due to excessive stopping and starting of the drive heads).

### **Configure Passwordless SSH**

If you are running DMF in an HA environment or using the Parallel Data-Mover Option, you should configure passwordless secure shell (SSH) so that DMF can properly gather, distribute, and display information. See "Passwordless SSH Configuration for DMF" on page 176.

### **Configure Filesystems and Directories Appropriately for DMF**

This section discusses the following:

- "Do Not Place Administrative and Store Directories in a Managed Filesystem" on page 95
- "Use Different Physical Devices for *HOME\_DIR* and *JOURNAL\_DIR*" on page 95
- "Avoid Root Filesystem Location for a Production System" on page 95

- "Restrict Administrative and Store Directories to DMF Use" on page 95
- "Use CXFS Filesystems with the Parallel Data-Mover Option" on page 96
- "Sizing Guidelines" on page 96
- "Use the Correct Mount Options" on page 99

Also see "DMF Administrative and Store Directories" on page 44.

### Do Not Place Administrative and Store Directories in a Managed Filesystem

A DMF administrative or store directory must not be in filesystem that is managed by DMF.

### Use Different Physical Devices for *HOME\_DIR* and *JOURNAL\_DIR*

To provide the best chance for database recovery, *HOME\_DIR* must be on a different physical device from *JOURNAL\_DIR*.

### Avoid Root Filesystem Location for a Production System

By default, the DMF daemon requires that a DMF administrative directory does not reside in the root filesystem. For testing or demonstration purposes, you can override this requirement for all but *MOVE\_FS* and a DCM MSP *STORE\_DIRECTORY* by using the *ADMDIR\_IN\_ROOTFS* parameter; however, SGI does not recommend overriding the requirement for a production system. See "base Object Parameters" on page 278.

### Restrict Administrative and Store Directories to DMF Use

You will place the DMF administrative and store directories on a general-purpose RAID storage system.

In a production system, SGI in most cases recommends that you restrict these directories to DMF use and make them the mount point of a filesystem, in order to limit the loss of data in the case of a filesystem failure.

The following are **required** to be dedicated to DMF use and to be a filesystem mount point:

*MOVE\_FS* (if used)  
*DCM MSP STORE\_DIRECTORY*  
*DUMP\_DESTINATION* for integrated backups

SGI suggests that other directories also be used exclusively by DMF and to be a filesystem mountpoint, as shown in Table 3-1.

**Table 3-1** DMF Exclusive Use of Filesystems

Required	Suggested
<i>STORE_DIRECTORY</i> for a DCM MSP	<i>STORE_DIRECTORY</i> for a disk MSP
<i>DUMP_DESTINATION</i> for integrated backups	<i>HOME_DIR</i>
<i>MOVE_FS</i>	<i>SPOOL_DIR</i>
	<i>JOURNAL_DIR</i>
	<i>TMP_DIR</i>
	<i>DATABASE_COPIES</i>
	<i>CACHE_DIR</i> (if used)

**Use CXFS Filesystems with the Parallel Data-Mover Option**

When using the Parallel Data-Mover Option, the following must be CXFS filesystems or be in CXFS filesystems:

- HOME\_DIR*
- SPOOL\_DIR*
- TMP\_DIR*
- MOVE\_FS*
- CACHE\_DIR* (if used)
- DCM MSP *STORE\_DIRECTORY*

**Sizing Guidelines**

---

**Note:** You must evaluate these guidelines in terms of the specifics at your site, rounding up to allow margin for error.

---

The following sections provide guidelines for sizing the filesystems that DMF requires:

- "*HOME\_DIR* Size" on page 97

- "*JOURNAL\_DIR* Size" on page 98
- "*SPOOL\_DIR* Size" on page 98
- "*TMP\_DIR* Size" on page 98
- "*MOVE\_FS* Performance and Size" on page 98

In general, these filesystems should be sized in terms of gigabytes. Table 3-2 shows the minimum recommended sizes.

**Table 3-2** Minimum Sizes for DMF Directories

Directory	Minimum Recommended Size (GB)
<i>HOME_DIR</i>	500
<i>JOURNAL_DIR</i>	75
<i>SPOOL_DIR</i>	200
<i>TMP_DIR</i>	500
<i>MOVE_FS</i>	Capacity of one new volume

For individual guidelines and requirements for each directory, see the specific parameter descriptions in Chapter 7, "DMF Configuration File" on page 271.

See also "Safely Make Changes to the DMF Configuration" on page 100.

#### ***HOME\_DIR* Size**

*HOME\_DIR* will require approximately the following:

- The daemon and LS databases require approximately 500 MB per 1 million migrated files, per DMF copy. If you make two copies, they would require approximately 1 GB (that is, 500 MB x 2).
- An alerts database of 1 MB can hold approximately 5,400 records.
- A performance records database of 1 MB can hold approximately 5,130 records

You can purge old records after specified period of time. See "Restrict the Size of the Alerts and Performance Records Databases" on page 117.

---

**Note:** Other database information (such as the OpenVault server database in an HA configuration) requires an insignificant amount of space in comparison.

---

#### ***JOURNAL\_DIR* Size**

*JOURNAL\_DIR* will require approximately 500 MB per 1 million database operations (such as migrate, recall, and hard delete). You can set the `JOURNAL_RETENTION` parameter to purge old journals after a period of time. The absolute minimum value should be the time since the last successful backup of the DMF databases.

#### ***SPOOL\_DIR* Size**

*SPOOL\_DIR* will require approximately 1 MB per 500 DMF requests. You can set the `LOG_RETENTION` parameter to purge old logs after a period of time.

#### ***TMP\_DIR* Size**

*TMP\_DIR* is used for various temporary storage needs for DMF, such as the following:

- If you do not have a dedicated *CACHE\_DIR* directory, cache merges will use *TMP\_DIR*. The `libraryserver` object's `CACHE_SPACE` parameter controls how much space is used for cache merges.
- If backups are being done to tape, a temporary snapshot of the DMF databases is stored in *TMP\_DIR* before being written to tape. (See `HOME_DIR` for database size.)
- The `run_filesystem_scan.sh` task places its output file in *TMP\_DIR* by default. This file is approximately 150 MB for every 1 million files contained in the managed filesystems.

#### ***MOVE\_FS* Performance and Size**

The *MOVE\_FS* filesystem should have performance characteristics similar to the primary managed filesystems because DMF will follow the same rules for drive utilization as defined in the drive groups (DGs) and VGs (the `DRIVE_MAXIMUM` and `MAX_PUT_CHILDREN` parameters) when moving large numbers of files. A *MOVE\_FS* filesystem with slower bandwidth than what the `DRIVE_MAXIMUM` and `MAX_PUT_CHILDREN` parameters are tuned for may become overloaded with DMF requests. In extreme cases, DMF can become backlogged on *MOVE\_FS* and delay the processing of user requests.



The size of *MOVE\_FS* should be approximately the capacity of a data cartridge, including compression, times the *MAX\_PUT\_CHILDREN* value.

For example:

*500 GB native capacity \* 1.6 compression \* 3 drives = 2.4 TB*

### Use the Correct Mount Options

Table 3-3 on page 99 lists the appropriate mount options for managed filesystems and filesystems that contain DMF administrative directories and store directories.

**Table 3-3** Required and Suggested Mount Options

Directory/Filesystem	Required Mount Options	Suggested Mount Options
Managed filesystems	<i>dmi, mtpt=<i>mountpoint</i></i>	<i>logbufs=8, logbsize=256k</i>
<i>HOME_DIR</i>		<i>logbufs=8, logbsize=256k</i>
<i>SPOOL_DIR</i>		<i>logbufs=8, logbsize=256k</i>
<i>JOURNAL_DIR</i>		<i>logbufs=8, logbsize=256k</i>
<i>TMP_DIR</i>	<i>inode64</i>	<i>logbufs=8, logbsize=256k</i>
<i>DATABASE_COPIES</i>		<i>logbufs=8, logbsize=256k</i>
<i>DUMP_DESTINATION</i> for disk backups		<i>logbufs=8, logbsize=256k</i>
<i>DUMP_DESTINATION</i> for integrated backups	<i>dmi, mtpt=<i>mountpoint</i></i>	<i>logbufs=8, logbsize=256k</i>
DCM MSP <i>STORE_DIRECTORY</i>	<i>dmi, mtpt=<i>mountpoint</i>, dirsync</i>	<i>logbufs=8, logbsize=256k</i>
Disk MSP <i>STORE_DIRECTORY</i>	<i>dirsync</i>	<i>logbufs=8, logbsize=256k</i>
<i>CACHE_DIR</i>	<i>inode64</i>	<i>logbufs=8, logbsize=256k</i>
<i>MOVE_FS</i>	<i>dmi, mtpt=<i>mountpoint</i>, inode64, logbufs=8, logbsize=256k</i>	

Note the following:

- SGI recommends that you do not mount any filesystems with `dmi` other than those displayed above.
- Specify the actual filesystem mount point in `mtpt=mountpoint`.
- Use of the `dirsync` option will ensure the integrity and consistency of `STORE_DIRECTORY` with the DMF daemon database in the event of a system crash and thereby avoid potential data corruption.
- The `logbufs=8,logbsize=256k` mount options tune the XFS log. These settings are especially important for performance on `MOVE_FS`, which will have heavy metadata activity from the quantity of small files that pass through it.

For more information, see the `mount(8)` and `fstab(5)` man pages.

### Migrate at Least Two Copies of a File

When you migrate a file in a DMF configuration, SGI strongly recommends that you make at least two secondary-storage copies of it on separate media to prevent file data loss in the event that a migrated copy is lost.

Note the following:

- Storing multiple copies on the cloud via the `CLOUD_REDUNDANCY` setting for a given cloud MSP does not ensure sufficient data protection in case of file loss. SGI highly recommends that you store a second copy of data on another cloud MSP, on tape, or on disk.
- Because the fast-mount cache configuration requires at least two copies (one to the cache and one to a secondary-storage target), SGI therefore recommends that you migrate at least three copies for this configuration (one to the cache and two to secondary-storage targets). See "Use Fast-Mount Cache Appropriately" on page 112.

### Safely Make Changes to the DMF Configuration

This section discusses the following:

- "Make and Mount the Required Filesystems First" on page 101
- "Use Sample DMF Configuration Files" on page 101
- "Back Up the DMF Configuration File" on page 102

- "Stop DMF Before Making Changes" on page 102
- "Always Validate Your Changes" on page 103

### Make and Mount the Required Filesystems First

You should make and mount the filesystems required for the DMF administrative directories before making configuration changes. If you try to apply configuration changes without having the filesystems referred to in the configuration file in place, you will get errors. See "Configure Filesystems and Directories Appropriately for DMF" on page 94

### Use Sample DMF Configuration Files

DMF is shipped with sample configuration files in the following directory where *DMFVERSION* is a variable that represents the DMF release version:

```
/usr/share/doc/DMFVERSION/info/sample
```

The sample files use a variety of MSPs and LSs for different purposes:

- `dmf.conf.cloud` (cloud MSP)
- `dmf.conf.copan_maid` (COPAN massive array of idle disks)
- `dmf.conf.copan_vtl` (SGI 400 virtual tape library)<sup>1</sup>
- `dmf.conf.disk` (disk MSP)
- `dmf.conf.dcm` (disk cache manager MSP)
- `dmf.conf.fmc` (fast-mount cache, such as for COPAN MAID in conjunction with a physical tape library)
- `dmf.conf.ftp` (FTP MSP)
- `dmf.conf.jbfs` (JBFS using an LS)
- `dmf.conf.ls` (LS)
- `dmf.conf.parallel` (Parallel Data-Mover Option)

---

<sup>1</sup> For historic reasons, the SGI 400 VTL is sometimes referred to as *COPAN* in literals and the graphical user interfaces.

You can edit these files via a file editor such as `vi(1)` or DMF Manager (see "Setting Up a New DMF Configuration File" on page 212). You should always validate your changes; see "Always Validate Your Changes" on page 103.

You can use the information in Chapter 7, "DMF Configuration File" on page 271, and in the `dmf.conf(5)` man page to customize your configuration.

### Back Up the DMF Configuration File

After you have initially successfully configured DMF, make a backup copy of the DMF configuration file (`/etc/dmf/dmf.conf`) so that you can return to it in case of failure. If you are using DMF Manager, it will automatically make a time-stamped backup for you.

If you have an existing configuration, you should ensure that a good backup copy of the DMF configuration file exists before making any configuration changes.

### Stop DMF Before Making Changes

It is safest to make changes to the DMF configuration while DMF is stopped. (For instructions about starting and stopping DMF and the mounting service in an HA environment, see *High Availability Guide for SGI InfiniteStorage*.) If you choose to make changes while DMF is running, be very cautious.



---

**Warning:** Never change pathnames or server names in base object parameters or add, delete, or change the order of `migrategroup` stanzas while DMF is running; making changes of this type can result in data corruption or data loss.

---

Do not change the following parameters while DMF is running:

```
ADMDIR_IN_ROOTFS
CACHE_DIR
COPAN_VSNS
DRIVE_GROUPS
EXPORT_METRICS
GROUP_MEMBERS
LICENSE_FILE
LS_NAMES
MSP_NAMES
MULTIPLIER
OV_KEY_FILE
```

```
OV_SERVER
ROTATION_STRATEGY
SERVER_NAME
SERVICES_PORT
SPOOL_DIR
TMP_DIR
VOLUME_GROUPS
```

Before making changes to any parameter, see the information about it in Chapter 7, "DMF Configuration File" on page 271.

### Always Validate Your Changes

SGI recommends that you always verify any configuration changes you make:

- When using DMF Manager to make changes, select the following to verify the changes:

#### Overview

> **Configuration ...**

> **Validate Current Configuration**

- When using a file editing tool such as `vi` to directly edit the DMF configuration file, you should do the following:

1. Back up the current configuration file. For example:

```
# cp /etc/dmf/dmf.conf /etc/dmf/dmf.conf.$(date +%Y%m%d)
```

2. Copy the current configuration to a test location. For example:

```
# cp /etc/dmf/dmf.conf /etc/dmf/dmf.conf.new
```

3. Edit `/etc/dmf/dmf.conf.new`.

4. Run the `dmcheck(8)` command on the test file:

```
# dmcheck -i /etc/dmf/dmf.conf.new
```

Fix errors and rerun `dmcheck` as needed until it passes without error.

5. Move the test file to the standard location, overwriting the current file:

```
# mv /etc/dmf/dmf.conf.new /etc/dmf/dmf.conf
```

### Use Inode-Resident Extended Attributes and 256-byte Inodes

SGI recommends that you configure your filesystems so that the extended attribute used by DMF is always inode-resident and that you use 256-byte inodes and the default `attr2` (`-i attr=2` option to `mkfs.xfs`) when possible. See "Inode Size Configuration" on page 171.

### Limit Path Segment Extension Records

You should configure your database record length to minimize the number of records that require a path segment extension record. See "Daemon Database Record Length" on page 173.

### Do Not Change Script Names

Do not change the pathnames or script names of the DMF administrative tasks. For more information, see "Automated Maintenance Tasks" on page 175.

### Configure DMF Appropriately with CXFS™

DMF must make all of its DMAPI interface calls through the CXFS active metadata server. The CXFS client nodes do not provide a DMAPI interface to CXFS mounted filesystems. A CXFS client routes all of its communication to DMF through the metadata server. This generally requires that DMF run on the CXFS metadata server. If DMF is managing a CXFS filesystem, DMF will ensure that the filesystem's CXFS metadata server is the DMF server and will use metadata server relocation if necessary to achieve that configuration.

---

**Note:** DMF data-mover processes must run only on the DMF server node and any parallel data-mover nodes. Do not run data-mover processes on CXFS standby metadata server nodes.

---

To use DMF with CXFS, do the following:

- For server-capable administration nodes, install the `sgi-dmapi` and `sgi-xfsprogs` packages from the ISSP release. These are part of the software for the DMF server and **DMF parallel data mover**. The DMF software will automatically enable DMAPI, which is required to use the `dmi` mount option.

For CXFS client-only nodes, no additional software is required.

- When using the Parallel Data-Mover Option, install the software for the DMF parallel data mover, which includes the required underlying CXFS client-only software. (From the CXFS cluster point of view, the DMF parallel data-mover node is a CXFS client-only node but one that is dedicated to DMF data mover activities.) For more information, see:
  - "Parallel DMF Overview" on page 33
  - "Parallel DMF Configuration Procedure" on page 485
- Use the `dmi` option when mounting a filesystem to be managed.
- Start DMF on the CXFS active metadata server for each filesystem to be managed.

See also "SAN Switch Zoning or Separate SAN Fabric Requirement" on page 49.

For more information about CXFS, see:

- *CXFS 7 Administrator Guide for SGI InfiniteStorage*
- *CXFS 7 Client-Only Guide for SGI InfiniteStorage*

## Improve Drive Performance with an Appropriate VG Zone Size

When using an LS, it is critical that the zone size you specify for the VG (the `ZONE_SIZE` parameter) is appropriate for the media speed and average data compression rate at your site. A value that is too small can cause poor write performance because a volume mark is written at the end of each zone; a value that is too large can reduce parallelism when migrating files.

The optimal zone size depends upon several site-specific factors. Answering the following questions will help you determine the correct zone size for your site:

- How long does it take the drive to flush data to media?

---

**Note:** Different drive types have different bandwidths, and the same drive type can have different bandwidths with different cartridge types.

---

- How fast can the drive write data?
- What is the average data compression rate? If your data compresses well, the zone size should be larger; if the data does not compress well, the zone size should be smaller.

A good zone size is one where the time spent flushing data to media is not a significant amount of the total I/O time. For increased write performance, choose a zone size such that the average time to write a volume mark for the drive type is a small percentage (such as 5%) of the time to write a zone at the drive's native rate.

For example, suppose the following:

- The drive requires 2 seconds to flush the data to tape
- The drive writes data at 120 MB/s
- The average compression rate is 2 to 1

In order to waste no more than 5% of the full bandwidth of the drive flushing data to media, the `ZONE_SIZE` value in this case must be large enough to hold 40 seconds (2 seconds / 0.05) worth of data in each zone. Because the drive writes at about 120 MB/s, then  $40 * 120 = 4800$  MB of data that can be written in 40 seconds. Not considering compression, a good preliminary `ZONE_SIZE` value is therefore 5g (5 GB).

Because the example site has a compression rate of 2 to 1, the preliminary `ZONE_SIZE` value should be multiplied by 2; the resulting `ZONE_SIZE` value should be 10g (10 GB), which is how much data will get written in 40 seconds while still keeping the flush waste within 5% of the total bandwidth.

---

**Note:** The zone size influences the required cache space. The value for the `CACHE_SPACE` parameter should be at least twice the value used for `ZONE_SIZE`. Increasing the `ZONE_SIZE` value without also increasing `CACHE_SPACE` could cause volume merging to become inefficient. Volume merges could have problems if the `ZONE_SIZE` value is larger than the `CACHE_SPACE` value. For more information about `CACHE_SPACE`, see "libraryserver Object Parameters" on page 393.

---

For more information about zone size, see the following:



- ZONE\_SIZE parameter in "volume group Object" on page 410
- "Media Concepts" on page 534
- Appendix H, "Case Study: Impact of Zone Size on Tape Performance" on page 781

### Appropriately Force Small Files to Migrate

If you want to quickly migrate small files, you should set `TIMEOUT_FLUSH` to a value that is less than the default of 2 hours but greater than 15 minutes. See "volume group Object Parameters" on page 411.



---

**Caution:** Do not set change `TIMEOUT_FLUSH` to fewer than 15 minutes or set `ZONE_SIZE` to an artificially low value for the purpose of migrating files more quickly; either of these actions may have a negative impact on performance.

---

### Add HBA Drivers to the `initrd` Image

The `ts` tape drive reads HBA information from `sysfs` just after being loaded in order to discover controller information. To ensure that this information is available when `ts` loads, SGI recommends that you add the HBA drivers to the `initrd` image so that they load early in the boot process. Do the following:

1. Add the HBA driver to the `INITRD_MODULES` line in the `/etc/sysconfig/kernel` file. For example, to add the driver QLogic QLA2200, you would include `qla2xxx` in the `INITRD_MODULES` line.
2. Create the initial RAM disk image so that it contains your modification:  

```
# mkinitrd
```
3. Reboot the DMF server.

### Set `RECALL_NOTIFICATION_RATE` to 0 if CXFS Range Tokens are Disabled

In a CXFS environment if CXFS range tokens are disabled, you should specify a value of 0 for the DMF configuration parameter `RECALL_NOTIFICATION_RATE` in order to avoid token thrashing, which can result in poor I/O transfer rates.

Using 0 can slightly improve recall performance in cases where users do not need to access files while they are coming online. (In this case, `dmatrc` does not have to stop and do an `fsync` every 30 seconds during the recall.) The optimum setting of `RECALL_NOTIFICATION_RATE` is dependent on many factors and must be determined by trial and error. See "dmdaemon Object" on page 289.

### Set the `xinetd tcpmux instances` Parameter Appropriately

You must use a sufficient setting for the `tcpmux instances` parameter in either the `/etc/xinetd.conf` file or the `/etc/xinetd.d/tcpmux` file.

Each remote DMF client command will consume one instance of a `tcpmux` service while it is active. For that reason, SGI recommends that you add the `instances` parameter to `/etc/xinetd.d/tcpmux` rather than increasing the `instances` parameter in `/etc/xinetd.conf`.

Determining the correct setting of this parameter depends on what the maximum number of simultaneous remote DMF user commands might be combined with any other `xinetd tcpmux` services that will be used. See the `xinetd(8)` man page for more information on setting the parameter.

Additionally, it is important that the `tcpmux` service is not disabled. If the following configuration line exists in `/etc/xinetd.d/tcpmux`, remove it:

```
disable = yes
```

### Avoid Unintentional File Recall by Filesystem Browsers

Graphical user interface (GUI) filesystem browsers (such as Windows Explorer, GNOME™ Nautilus / File Manager) can unintentionally cause files to be recalled because they read the first few blocks of the file in order to show the correct icon in the view screen:

- Windows Explorer: if you follow the directions in "Modify Settings If Providing File Access via Samba" on page 127, you can avoid this problem for Windows Explorer.
- Nautilus and other filesystem browsers: these filesystem browsers may have settings to prevent them from reading the file for thumbnail icons, but testing is still required because the browser may still read the file for other reasons. Also, file browser behavior may change in future releases, so you must retest after upgrading. You should do one of the following for these filesystem browsers:

- Do not use GUI filesystem browsers on a managed filesystem.
- Set the DMF policy to keep the number of kilobytes permanently on disk required by your filesystem browser, to allow the reading activity to happen without recalling files. Do the following:
  1. Determine how many kilobytes are read by your filesystem browser.
  2. Verify that the partial-files feature is enabled (see `PARTIAL_STATE_FILES` in "dmdaemon Object" on page 289).
  3. Use the `ranges` clause to keep the required number of bytes of each file online. See:
    - "ranges Clause" on page 383
    - "Automated Space-Management Example" on page 386, and "Automated Space-Management Using Ranges Example" on page 387
  4. Repeat the above steps as needed after upgrading the filesystem browser.

See also:

- "Partial-State Files" on page 5
- Appendix G, "Considerations for Partial-State Files" on page 779

## Configure Appropriately for SGI 400 VTL or COPAN MAID Shelves

You can use SGI 400 VTL shelves COPAN MAID shelves either as secondary storage or a cache. For initial configuration, see:

- *COPAN MAID for DMF Quick Start Guide*
- *SGI 400 VTL for DMF Quick Start Guide*

To use DMF with SGI 400 VTL shelves or COPAN shelves, do the following:

- Within reason, create smaller volumes, so that hard-deletes will free-up volumes without requiring merges. In general, a larger number of smaller-sized volumes will result in fewer partially-full volumes in the DMF database (and therefore more room for new data). This can potentially provide faster recalls of migrated data because there are more volumes available for reading and writing (you cannot simultaneously write to and read from the same volume). However, you do not want to use volumes that are unreasonably small, as that might cause

excessive mounts and unmounts. For size recommendations, see the *Quick Start* for your system.

- Set the volume size, so that you can use the `dmcapacity(8)` command or its display in DMF Manager to accurately estimate the remaining capacity of the volumes on the COPAN shelves. See "Set Volume Size If You Want to Use Capacity Features" on page 129.
- Use the sample DMF configuration files:
  - For secondary storage, use `dmf.conf.copan_maid` or `dmf.conf.copan_vtl`.
  - For cache, use `dmf.conf.fmc`. See "Use Fast-Mount Cache Appropriately" on page 112.

Each sample file does the following:

- Uses one OpenVault library control program (LCP) per shelf
  - Uses a shelf with a single DG and a single VG.
  - Uses one or more migrate groups to combine multiple COPAN shelves into a single destination for a migration request
- Set the following parameters, which apply particularly to COPAN shelves, appropriately according to the information in Chapter 7, "DMF Configuration File" on page 271:

```
COPAN_VSNS  
MAX_PUT_CHILDREN  
RESERVED_VOLUMES  
ZONE_SIZE
```

---

**Note:** For COPAN shelves, a larger number for `MAX_PUT_CHILDREN` may provide more total write bandwidth, but the bandwidth increases will diminish rapidly with additional children and all of the children will write more slowly. For COPAN MAID, use a `MAX_PUT_CHILDREN` value in the range 2-6; for SGI 400 VTL, use a `MAX_PUT_CHILDREN` value in the range 2-4.

---

If creating backups via `xfsdump` to disk for COPAN MAID, also set the following parameters appropriately:

COMPRESSION\_TYPE  
DUMP\_COMPRESS  
DUMP\_CONCURRENCY  
DUMP\_DESTINATION  
DUMP\_MIRRORS

- For COPAN MAID, use one VG per shelf.

## Use Migrate Groups Appropriately

If you use migrate groups (MGs), do the following:

- Do not specify overlapping MSPs, VGs, or MGs on the same MSP/VG selection parameter. You must ensure that the statement expands to a set of non-overlapping MSPs and VGs when all of the MG members are considered. See:
  - "MSP/VG Selection Parameters for a Managed Filesystem" on page 374
  - "VG Selection Parameters for a DCM MSP STORE\_DIRECTORY" on page 380
- Never add, delete, or change the order or contents of `migrategroup` stanzas while DMF is running.
- If you want to use a cloud/DCM/FTP MSP as a group member of an MG with a sequential rotation strategy, it should be the last group member listed (because these MSPs are never marked as full by DMF). See "migrategroup Object" on page 426.
- Do not include an MSP or VG that uses the `IMPORT_ONLY` parameter (meaning that the MSP/VG is used only for recalls) in a `migrategroup` stanza. The `dmcheck` command will flag this situation as an error.
- If you specify a `ROTATION_STRATEGY` of `SEQUENTIAL`, all `GROUP_MEMBERS` except the last should be able to report when they are full:
  - For a disk MSP, you should specify `FULL_THRESHOLD_BYTES`.
  - For a VG, you should specify a non-zero value for `RESERVED_VOLUMES`.
  - Because a cloud/DCM/FTP MSP never reports that it is full, if used it must be the last member in the `GROUP_MEMBER` list.

For more information, see:

- "Configure Appropriately for SGI 400 VTL or COPAN MAID Shelves" on page 109
- "volume group Object" on page 410
- "msp Object for a Disk MSP" on page 466

### Use Fast-Mount Cache Appropriately

Using a cache (such as COPAN MAID) in conjunction with other secondary-storage migration targets (such as VGs in a physical tape library) is appropriate if your site has a high turnover of relevant data and therefore the most recently migrated files are also the most likely to be recalled.

To use fast-mount cache environment, do the following:

- Define a `fastmountcache` object for each logically separate fast-mount cache. By using multiple logical fast-mount caches, you can account for differences in the following characteristics:
  - The percentage of free volumes that must be available (minimum and target values)
  - File retention policies
  - Physical library residency
- Set the `CACHE_MEMBERS` parameter to name one or more `migrategroup` and `volume group` objects that constitute the fast-mount cache. The type of object you name will control what DMF considers when determining whether the free-volume threshold has been reached and the number of volumes to therefore be freed (see `FREE_VOLUME_MINIMUM` and `FREE_VOLUME_TARGET` below):
  - If you name a `migrategroup` object, DMF will consider the total number of volumes that constitute that MG
  - If you name a `volume group` object, DMF will consider only the number of volumes that constitute that VG
- Set the following `volume group` object parameters:
  - Set `RESERVED_VOLUMES`:
    - 0 (the default) for a VG that is an independent member of a fast-mount cache (that is, the VG is listed in `CACHE_MEMBERS`)

- 1 for every VG that is part of an MG that is a member of a fast-mount cache (that is, the MG is listed in `CACHE_MEMBERS`)
- Set `MERGE_THRESHOLD` to 0 for any VG that is part of a fast-mount cache (whether it is the MG or the VG that is listed in `CACHE_MEMBERS`)
- Do not assign an `ALLOCATION_GROUP` parameter to any VG that is part of a fast-mount cache (whether it is the MG or the VG that is listed in `CACHE_MEMBERS`)
- Ensure that the fast-mount cache is the first target chosen. See "Ensure that the Cache Copy is Recalled First" on page 116.
- Define two other VGs/MSPs (such as on physical tape) as secondary-storage locations into which file data is copied at the time of initial migration, along with the fast-mount cache location. These VGs and MSPs must not be on a DCM MSP or on another fast-mount cache.

---

**Note:** One other VG/MSP is the minimum requirement, but SGI recommends two so that the recommended two migrated copies will remain after the copy in the fast-mount cache has been deleted.

---

- Do not schedule merging tasks for the `volume` or `migrate` objects that represent the fast-mount cache.
- If two separate fast-mount caches are configured, do not configure any policies that would result in a file being migrated to more than one fast-mount cache.
- Define a `taskgroup` object for the fast-mount cache with a `RUN_TASK` object for the `run_fmc_free.sh` script and the following parameters:
  - Required to free the volume when full:

```
FREE_VOLUME_MINIMUM
FREE_VOLUME_TARGET
```

---

**Note:** Because the volumes can be freed immediately, normally you want to set the above to relatively low values. You must set `FREE_VOLUME_MINIMUM` so that it is less than `FREE_VOLUME_TARGET`.

---

- Optional to ensure that recently accessed files are copied to another volume in the fast-mount cache before the original volume is emptied (which can result in lower performance):

`FILE_RETENTION_DAYS`

- Optional to minimize the competition for disk space by the *MOVE\_FS* scratch filesystem when using `FILE_RETENTION_DAYS`:

`FMC_MOVEFS`

See:

- "dmdaemon Object Parameters" on page 290
- "taskgroup Object Parameters" on page 312
- "taskgroup Object Example for Fast-Mount Cache Tasks" on page 339
- "drivegroup Object Parameters" on page 397
- "volumegroup Object" on page 410
- "Example: LS for Fast-Mount Cache" on page 439

## Use Cloud Storage Appropriately

This section discusses the following:

- "Migrate a Second Copy Outside of the Cloud" on page 114
- "Use a Firewall" on page 115
- "Whitelist Only the DMF Server in a Private Cloud" on page 115
- "Use a Dedicated S3 Bucket" on page 115
- "Improve Throughput for S3" on page 115

Also see "Minimize Access Times by Using `NAME_FORMAT`" on page 116.

## Migrate a Second Copy Outside of the Cloud

When using the cloud MSP, it is not sufficient from a DMF data-protection perspective to have multiple copies stored in a single cloud using the cloud's



redundancy feature; to protect data, you must migrate a second copy to a different cloud, tape, or disk storage. See "Migrate at Least Two Copies of a File" on page 100.

### Use a Firewall

When setting up a firewall, you should add a rule that allows the DMF server to initiate a TCP connection to the port listed in the `CLOUD_HOST` configuration parameter; see "m<sub>SP</sub> Object Parameters for a Cloud MSP" on page 449. The default ports are 81 for Scality and 80 for Simple Storage Service (S3).

---

**Note:** You should also be aware of the security issues listed in "Cloud MSP Limitations and Considerations" on page 572.

---

### Whitelist Only the DMF Server in a Private Cloud

When setting up a private cloud in a production environment, you should use `iptables` rules on the cloud server that deny access by default but whitelist the specific IP addresses that are authorized to use the service.

### Use a Dedicated S3 Bucket

For simplicity when using the S3 cloud, use a bucket that is dedicated to the data migrated by DMF. However, if other applications will use the same bucket, you can use the `CLOUD_BASE_PATH` parameter to provide a prefix to the keys that will help you identify them as data migrated by DMF. See "m<sub>SP</sub> Object Parameters for a Cloud MSP" on page 449.

### Improve Throughput for S3

For an S3 cloud MSP, see the following for more information about improving throughput:

<http://aws.amazon.com/articles/Amazon-S3/1904>

Also see "NAME\_FORMAT Details" on page 446 for information about minimizing access times.

### Minimize Access Times by Using `NAME_FORMAT`

The `NAME_FORMAT` configuration parameter for MSPs consists of substitution strings that form a template for filenames used in secondary storage. You can customize the substitution strings to provide a template that is suited to your site. See "`NAME_FORMAT` Details" on page 446.

### Ensure that the Cache Copy is Recalled First

The fast-mount cache and DCM MSP copies must be used for recall before any other copy in order to take advantage of their faster recall characteristics. To achieve this, you must correctly specify the order of parameter values in the DMF configuration file. Do the following:

- List any DCM MSP names first for the `LS_NAMES` parameter
- List any fast-mount cache LS, DG, and VG names first for the `LS_NAMES`, `DRIVE_GROUPS`, and `VOLUME_GROUPS` parameters, respectively

For more information, see Chapter 7, "DMF Configuration File" on page 271.

### Use a Task Group to Run `dmmigrate` Periodically

Sites whose workflow involves ingesting many files throughout the day in an unpredictable pattern may find that relying on `dmfsfree(8)` alone to migrate these files is insufficient. There may be many files that require migration just prior to running the daily `xfsdump(8)` task, and there may be many new files that require migration.

To avoid these problems, you can use a `taskgroup` object that calls the `run_dmmigrate.sh` script to run the `dmmigrate(8)` command on a regular basis throughout the day to cut down on the amount of work needed prior to an `xfsdump` run. The object that calls the task group determines the scope of the migration and the location of the associated log messages

- If you reference the task from the `dmdaemon` object, `dmmigrate` will be run on all filesystems defined with automated space-management or user space-management enabled. The log messages generated by the script will appear in the `dmdlog` file.
- If you reference the task from either a `filesystem` object or a DCM `mcp` object, `dmmigrate` will migrate data from that object only. Each object can reference the same or different `taskgroup` objects. The log messages generated by the script will

appear in the `autolog` file if the task is called from a `filesystem` object or in the appropriate `misplog` file if called from a DCM `misp` object.

---

**Note:** If the same `taskgroup` is referenced by multiple objects, then there will be separate `dmmigrate` commands running simultaneously for multiple objects. This may result in an unwanted spike in migration requests sent to the daemon.

---

You can modify the operation of `dmmigrate` by using the following configuration parameters in the `taskgroup` object to specify that it will be run with particular `dmmigrate` command-line options:

`DMMIGRATE_MINIMUM_AGE` (-m *minutes*)  
`DMMIGRATE_TRICKLE` (-t)  
`DMMIGRATE_VERBOSE` (-v)  
`DMMIGRATE_WAIT` (-w)

---

**Note:** When enabled, `DMMIGRATE_TRICKLE` (ON by default) only limits the number of requests submitted at a time by an individual `dmmigrate` command. If you define multiple `taskgroup` objects containing the `run_dmmigrate.sh` script that are scheduled to run with overlapping times, it is still possible to flood the DMF daemon with migration requests even if `DMMIGRATE_TRICKLE` is enabled. Therefore, SGI recommends that you to call the `taskgroup` object containing the `run_dmmigrate.sh` script from the `dmdaemon` object in order to migrate files in all managed filesystems with a single command.

---

For more information about these parameters, see:

- "taskgroup Object Parameters" on page 312
- "taskgroup Object Example for Periodic `dmmigrate` Tasks" on page 341
- The `dmmigrate(8)` man page

## Restrict the Size of the Alerts and Performance Records Databases

You should configure tasks to automatically purge old records from the alerts and performance databases, based on the age of the records and the size of the databases:

- `run_remove_alerts.sh` removes records from the alerts database according to the following parameters:

```
ALERT_RETENTION
MAX_ALERTDB_SIZE
REMALERT_PARAMS
```

- `run_remove_perf.sh` removes records from the performance database according to the following parameters:

```
PERF_RETENTION
MAX_PERFDB_SIZE
REMPERF_PARAMS
```

---

**Note:** If you configure a task group to run the above scripts, then you must specify at least one of the retention or database-size parameters. For example, if you specify a task group containing `run_remove_alerts.sh` but you do not include either the `ALERT_RETENTION` or the `MAX_ALERTDB_SIZE` parameter, you will get an error.

---

The sample configuration files provide task groups with recommended starting values:

- An age of 4 weeks for alert and performance records
- A maximum alerts database size of 100 MB
- A maximum performance database size of 256 MB

However, you should modify these values as necessary for your site. SGI recommends that the alerts and performance databases each be less than 512 MB. For approximate size requirements, see "*HOME\_DIR* Size"

See:

- "Overview of the Tasks" on page 304
- "taskgroup Object Parameters" on page 312
- "taskgroup Object Example for Removing Alerts and Performance Records" on page 341

## Prevent Stalled-Recovery Timeout in a Non-HA Environment

If you use CXFS and DMF in a non-HA environment, you must disable the stalled-recovery timeout feature for all potential CXFS metadata servers of managed

filesystems. This will prevent a standby metadata server from experiencing a recovery timeout while waiting for DMF to be manually started.

For example, add the following lines to the `/etc/modprobe.d/sgi-cxfs-xvm.conf` file on all potential CXFS metadata servers for the managed filesystems:

```
# Disable recovery timeout feature to allow for
# manual startup of DMF on the standby MDS during recovery
options sgi-cell cxfs_recovery_timeout_stalled=0
```


See the information about the `cxfs_recovery_timeout_stalled` system tunable parameter in the *CXFS 7 Administrator Guide for SGI InfiniteStorage*.

## Use Appropriate Tape Barcodes

A tape library must be set up to report 8-character barcodes to OpenVault: the first 6 characters provide a unique volume serial number (VSN) and the final 2 characters indicate the media type (such as `L5`, which indicates `LT05` media). Many libraries report 8 characters by default, but some libraries may require modification; for details, see the information about supported libraries and tape drives in the DMF release note.


## Use `dmarchive` to Copy Archive File Data to Secondary Storage

You can use the *direct archiving* feature to manually copy file data between a POSIX filesystem (such as a Lustre™ filesystem) directly to DMF secondary storage by configuring the POSIX filesystem for archive use in the DMF configuration file and using the `dmarchive(1)` command. This POSIX filesystem cannot be DMAPI-enabled (that is, it cannot be mounted with the `dmi` mount option) and is known as an *archive filesystem*. When using this feature, DMF software copies the file data to DMF secondary storage while placing the metadata in a filesystem that is managed by DMF, as shown in Figure 3-2.



**Figure 3-2** Archiving Files from an Archive Filesystem to Secondary Storage

Figure 3-3 shows that the Lustre server is serving the `/lustrefs/work` filesystem, which is mounted on both the DMF server and the DMF client, allowing you to run the `dmarchive` command. The DMF server is managing the `/dmf` filesystem, which is NFS-mounted at `/mnt/dmfusr1` on the DMF client.



**Figure 3-3** DMF Direct Archiving

Without the `dmarchive` command, you would have to first manually copy the file to a managed filesystem and then manually migrate the files. For example:

```
dmfclient% cp -a /lustrefs/work /mnt/dmfusr1
dmfclient% dmput /mnt/dmfusr1/work/*
```

However, using `dmarchive` on a DMF client, you can achieve the same results with a single command:

```
dmfclient% dmarchive -a /lustrefs/work /mnt/dmfusr1
```

Using `dmarchive`, the file data will be copied directly to DMF secondary storage and the file metadata will be copied to the specified managed filesystem (`/dmf`). The `dmarchive` command recursively copies the entire directory structure (similar to `cp -a`), so the metadata will reside in `/dmf/work`.

On retrieval, the data is copied directly from DMF secondary storage to the archive filesystem. The `dmarchive` method is therefore more efficient because it requires less time, bandwidth, and filesystem capacity.

## Use an Appropriate Filesystem for a Disk MSP

If you use a disk MSP, the filesystem should be local for best performance and reliability.

A remote filesystem mounted through NFS or a similar file-sharing protocol is appropriate when testing or when transitioning to a DMF environment.

## Use Corresponding Drive-Group Names in OpenVault and DMF

OpenVault and DMF each have a group of interchangeable devices known as a *drive group*. Despite their use of the same terminology, a DMF drive group is different from an OpenVault drive group, and need not use the same name. However, to avoid confusion, SGI recommends that you use corresponding names for the DMF drive group and the OpenVault drive group whenever possible.

## Use a Private Network Interface in a Parallel Environment

To prevent the possibility of external attack when using the Parallel Data-Mover Option, do the following:

- Set the `INTERFACE` and `MERGE_INTERFACE` parameters to a private network. See "node Object Parameters" on page 294.
- Do not use port scanners on the private network.

## Modify Partial-State Capability with Care

The partial-state file capability is turned on by default and an appropriate default maximum number of regions is calculated at filesystem mount time.

You can use the `MAX_MANAGED_REGIONS` parameter to configure the maximum number of file regions on a per-filesystem basis, but you should use this parameter cautiously. If set capriciously, filesystem scan times can increase greatly. For details about using `MAX_MANAGED_REGIONS`, see "filesystem Object" on page 350.

To turn off the partial-state file feature, set the `PARTIAL_STATE_FILES` daemon configuration parameter to `off`. See "dmdaemon Object Parameters" on page 290.

For additional details, see Appendix G, "Considerations for Partial-State Files" on page 779.

## Use the Correct Child-Process Constraints for a DCM MSP

If your environment uses a DCM MSP, you should ensure that you have appropriate settings for the following parameters in the DMF configuration file:

- `CHILD_MAXIMUM`
- `GUARANTEED_DELETES`
- `GUARANTEED_GETS`

SGI recommends that you use a larger value for `CHILD_MAXIMUM` than the default with a DCM MSP in order to maximize throughput to the DCM *STORE\_DIRECTORY*. The value for `CHILD_MAXIMUM` must be greater than the sum of the values for `GUARANTEED_DELETES` and `GUARANTEED_GETS`.

See "msp Object Parameters for a DCM MSP" on page 460.

## Explicitly Specify the Server on OpenVault Commands

To ensure that OpenVault communicates with the intended server, explicitly specify the `-S server` option on OpenVault commands such as `ov_admin(8)`, `ov_dcp(8)`, `ov_stat(8)`.



## Best Practices for Administration

This section discusses the following:

- "Stop and Start DMF Using the `service` Command" on page 124
- "Use a Time Synchronization Application" on page 124
- "Monitor DMF Daily" on page 125
- "Run Certain Commands Only on a Copy of the DMF Databases" on page 125
- "Be Aware of Differences in an HA Environment" on page 125
- "Start Site-Specific Configuration Parameters and Stanzas with `"LOCAL_"`" on page 125
- "Use TMF Tracing" on page 126
- "Run `dmc collect` If You Suspect a Problem" on page 126
- "Modify Settings If Providing File Access via Samba" on page 127
- "Export from the Active CXFS Metadata Server" on page 128
- "Disable Journaling When Loading an Empty Database" on page 128
- "Use Sufficient Network Bandwidth for Socket Merges" on page 128
- "Temporarily Disable Components Before Maintenance" on page 128
- "Gracefully Stop the COPAN Disks and JBFS Disks" on page 129
- "Reload STK ACSLS Cartridges Properly" on page 129
- "Disable Zone Reclaim to Avoid System Stalls" on page 129
- "Set Volume Size If You Want to Use Capacity Features" on page 129
- "Monitor the Size of the PCP Metrics Archive" on page 130
- "Be Aware that API Commands Change Without Notice" on page 130
- "Be Aware of Memory-Mapping Issues" on page 131
- "Use a Task to Perform Hard-Deletes Periodically" on page 131
- "Enable the Enhanced-NFS RPC Corruption Workaround Parameter if Needed" on page 131

- "Use the Appropriate Tool to Load Volumes to an Existing Environment" on page 132
- "Configure Fibre Channel Switches and Zones Appropriately" on page 132
- "Use `dmmove(8)` Safely" on page 136
- "RHEL: Disable SELinux or Increase the Inode Size" on page 136
- "Apply Appropriate PostgreSQL Updates" on page 136

### Stop and Start DMF Using the `service` Command

To stop or start DMF, you should use the `service(8)` command. See "Starting and Stopping the DMF Environment" on page 181.

### Use a Time Synchronization Application

You must ensure that all nodes that can manage DMF and OpenVault operations have consistent time and time-zone settings. This includes the following:

- DMF server
- Passive DMF server (in an HA configuration)
- Parallel data-mover nodes (if using the Parallel Data-Mover Option)
- OpenVault server (if different from the DMF server)

SGI recommends that you use a time synchronization application on these nodes and that you force synchronization at every boot. For example, if you use Network Time Protocol (NTP), you should set the following in `/etc/sysconfig/ntp`:

```
NTPD_FORCE_SYNC_ON_STARTUP="yes"
```

---

**Note:** If you are using an S3 cloud MSP, the DMF server clock and the S3 clock must be within 15 minutes of each other, otherwise authentication errors will result due to security requirements.

---

## Monitor DMF Daily

You should monitor DMF on a daily basis to ensure that it is operating properly and that you find any problems in time to retrieve data.

DMF provides a number of automated tasks that you can configure to generate reports about errors, activity, and status. Additionally, some serious error conditions generate email messages. Examining this information on a timely basis is important to ensure that DMF is operating properly and to diagnose potential problems.

## Run Certain Commands Only on a Copy of the DMF Databases

You should run the following commands **only on a copy** of the DMF databases:

- `dmdbcheck(8)`
- `dmdump(8)`

If you run these commands on an active database (that is, on a database located in the `HOME_DIR` directory while DMF is running), the results of the commands will be unreliable because DMF may be actively changing the data while the command is running.

## Be Aware of Differences in an HA Environment

If you run DMF in a high-availability (HA) cluster, some configuration requirements and administrative procedures differ from the information in this guide. For example, in an HA environment you must first remove HA control of the resource group before stopping DMF. For more information, see *High Availability Guide for SGI InfiniteStorage*.

## Start Site-Specific Configuration Parameters and Stanzas with “LOCAL\_”

If you choose to add site-specific parameters or object stanzas to the DMF configuration file, you should begin the parameter name or stanza name with “LOCAL\_” (such as `LOCAL_MYPARAM`) so that the names will not cause conflict with future SGI DMF parameters and stanzas.

## Use TMF Tracing

Each TMF process writes debugging information to its own trace file, located in the directory specified by the `trace_directory` parameter in the TMF configuration file `/etc/tmf/tmf.config`. If you use TMF, you should leave TMF tracing on so that this debugging information is available if problems occur.

The trace files are circular, meaning they only contain the most recent activity from a TMF process. To change the amount of history available in a trace file, modify the `trace_file_size` configuration parameter.

When TMF is restarted, any trace files from the previous instance of TMF are moved to the directory specified in `trace_save_directory`.

For more information, see *TMF 6 Administrator Guide for SGI InfiniteStorage*.

## Run `dmcollect` If You Suspect a Problem

As soon as you suspect a problem with DMF, run the `dmcollect(8)` command to gather the relevant information about your DMF environment that will help you and SGI analyze the problem.

---

**Note:** Take care to enter the correct number of **previous** days from which to gather information, so that logs containing the first signs of trouble are included in the collection.

---

For example, the will collect data for today only (0 previous days):

```
server# dmcollect -b 0
```

If the problem started the previous day, you would want to collect data from that day as well (1 previous day):

```
server# dmcollect -b 1
```

Specify a larger number of prior days to cover a longer time period, as required.

Also see Chapter 19, "Troubleshooting" on page 641.

## Modify Settings If Providing File Access via Samba

You can avoid unnecessary Windows SMB request timeouts by setting the `SessTimeout`, `ExtendedSessTimeout`, and `ServersWithExtendedSessTimeout` registry parameters on every Windows client system to the values appropriate for a DMF environment. This is especially important for slower mounting/positioning libraries and tape drives. For example:

```
SessTimeout=300
ExtendedSessTimeout=1000
ServersWithExtendedSessTimeout=value
```

Where *value* specifies all possible Samba server names and IP addresses, separated by a new line, such as in the following formats:

```
SambaServerName
SambaServerName.domainname.com
SambaServerIPAddress1
SambaServerIPAddress2
```

For details, see the following:

<http://blogs.msdn.com/b/openspecification/archive/2013/03/19/cifs-and-smb-timeouts-in-windows.aspx>  
<http://blogs.msdn.com/b/openspecification/archive/2013/03/27/smb-2-x-and-smb-3-0-timeouts-in-windows.aspx>  
<http://technet.microsoft.com/en-au/library/cc938292.aspx>

The Windows Explorer desktop can show which files in an SMB/CIFS network share are in a fully or partially offline state. If so enabled, Windows Explorer overlays a small black clock on top of a migrated file's normal icon; the black clock symbol indicates that there may be a delay in accessing the contents of the file. (This feature is disabled by default.)

To enable this feature, do the following:

1. Install the `sgi-samba` RPMs from ISSP.

---

**Note:** This feature is not available in community Samba.

---

2. Add the following line to the Samba configuration file `/etc/samba/smb.conf` on the DMF server:

```
dmapi support = Yes
```

3. Restart the `smb` daemon on the DMF server:



---

**Caution:** For instructions about starting and stopping DMF and the mounting service in an HA environment, see *High Availability Guide for SGI InfiniteStorage*.

---

```
server# service smb restart
```

For more information, see the `smb.conf(5)` man page.

## Export from the Active CXFS Metadata Server

When exporting a managed filesystem using enhanced Samba in a CXFS environment, you should perform the CIFS export from the active CXFS metadata server in order to realize the full benefit of enhanced Samba.

## Disable Journaling When Loading an Empty Database

If you are loading an empty database, you should disable journaling in order to eliminate unnecessary overhead. To do this, use the `-j` option to the `dmdadm(8)` and `dmcatadm(8)` commands. For example:

```
# dmdadm -j -u -c "load /dmf/scratch/daemon.txt"
# dmcatadm -j -m ls -u -c "load /dmf/scratch/ls_cat_txt" > /dmf/tmp/load.ls.db.out 2>&1
```

## Use Sufficient Network Bandwidth for Socket Merges

If you perform a merge using a socket, you must ensure that the network has sufficient bandwidth. For more information, contact SGI technical support.

## Temporarily Disable Components Before Maintenance

Before you perform maintenance on tape drives, a tape library, a COPAN shelf, or a JBFS enclosure, you can perform steps that will allow DMF to quit using the component. You can then verify that the component is currently unused and will no longer accept new work. See "Temporarily Disabling Components" on page 589.

## Gracefully Stop the COPAN Disks and JBFS Disks

Before stopping COPAN disk or JBFS disks, you should ensure that DMF is not using any of its virtual tape drives and then stop the OpenVault LCPs associated with the disks. See "Stop the COPAN VTL" on page 595.

## Reload STK ACSLS Cartridges Properly

After you load tape cartridges into a StorageTek tape library controlled by Automated Cartridge System Library Software (ACSL) via the cartridge access port, you must manually cancel all prior ACSLS `enter` requests. This will allow OpenVault to update the DMF database.

## Disable Zone Reclaim to Avoid System Stalls

To avoid transient system stalls on DMF servers and all parallel data-mover nodes, you should disable zone reclaim by adding the following line to the `/etc/sysctl.conf` file:

```
vm.zone_reclaim_mode = 0
```

To make this change take effect, enter the following:

```
# sysctl -p
```

For more information about this kernel parameter, refer to the `Documentation/sysct/vm.txt` file in the Linux kernel source.

---

**Note:** For large NUMA compute servers, whose typical workload is HPC applications, you should consider whether the benefits of memory locality outweigh the cost of memory reclaim.

---

## Set Volume Size If You Want to Use Capacity Features

If you want to use features such as the `dmcapacity(8)` command and its display via DMF Manager (which are particularly useful features for COPAN MAID and SGI 400 VTL), you should set the size of volumes in the DMF database. Do one of following:

- Use the `-s tapesize` option to `dmov_loadtapes(8)` when loading new volumes to set the size in bytes. For example:

- ```
# dmov_loadtapes -t Ultrium4-800 -l C00 -s 20000000000 dump_tasks
```
- Use the `dmvoladm(8)` command with the `update` directive to modify the `ts` field to set the size in bytes. For example:  

```
# dmvoladm -m vtl_ls -c "update C00X1Z tapesize 20000000000"
```
  - Specify the cartridge size on the **Add Volumes** dialog in DMF Manager to set the size in bytes. See "Managing Volumes" on page 229.

### Monitor the Size of the PCP Metrics Archive

PCP continuously gathers DMF performance metrics for display in DMF Manager. These metrics are stored in `/var/lib/pcp-storage/archives`.

---

**Note:** In an HA environment, the PCP metrics archive is stored in the directory specified by the `dmfman_setup_ha` script. For more information, see the section about configuring DMF for HA in *High Availability Guide for SGI InfiniteStorage*.

---

Each month, DMF performs a data-reduction process on the metrics gathered for the month. This reduces the size of the archives while retaining a consistent amount of information. Although the size of the archive has a bounded maximum, this can still be quite large depending on the configuration of the server and how many clients access it. For example, a server with a large number of filesystems could generate up to 100 Mbytes of archives per day. You should initially allow around 2 GB of space in `/var/lib/pcp-storage/archives` for archive storage and monitor the actual usage for the first few weeks of operation.

### Be Aware that API Commands Change Without Notice

DMF uses several undocumented commands as an internal API layer. These commands can change or be removed without notice.

---

**Note:** If you require functionality that is not provided by the standard set of documented DMF administrator and user commands, contact SGI Support to suggest a request for enhancement.

---



## Be Aware of Memory-Mapping Issues

On Linux nodes, memory-mapping an offline file in a DMF filesystem may cause other processes such as `ps(1)` to block while DMF is making the file online.

There are also memory-mapping issues with CXFS clients running Red Hat Enterprise Linux (RHEL) or Windows; for more information, see the *CXFS 7 Administrator Guide for SGI InfiniteStorage*.

## Use a Task to Perform Hard-Deletes Periodically

To avoid reaching the maximum DMF database size (4 billion records), you should configure the `run_hard_deletes.sh` task to periodically delete database records that have become eligible for hard-deletion. Otherwise, the daemon database can continue to grow in size as obsolete records accumulate.

See:

- "taskgroup Object" on page 304
- "Cleaning Up Obsolete Database Entries" on page 586

## Enable the Enhanced-NFS RPC Corruption Workaround Parameter if Needed

A Linux NFS-client data corruption bug was fixed in Linux kernel version 2.6.37 with commit ID `f5fc3c50c99a7df2bf908dfe66f112d35178ee07`. If you are running Linux NFS clients with a prior release, you must avoid the problem by using a system-tunable kernel parameter that is available in enhanced NFS. Contact your Linux NFS client OS distribution provider to determine whether or not you must make this change.

---

**Note:** Enabling the parameter can have a negative impact on benchmarking and code compiles over NFS. Therefore, the parameter is disabled (set to 0) by default. You should enable it only if the kernel version on any of your Linux NFS clients contains the corruption bug.

---

If required, the parameter that you must enable (set to 1) on the enhanced-NFS server is `nfsd_workaround_nfs3_xdr_readres_corruption`. Do the following:

1. Add the following line to the `/etc/modprobe.conf` file on the enhanced-NFS server:

```
options nfsd nfsd_workaround_nfs3_xdr_readres_corruption=1
```

2. Reboot the enhanced-NFS server.

For more information about the bug and the enhanced-NFS `nfsd_workaround_nfs3_xdr_readres_corruption` parameter, see the section about enhanced NFS in the ISSP release note.

### Use the Appropriate Tool to Load Volumes to an Existing Environment

Table 3-4 describes the tools you should use to load volumes to an existing DMF and OpenVault environment.

**Table 3-4** Tools to Load Volumes to an Existing DMF/OpenVault Environment

| Volumes Already in DMF? | Volumes Already in OpenVault? | Tool to Use                 |
|-------------------------|-------------------------------|-----------------------------|
| No                      | No                            | <code>dmov_loadtapes</code> |
| Yes                     | No                            | <code>dmov_makecarts</code> |
| No                      | Yes                           | <code>dmvoladm</code>       |

### Configure Fibre Channel Switches and Zones Appropriately

You must configure Fibre Channel switches appropriately to ensure that tapes will not be inappropriately overwritten, potentially resulting in data loss. This is particularly important when using the Parallel Data-Mover Option. This section discusses the following:

- "Ensure that You Follow the Switch Requirements" on page 133
- "Segregate Tape and Disk HBAs" on page 133
- "Suppress Change Notification for Switch Ports Connected to Nodes" on page 133
- "Use N-port Topology for LSI Ports Used with Tape Drives" on page 133

- "Avoid Bottlenecks when Tape Drives and Host Port Speeds Do Not Match" on page 134

### **Ensure that You Follow the Switch Requirements**

See "SAN Switch Zoning or Separate SAN Fabric Requirement" on page 49.

### **Segregate Tape and Disk HBAs**

Never mix tape and disk access via the same HBA port. SGI also recommends that you do not mix tape and disk access on a given multiport card; this recommendation may not apply to some newer multiport cards.

Use separate physical SAN switches or switch zoning to logically separate tape and disk SAN fabrics. See "SAN Switch Zoning or Separate SAN Fabric Requirement" on page 49.

### **Suppress Change Notification for Switch Ports Connected to Nodes**

To prevent unnecessary interruptions, enable the suppression of change notification if the port is connected to a host HBA and disable the suppression for all other ports. See:

- "Suppressing RSCN on Host Port HBAs" on page 177
- "QLogic® Fibre Channel Switch" on page 178

### **Use N-port Topology for LSI Ports Used with Tape Drives**

During error recovery, a bus reset will cause the LSI Fibre Channel port to renegotiate its connection with the Fibre Channel switch. This renegotiation can result in the LSI host port acquiring a different port ID. Should this happen, reservation conflicts or errors that result in the tape driving transitioning to `swdn` can occur. To avoid this problem, use `lsiutil` to set the link topology to `N-port` for all LSI Fibre Channel ports used with tape drives, which eliminates the possibility that the host adapter port could acquire a different port ID.

### Avoid Bottlenecks when Tape Drives and Host Port Speeds Do Not Match

---

**Note:** This section does not apply to STK drives. For those drives, the only control is the size of the tape drive I/O request, which DMF determines. STK 4-Gbit adapters perform at approximately 200 MB/s.

---

If you have one 4-Gbit host port and are writing data to multiple 2-Gbit tape drives, the aggregate desired bandwidth on the host port is greater than the data rate of the Fibre Channel (FC) adapters on the tape drives. This can cause the switch's frame buffers to fill up, causing the switch to stop accepting data from the 4-Gbit HBA, dropping the effective data rate close to that of a 2-Gbit HBA.

You can correct this situation by changing the maximum burst size (`burst_size`) for the tape drive. The maximum burst size specifies the maximum amount of data that the port can transfer during a single operation. It should be double the switch port buffering (after unit conversions, because maximum burst size is in units of 512 bytes). For example, a Brocade 4100 switch has at least 32 KB of buffering per port, so you would start with a value of 128.

---

**Note:** Determining the optimum value for `burst_size` depends upon many site-specific factors, including HBA speed, switch speed, tape speed, and number of tapes per port; it may take some trial-and-error to set optimally. SGI suggests beginning by using a value of 64 or 128, which have been shown to improve results without negative impact.

---

Before changing the maximum burst size, ensure that you have stopped DMF, APD, and the TMF or OpenVault mounting service.

If you have installed the optional `sdparm` RPM from RHEL or SLES, you can use the `sdparm` command to set the burst size:

```
# sdparm -t fcp --set MBS=burstsize /dev/sgNN
```

You can test the effects of changing the burst size by doing the following:

1. Ensure that the services for DMF, APD, and the TMF or OpenVault are stopped. (In an HA environment, see *High Availability Guide for SGI InfiniteStorage*.)
2. Ensure you have two 2-Gbit tape drives on 4-Gbit FC switch with one 4-Gbit host connection.

3. Set the maximum burst size to 0 (no limit) on both drives. For example:

```
# sdparm -t fcp --set MBS=0 /dev/sg0
```

4. Load scratch tapes on the drives.
5. Enter the following for each drive separately and then both drives in parallel and monitor performance with SGI Performance Co-Pilot™ (PCP™) or an FC switch tool:

```
# dd if=/dev/zero of=/dev/ts/... bs=256k
```

6. Change maximum burst size. For example, to set it to 128:

```
# sdparm -t fcp --set MBS=128 /dev/sg0
```

7. Enter the following for each drive separately and then both drives in parallel and monitor performance with PCP or an FC switch tool:

```
# dd if=/dev/zero of=/dev/ts/... bs=256k
```

To determine the current maximum burst size, use the `sginfo -D` command. For example:

```
# sginfo -D /dev/sg0
Disconnect-Reconnect mode page (0x2)
-----
Buffer full ratio                0
Buffer empty ratio               0
Bus Inactivity Limit (SAS: 100us) 0
Disconnect Time Limit            0
Connect Time Limit (SAS: 100us)  0
Maximum Burst Size               128
EMDP                             0
Fair Arbitration (fcp:faa,fab,fac) 0
DIMM                             0
DTDC                             0
First Burst Size                 0
```

You can also use the `sdparm --get` command. For example:

```
# sdparm -t fcp --get MBS /dev/sg0
```

For more information about `sdparm`, see:

<http://freshmeat.net/projects/sdparm/>

<http://dag.wieers.com/rpm/packages/sdparm/>

### Use `dmmove(8)` Safely

Unless you specify the `-d` option, `dmmove(8)` will delete existing copies from MSPs/VG that are not listed in the final set of arguments on the command line. Therefore, when issuing a `dmmove` command, it is a best practice to always explicitly state all of the MSPs/VGs from which a copy should be deleted (which may be `-d none` if no copy should be deleted) and all of the MSPs/VGs into which a copy should be placed/retained. For an example, see "Replacing a Bad DMF Copy with a Good DMF Copy" on page 642. For details about the command, see the `dmmove(8)` man page.

### RHEL: Disable SELinux or Increase the Inode Size

By default, Security-Enhanced Linux (SELinux) is enabled on RHEL systems. Because SELinux uses extended attributes, using the default inode size (256) with SELinux enabled causes all DMF attributes to be stored outside the inode, which potentially slows down most DMF operations.

If you are running DMF with RHEL, you should do one of the following for best performance:

- If SELinux is unnecessary, disable it by setting the following in the `/etc/sysconfig/selinux` file:  

```
SELINUX=disabled
```
- If you require SELinux, increase the inode size for the filesystems managed by DMF to 512 by using the `-i size=512` option to the `mkfs.xfs` command. For more information, see the `mkfs.xfs(8)` man page.

### Apply Appropriate PostgreSQL Updates

You should apply all future security updates and bugfixes in the PostgreSQL 9.3.X series.

---

**Note:** DMF requires the PostgreSQL 9.3.X series. Do not manually upgrade to another major version (such as 9.4.X).

---

## Best Practices for Backups

This section discusses the following:

- "Back Up Migrated Filesystems and DMF Databases" on page 137
- "Migrate All Files Before Performing a Backup" on page 137
- "Use the Integrated Backup Method" on page 138
- "Use a Remote Location for the Disaster-Recovery Bundle" on page 138
- "Retain Log and Journal Files Between Full Backups" on page 138

## Back Up Migrated Filesystems and DMF Databases

When using DMF, you must still perform regular backups to protect inodes, directory structures, and unmigrated files; DMF moves only the data associated with files, not the file inodes or directories. You can configure DMF to automatically run backups of your managed filesystems.

You must also back up the daemon database and the LS database regularly using the `run_copy_databases.sh` task.

See:

- "Administration Tasks" on page 51
- "taskgroup Object" on page 304
- Chapter 4, "Backups and DMF" on page 141

## Migrate All Files Before Performing a Backup

You can greatly reduce the amount of time it takes to back up filesystems by configuring DMF to migrate all files in the managed filesystems by setting the `DUMP_MIGRATE_FIRST` parameter to `yes`. See "Migrate All Files First" on page 146.

## Use the Integrated Backup Method

When using DMF, you must still perform regular backups to protect inodes, directory structures, and unmigrated files; DMF moves only the data associated with files, not the file inodes or directories. The DMF integrated backup method is the preferred backup method. In this method, DMF is configured to migrate file data to the backup media before using `xfsdump` to dump the remaining file metadata and directory structure so that both dump size and the dump time are reduced. For filesystems not managed by DMF, DMF dumps file data, file metadata, and directory structure.

For information about converting an existing DMF configuration to this method, see "Converting to Integrated Backups" on page 157

## Use a Remote Location for the Disaster-Recovery Bundle

For data security SGI recommends that you specify a remote location for the disaster-recovery bundle mirror when using the integrated-backup method. See the `DUMP_DR_MIRRORS` configuration parameter in "taskgroup Object Parameters" on page 312

## Retain Log and Journal Files Between Full Backups

You must retain DMF log and journal files between full backups of the DMF databases. After a full backup, you may remove old journal and log files to prevent the spool directory from filling. You can use the `run_remove_logs.sh` and `run_remove_journals.sh` tasks to schedule automatic removal of the old files after the backup completes. See "taskgroup Object" on page 304.

## Best Practices for Optional Tasks

This section discusses the following:

- "Balance Data Among Libraries" on page 139
- "Prevent Recalls From Waiting for a Busy Volume" on page 140
- "Use the Immutable Bit if You Want to Prevent File Modification" on page 140



## Balance Data Among Libraries

If you want to balance migrated data among libraries, you can use configurations such as the following:

- Suppose you have two libraries and you want to make two copies of the migrated data. You would use a VG for each library (`lib1vg` and `lib2vg`) and the following statement for VG selection:

```
SELECT_VG lib1vg lib2vg
```

One copy would go to each library.

See "MSP/VG Selection Parameters for a Managed Filesystem" on page 374.

- Suppose you have four libraries and you want to make two copies of the migrated data. You can use two migrate groups, each with two VGs, and a rotation strategy of `ROUND_ROBIN_BY_BYTES`:

```
mg1
  lib1vg
  lib2vg
```

```
mg2
  lib3vg
  lib4vg
```

You would use the following statement for VG selection:

```
SELECT_VG mg1 mg2
```

One copy of would go to either `lib1vg` or `lib2vg`, the other copy would go to either `lib3vg` or `lib4vg`.

For more information, see:

- "Migrate Groups" on page 42
- "Use Migrate Groups Appropriately" on page 111
- "migrategroup Object Example with Multiple MGs" on page 431

## Prevent Recalls From Waiting for a Busy Volume

If you want to prevent recall requests from waiting for a volume that is busy because it is being written to, you can use the configuration parameters `FORWARD_RECALLS` and `GET_WAIT_TIME` in the `volume group` stanza.

For example, to allow DMF to continue writing to the volume for only up to 1 hour (3600 seconds) after receiving a recall request and to direct recall requests to another VG if this VG is writing to the volume, you would include the following parameters:

```
GET_WAIT_TIME          3600
FORWARD_RECALLS       ON
```

For more information about these parameters, see "volume group Object" on page 410.

## Use the Immutable Bit if You Want to Prevent File Modification

If you want to prevent a file from being changed or deleted even by the `root` user, use the XFS immutable bit. For more information, see the `chattr(8)` command.

## Backups and DMF

This section discusses the following:

- "DMF Requirement for Backups" on page 141
- "Dump Scripts" on page 141
- "Site-Specific Factors to Consider" on page 144
- "Media-Specific Requirements" on page 144
- "Considerations for Optimizing Backups" on page 145
- "Integrated-Backup Method" on page 148
- "Other Backup Methods" on page 161

### DMF Requirement for Backups

The fact that DMF maintains copies of data on another medium does not mean that it is a backup system. The copies made by DMF may become inaccessible if there is a failure and proper backups have not been made.

In addition, although using RAID may protect you against the failure of one disk spindle, data can still be endangered by software problems, human error, or hardware failure.

Therefore, **backups are essential**.

### Dump Scripts

DMF provides the following scripts that you can add to a `taskgroup` object:

- "run\_full\_dump.sh" on page 142
- "run\_partial\_dump.sh" on page 143

### run\_full\_dump.sh

The `run_full_dump.sh` script performs a full backup of configured filesystems at intervals specified by a time expression when configured as part of a `dump taskgroup` object.

You can invoke this script manually by using the following command line:

```
/usr/lib/dmf/run_full_dump.sh dmdaemon taskgroup [prune]
```

where:

- |                          |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
|--------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>dmdaemon</i>          | Indicates the name of the <code>dmdaemon</code> object                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
| <i>taskgroup</i>         | Indicates the name of the <code>taskgroup</code> object                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
| <i>prune</i>             | Indicates the type of prune action to be performed, one of the following:                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
| <code>prune-files</code> | <i>(integrated backups only)</i> Removes orphaned filesystem dumps from the backup filesystem that have no corresponding entry in the <code>xfsdump</code> inventory. For safety reasons, this type of prune will not remove any other files, so there could still be other orphaned backup files in the backup filesystem (such as database, configurations, and inventories); these files will eventually be removed after their age exceeds the <code>DUMP_RETENTION</code> period. Before using this argument, ensure that the orphaned filesystem dump is no longer required to restore a filesystem; see the <b>Caution</b> below. |
| <code>prune-inv</code>   | <i>(integrated backups only)</i> Removes orphaned inventory entries from the <code>xfsdump</code> inventory. <i>Orphaned inventory entries</i> do not have corresponding dump files in the backup filesystem. Before using this argument, ensure that the entries do not correspond to dump files that might still be restored to the backup filesystem; see the <b>Caution</b> below.                                                                                                                                                                                                                                                   |

`prune-only`

Removes expired dumps based on the `DUMP_RETENTION` value

The `prune-files` and `prune-inv` arguments are typically used to resolve consistency errors reported by an integrated backup session.



**Caution:** The `prune-inv` and `prune-files` arguments do not prune based on the `DUMP_RETENTION` value and hence could cause important filesystem dumps or `xfsdump` inventory entries to be removed even though they might still be required to restore filesystem components.

---

### `run_partial_dump.sh`

The `run_partial_dump.sh` script performs an incremental backup.

---

**Note:** If the `DUMP_MAX_FILESPACE` configuration parameter is defined (in any configuration object that applies to the filesystem) but the `UPDATE_CTIME` configuration parameter is undefined or set to `OFF`, then `run_partial_dump.sh` will for safety reasons perform a full (level-0) backup for a managed filesystem. See "DUMP\_MAX\_FILESPACE Requires UPDATE\_CTIME for Incremental Backups" on page 148.

---

You can invoke this script manually by using the following command line:

```
/usr/lib/dmf/run_partial_dump.sh dmdaemon taskgroup
```

where:

*dmdaemon*     Indicates the name of the `dmdaemon` object

*taskgroup*    Indicates the name of the `taskgroup` object

## Site-Specific Factors to Consider

Backup requirements depend upon a number of very site-specific factors, including the following:

- The amount of data that is migrated and the amount of data that is not migrated at the time a backup takes place
- The number of inodes
- The size of the DMF databases (see "*HOME\_DIR* Size" on page 97)
- The backup methodology for using full and/or incremental backups
- Amount of space occupied by each dump, which in turn depends on:
  - Size of DMF database
  - Number of inodes
  - Amount of space occupied by regular files
  - Your choice of full versus incremental backups
- The desired amount of time you want to retain dumps

## Media-Specific Requirements

This section discusses the following:

- "Backups using Physical Tapes and SGI 400 VTL Tapes" on page 144
- "Backups using COPAN MAID" on page 145

### Backups using Physical Tapes and SGI 400 VTL Tapes

The number of physical or virtual backup tapes that will be used depends upon the retention period and the information in "Site-Specific Factors to Consider" on page 144.

Tapes are recycled after the retention period is completed, therefore you must have more backup tapes than are required to fulfill the retention period (at least one extra tape). Assuming that backups are done daily, the minimum number of tapes required is:

$$\textit{Retention\_Period\_In\_Days} + 1 = \#\_Backup\_Tapes$$

For example, using a retention period of 4 weeks (28 days):

$$28 + 1 = 29 \text{ tapes}$$

So long as each day's backup can fit onto one tape, this means that at a minimum 29 backup tapes are required, assuming that backups are performed each day.

---

**Note:** You should monitor the backup report daily to verify that there are sufficient tapes available for future backups. If it turns out that a given day requires multiple backup tapes for the set of backups for that day's backup, you must empty previously used backup tapes or add more backup tapes.

---

## Backups using COPAN MAID

The amount of space that your site will require for the backups created by each day's backup depends upon the information discussed in "Site-Specific Factors to Consider" on page 144. This amount is the *Dump\_Space\_Needed\_Per\_Day* value.

The approximate formula for the amount of disk space that you must reserve for backups is:

$$\textit{Dump\_Space\_Needed\_Per\_Day} * (\textit{Retention\_Period\_In\_Days} + 1) = \textit{Reserved\_Space}$$

You can allocate the *Reserved\_Space* on a reserved portion of the RAID set that is not managed by DMF). If you prefer, you could allocate space on physical tapes instead. For more information, see *COPAN MAID for DMF Quick Start Guide*.

## Considerations for Optimizing Backups

This section discusses the following:

- "Migrate All Files First" on page 146
- "Consistent Backup Completing Times via DUMP\_MAX\_FILESPACE" on page 147
- "DUMP\_MAX\_FILESPACE Requires UPDATE\_CTIME for Incremental Backups" on page 148

## Migrate All Files First

You can greatly reduce the amount of time it takes to back up filesystems by configuring DMF to migrate all files. To do this, set the `DUMP_MIGRATE_FIRST` parameter to `yes`, which specifies that the `dmmigrate` command is run before the dumps are done to ensure that all migratable files in the managed filesystems are migrated. For more information, see the description of the parameter in the following sections:

- "dumpgroup Object Parameters" on page 343 (integrated-backup context only)
- "filesystem Object Parameters" on page 351 (integrated-backup context only)
- "taskgroup Object Parameters" on page 312

Migrating all files before performing a backup has the following benefits:

- The backup image will be smaller because it contains just the metadata information, not the file data itself
- The backup will complete more quickly because:
  - It is reading just the metadata
  - There is less time spent performing random disk seeks to back up the data of unmigrated files

For any files that you want to remain permanently on disk (that is, permanently dual-state), you can assign a negative priority weight to those files. The result is that when the filesystem is filled up, DMF will never free the blocks for these files. The files therefore are always dual-state, ready to be used. When the filesystem is backed up, the backup facility will recognize that they are dual-state and therefore back them up as offline. The net effect is that there is no file data in the backup at all for these files, just their inodes, while keeping the files always available. In the case of millions of small files, this speed-up of the backup process can be dramatic. For example, for a filesystem with a large number of small files (files of up to 64 KB), you could assign the following `AGE_WEIGHT` value:

```
AGE_WEIGHT      -1      0      when space < 64k
```



Be aware of the following:

- For extremely small files (under a few hundred bytes), the disk space required for DMF database entries may exceed the size of the original file. For extremely large numbers of such files, this issue should be considered.
- The `space` value in a `when` clause, as used above, refers to the space the file occupies on disk, which for sparse files may actually be smaller than the size of the file as shown by `ls -l`. The `space` value will be rounded upward to a multiple of the disk blocksize defined by `mkfs(8)`; the default is 4096 bytes. For example, attempting to discriminate between files above or below 1000 bytes based on their `space` value is futile because all non-empty files will have a `space` value that is a multiple of (typically) 4096 bytes.

If you use negative weights with `AGE_WEIGHT` or `SPACE_WEIGHT`, DMF automatic migration will never free the space for these files but a user can still do a `dmput -r` to manually free the space.

However, if you do not want files to migrate for any reason, then you must continue to use the `SELECT_VG` method despite the slower and larger backups.

## Consistent Backup Completing Times via `DUMP_MAX_FILESPACE`

If you do not first migrate all files before performing a backup (see "Migrate All Files First" on page 146) but you still want to make your backup completion times consistent, you can use the `DUMP_MAX_FILESPACE` configuration parameter on specific `filesystem` objects to restrict the size of regular files that are included in the dumps. For example, you could set `DUMP_MAX_FILESPACE` to `1K` to prevent all regular files exceeding 1 KB from being backed up; this assumes that although most regular-state files will be skipped in the next backup, they will soon be migrated, and then their inodes only will be included in a later backup. Using this method will also require setting `UPDATE_CTIME` if using incremental backups; see "DUMP\_MAX\_FILESPACE Requires UPDATE\_CTIME for Incremental Backups" on page 148



**Caution:** This parameter is also available for the `dumpgroup` and `taskgroup` objects, but it can be dangerous because files are omitted silently and the limit applies to all of the filesystems specified by an object (which by default is all filesystems for the `taskgroup` object). . Therefore SGI recommends that you set this limit only for specific `filesystem` objects.

---

## **DUMP\_MAX\_FILESPACE Requires UPDATE\_CTIME for Incremental Backups**

If you set the `DUMP_MAX_FILESPACE` configuration parameter and you want to perform incremental backups of a managed filesystem, then you must also set the `UPDATE_CTIME` configuration parameter to `ON`. This is required to avoid the situation in which a file is never backed up, due to the default way in which timestamps are changed on files.

---

**Note:** If you set `DUMP_MAX_FILESPACE` in any configuration object that applies to the filesystem without setting `UPDATE_CTIME` to `ON`, DMF will always perform full (level-0) backups.

The `run_partial_dump.sh` script for safety reasons performs a full (level-0) backup for a managed filesystem when both of the following conditions are true:

- The `DUMP_MAX_FILESPACE` configuration parameter is defined in the `taskgroup` object for tape/disk backups or in the `dumpgroup`, `filesystem`, or `taskgroup` object for integrated backups
- The `UPDATE_CTIME` configuration parameter is undefined or set to `OFF` for the filesystem

---

See:

- "dumpgroup Object Parameters" on page 343
- "filesystem Object Parameters" on page 351
- "taskgroup Object Parameters" on page 312
- "filesystem Object Example for Incremental Backups that Restrict File Size" on page 362

## **Integrated-Backup Method**

This section discusses the following:

- "Overview of Integrated Backup" on page 149
- "Contents of the Integrated Backup" on page 149
- "Size of the Backup Filesystems" on page 153
- "DR Bundle Locations" on page 154

- "Configuring Integrated Backups" on page 154
- "Converting to Integrated Backups" on page 157
- "Consideration for Integrated Backups: Restored Database May Point to Freed Space" on page 160
- "Monitoring Backup Reports for Integrated Backups" on page 160

## Overview of Integrated Backup

The integrated-backup method provides a fast, safe, and efficient backup method for DMF. Dumps are sent to a backup filesystem from which the dump data is then migrated to multiple volumes, providing redundancy.

A policy for the backup filesystem must be configured to ensure the following:

- Temporary files produced by the integrated-backup method (which have a project ID of 4136) are excluded from migration. This is required under the following conditions:
  - If `DUMP_WORKSPACE` is not set
  - If `DUMP_WORKSPACE` is explicitly set to a location inside the backup filesystem (the filesystem that has `USE_AS_DUMP_DEST` set to ON)
- All appropriate files are migrated to at least two separate locations. The separate locations can be defined using any combination of volume groups (VGs), media-specific processes (MSPs), or migrate groups (MGs).

The integrated-backup method is the preferred backup method. It applies to basic DMF, DMF in an HA environment, and DMF using the Parallel Data-Mover Option (Parallel DMF).

## Contents of the Integrated Backup

An integrated backup consists of the following:

- The `dumps.db` database stored in `HOME_DIR/backups` (such as `/home/dmf/backups`) that contains status information about dumps and information about the backup filesystem

- A backup filesystem, such as `/dmf_backups` (defined by the `filesystem` object in the DMF configuration file and labeled with the `DUMP_DESTINATION` parameter), that contains the following:
  - Dumps of the following:
    - Each of the filesystems configured for backup
    - XFS inventory
    - DMF databases
  - Configuration bundle containing the following files:
    - DMF configuration file
    - Tape-driver configuration file
    - `/etc/fstab` file
    - License file
    - Mount information
    - Usage details and UUID of filesystems
    - OpenVault configuration

---

**Note:** OpenVault maintains a history of its configurations. Because backing up the current configuration could create an inconsistent copy, the backup process saves the last snapshot of the OpenVault configuration.

However, restoring the OpenVault configuration might not always produce the desired result. If the device paths change between the time the configuration was created and the time when the configuration is restored, OpenVault configuration would be invalid. In such cases, manual intervention is required to create a similar configuration from scratch.

---

- Disaster-recovery bundle (referred to as the *DR bundle*) containing the following:
  - A copy of the above configuration bundle
  - XFS inventory

- A dump of the backup filesystem
- Disaster-recovery database (containing the DMF database entries that correspond to the backup filesystem)

---

**Note:** The files specified by the `FTP_PASSWORD` and `CLOUD_PASSWORD` configuration parameters are not included in the backup. You should keep the contents of those files in a safe location. You can also use the `DUMP_MISC_LOCATIONS` configuration parameter to include them in the dump. See "taskgroup Object Parameters" on page 312.

---

Figure 4-1 describes the backup process.




Figure 4-1 DMF Integrated Backups

Figure 4-2 represents the directory structure of the backup filesystem and the location used to store the backup database.




Figure 4-2 Integrated Backup Directory Structures

## Size of the Backup Filesystems

Eventually, all of the files in the filesystem that is defined to hold DMF backups (such as `/dmf_backups`) are migrated. The size of the backup filesystem should be such that it is able to hold the files that are created before migration and it should also be able to hold the recalled files during a filesystem restore or disaster-recovery process. As a guideline, the backup filesystem should be large enough to hold the following:

- The DMF databases
- The dumps of filesystems that are configured for backup
- An additional 50-100 GB for other backup components

## DR Bundle Locations

The DR bundle must be sent to a safe remote location, at least one of the following:

- A remote mirror specified by the `DUMP_DR_MIRRORS` configuration parameter. The mirror location requires the following:
  - If using `scp(1)`, the node must permit passwordless login.
  - If using NFS, the mirrored filesystem must be mounted so that the `root` user is able to access the filesystem with `root` privileges (that is, with `root squashing` disabled).



**Caution:** A local mirror is permitted but not recommended because it could be at risk in a disaster, such as a fire. Without a working mirror location, you are in danger of losing the ability to restore filesystems because the `/dmf_backups` filesystem and its metadata are part of the DR bundle.

---

- Cloud storage, using a preconfigured site-specific script

For additional safety or testing purposes, the DR bundle may also be sent in an email to the address specified by the `DUMP_DR_EMAIL` configuration parameter. (The email contains the DR bundle plus information on how to restore a lost bundle from copies on the volume.) If used, you must ensure that you allows a sufficiently large email size limit in the `sendmail` configuration.

## Configuring Integrated Backups

This section discusses the following:

- "Precedence of Objects for Integrated Backups" on page 154
- "Procedure to Configure Objects for Integrated Backups" on page 156

### Precedence of Objects for Integrated Backups

Some parameters can be defined in multiple objects in the DMF configuration file. For each filesystem using integrated backups, you can define the following parameters in the `dumpgroup` object, `filesystem` object, and `taskgroup` object:

```
DUMP_COMPRESS
DUMP_MAX_FILESPACE
```




DUMP\_MIGRATE\_FIRST  
 DUMP\_STREAMS  
 DUMP\_XFSDUMP\_PARAMS

In addition, you can define `DUMP_FLUSH_DCM_FIRST` in the `msp` object for a DCM MSP and the `taskgroup` object.

If you define a given parameter in more than one object, the object order of precedence is as follows:

- **Top precedence:**
  - A `dumpgroup` object that is included in a `DUMP_GROUPS` parameter of a `taskgroup` object that applies to integrated backups.
  - An `msp` object for a DCM MSP that applies to integrated backups
- **Medium precedence:** A `filesystem` object for a managed filesystem that is configured to be backed up as part of a `taskgroup` object that applies to integrated backups.
- **Least precedence:** A `taskgroup` object that applies to integrated backups.

For example, if `DUMP_COMPRESS` is defined in multiple objects, the value in the `dumpgroup` object overrides the value in the `filesystem` object, which overrides the value in `taskgroup` object.



**Figure 4-3** Order of Precedence for Dump Parameters

### Procedure to Configure Objects for Integrated Backups

To enable integrated backups, do the following:

1. Configure a `filesystem` object for the dump destination.
2. Configure two `policy` objects for the backup filesystem:
  - A `policy` object that defines free-space and migration thresholds
  - A `policy` object that contains the following one or more `SELECT_VG/SELECT_MSP` parameters:
    - If `DUMP_WORKSPACE` is not set or if it is explicitly set to a location inside the backup filesystem (the filesystem that has `USE_AS_DUMP_DEST` set to `ON`), then you must prevent the migration of temporary files produced by the integrated-backup method. These temporary files have a project ID of 4136. To accomplish this, set the **first** `SELECT_VG/SELECT_MSP` parameter to the following value:

```
none when projid = 4136
```

---

**Note:** The order of `SELECT_VG/SELECT_MSP` parameters is important. If this function is required, it must be the first `SELECT_VG/SELECT_MSP` parameter in the stanza.

---

- At least one `SELECT_VG/SELECT_MSP` parameter that defines at least two locations for the migrated data.

For example:

```
define backup_vg_policy
    TYPE                policy
    SELECT_VG           none when projid = 4136
    SELECT_VG           bvg1a bvg1b
enddef
```

3. Configure a single backup `taskgroup` (such as `dump_tasks`) that runs a set of tasks (`run_full_dump.sh`, `run_partial_dump.sh`, and `run_hard_deletes.sh`) on the managed filesystems.
4. If you want to apply different characteristics (such as the number of `xfsdump` streams or the compression type) to specific managed filesystems, you can do so by setting various `DUMP_*` parameters in the `filesystem` or `dumpgroup` objects

for those specific filesystems; see "Precedence of Objects for Integrated Backups" on page 154.

5. (*HA or Parallel DMF only*) Copy the certificate file to all DMF nodes.

In an environment using HA or Parallel DMF, the backup process will collect information from all potential DMF servers and all parallel data-mover nodes using a `xinetd`-based communication mechanism that uses SSL certificates for authentication. To achieve this, you must run the `ov_makecert(8)` command on the active DMF server and manually copy the resulting certificate file to the passive DMF server (in an HA configuration) and any parallel data-mover nodes. For more information, see the `ov_makecert(8)` command.

For details, see:

- "Precedence of Objects for Integrated Backups" on page 154
- "taskgroup Object" on page 304
- "dumpgroup Object" on page 342
- "filesystem Object" on page 350
- "policy Object" on page 364

## Converting to Integrated Backups

If you want to convert an existing system to integrated backups, do the following:

1. Prepare for the conversion by executing the following command, depending upon your current nonintegrated backup method:

- Disk backups:

```
# /usr/sbin/dmconvertbackup
```

- Tape backups (or a mix of disk and tape):

```
# /usr/sbin/dmconvertbackup [-v VG_or_AG [-l LS ]]
```

where:

-l *LS*

Specifies the library server to which freed-up tapes will be added for the specified VG or AG

`-V VG_or_AG` Specifies the VG or AG to which freed-up tapes will be added.

The first time that you execute `dmconvertbackup`, it does the following:

- a. Adds a daily `cron(8)` job that performs prune-only runs of existing nonintegrated disk and tape backup tasks.
- b. Saves a copy of the DMF configuration file in the `HOME_DIR/convertbackup` directory. Arguments passed to `dmconvertbackup` are also stored in this copy of the DMF configuration.
- c. Saves a copy of the files specified by the `DUMP_TAPES` configuration parameter (for nonintegrated tape-based backups only) in the `HOME_DIR/convertbackup` directory.
- d. Prunes dumps from nonintegrated backups according to their respective `DUMP_RETENTION` values.
- e. Optionally returns any freed-up tapes to the specified volume group (VG) or allocation group (AG) in the specified library server (LS).

---

**Note:** Subsequent executions of this command perform step 1d through step 1e until there are no dumps from nonintegrated backups in the XFS dump inventory. At that point, the command removes the daily `cron` job that calls this command and removes the `HOME_DIR/convertbackup` directory.

---

For example:

- To install a `cron` job that prunes nonintegrated disk and tape dumps based on the `DUMP_RETENTION` values configured in their respective task groups:

```
# dmconvertbackup
```

- To install a `cron` job as described above and also return tapes thus freed up to AG `myag` in LS `myls`:

```
# dmconvertbackup -V myag -l myls
```

2. Make changes to the DMF configuration file. For example:
  - a. Delete the nonintegrated `taskgroup` objects that pertain to backups.

- b. Create a new `taskgroup` object for the integrated backups. This new object must have a unique name that differs from the nonintegrated `taskgroup` names. For example, you could use `integrated_dumptasks`.

---

**Note:** You must use a new, unique name for the integrated backup `taskgroup` because the command uses the names of the nonintegrated backup `taskgroup` objects to determine if there is a nonintegrated backup still to be pruned from the `xfsdump` inventory entries.

---

If you want to use dump parameter values that differ between filesystems, you can include those parameters in the `filesystem` or `dumpgroup` objects. See "Precedence of Objects for Integrated Backups" on page 154.

- c. Configure two VGs sharing one AG (specified above)
- d. Define `backup_vg_policy` to exclude temporary files produced by the integrated-backup method (which have project ID 4136) and to use two VG locations for the migrated files. For example:

```
define backup_vg_policy
    TYPE                policy
    SELECT_VG           none when projid = 4136
    SELECT_VG           bg_vg1 bg_vg2
```

- e. Use a managed filesystem as the backup filesystem. This filesystem is used as the `DUMP_DESTINATION` value for the integrated-backup `taskgroup` object. This filesystem object must set `USE_AS_DUMP_DEST` to `ON` and use the `backup_vg_policy` defined in the above step. The following is an example excerpt:

```
define /dmf_backups
    TYPE                filesystem
    MIGRATION_LEVEL     auto
    POLICIES            backup_space_policy backup_vg_policy
    USE_AS_DUMP_DEST    on
enddef

define integrated_dumptasks
    TYPE                taskgroup
    DUMP_DESTINATION    /dmf_backups
    DUMP_DR_MIRRORS     root@mymachine:/tmp/mymirrors
```

```
DUMP_DR_EMAIL      admin@company.com
enddef
```

See also:

- "taskgroup Object Example for Integrated Backups" on page 332
- "dumpgroup Object Example for Integrated Backups" on page 345
- "filesystem Object Example for Integrated Backups" on page 362

### Consideration for Integrated Backups: Restored Database May Point to Freed Space

If DMF database is corrupt or lost and must be restored from a period older than *HFREE\_TIME*, it is possible that the entries in the older database copy point to the space that has already been freed. This could lead to an incomplete DMF recovery and partial data loss. Although you would normally immediately notice a problem requiring disaster recovery actions, it is possible for a problem to go undetected for some time. Therefore, you should set *HFREE\_TIME* to a value that is large enough to accommodate the use of an older DR bundle. Assuming that full backups are done weekly, SGI recommends setting *HFREE\_TIME* to 1209600 (2 weeks).

---

**Note:** The value of the *MERGE\_THRESHOLD* parameter for the *volume* object and the *THRESHOLD* parameter for the *taskgroup* object determine when sparsely occupied tapes are merged. Any successful tape merge effectively invalidates the previous DMF database backups and DR bundles; therefore, setting an appropriate *HFREE\_TIME* helps keep enough DMF database backups and DR bundles valid for disaster recovery.

---

### Monitoring Backup Reports for Integrated Backups

You should monitor the backup report daily to verify that there is sufficient storage space for future backups. Integrated backups regularly prune older backups based on *DUMP\_RETENTION* time, but to free up space after pruning, it is important to run hard deletes followed by periodic volume merges.

## Other Backup Methods

This section discusses nonintegrated disk backups and nonintegrated tape backups:

- "Report Monitoring for Nonintegrated Tape Backups" on page 161
- "Storage Used by an FTP MSP or a Standard Disk MSP for Nonintegrated Backups" on page 161
- "Filesystems Used by a DCM MSP for Nonintegrated Backups" on page 161
- "DMF's Private Filesystems and Nonintegrated Backups" on page 163

### Report Monitoring for Nonintegrated Tape Backups

You should monitor the tape backup report daily to verify that there are sufficient tapes available for future backups. If it turns out that a given day requires multiple backup tapes for the set of backups for that day's backup, you must empty previously used backup tapes or add more backup tapes.

### Storage Used by an FTP MSP or a Standard Disk MSP for Nonintegrated Backups

If you are depending on an FTP MSP or a standard disk MSP to provide copies of your offline files in order to safeguard your data, then they should also be backed up.

If you use them just to hold extra copies for convenience or to speed data access, they need not be backed up. But you should consider how you would handle their loss. You would probably need to remove references to lost copies from the DMF daemon database, using `dmcdadm`, which can only be done when the daemon is not running.

### Filesystems Used by a DCM MSP for Nonintegrated Backups

A DCM MSP differs from a disk MSP in that it uses DMAPI to manage the files. It will not operate properly if the files are reloaded by a package that cannot also restore the DMAPI information associated with each file.

---

**Note:** For simplicity, this discussion assumes that the site wishes to keep two copies of migrated files at all times to guard against media problems. (Keeping only one copy is considered risky, and keeping more than two copies is frequently impractical.)

---

The DCM MSP can have one of the following configurations:

- A DCM MSP may be holding an extra copy of files in addition to the normal number of tape-based or MAID-based copies. That is, after the initial migration has completed, there will be two lower-tier copies and a third in the cache. The DCM MSP may easily remove this third copy from the cache after some period of time, just leaving two lower-tier copies. With this configuration, there is normally no need to back up the cache filesystem.
- The initial migration could result in one cache copy and one on lower tier. Later on, when the cache has to be flushed, a second lower-tier copy is written by the DCM MSP before the cache-resident one is deleted. If the file is hard-deleted before the cache flushes, the second lower-tier copy will never be made, thereby saving time and lower-tier space. The tradeoff is that cache-flushing is slower and the cache filesystem should be backed up; otherwise a media problem in conjunction with a disk failure would result in data loss. With this configuration, the cache filesystem should be backed up. Otherwise, the loss of the cache disk could leave you with just one copy of data on a lower tier. This is considered to be risky.

For both configurations, any backups require the use of a backup package that is aware of DMF (as listed in Appendix D, "Third-Party Backup Package Configuration" on page 767) to back up the cache.

To use `run_full_dump.sh` or `run_partial_dump.sh` to back up any of these filesystems, include the pathname of its mountpoint in the `DUMP_FILE_SYSTEMS` parameter.



## DMF's Private Filesystems and Nonintegrated Backups

The following DMF private filesystems do not require a backup package that is aware of DMF when using nonintegrated backups:

*HOME\_DIR*  
*JOURNAL\_DIR*  
*SPOOL\_DIR*  
*TMP\_DIR*  
*CACHE\_DIR*  
*MOVE\_FS*

Take care when backing up the databases in *HOME\_DIR* if there is any DMF activity going on while the backup is underway, due to the risk of making the copy of the database while it is being updated. A safe technique is to take a snapshot of the databases with `dmsnap` and back up the snapshot. The `run_full_dump.sh` or `run_partial_dump.sh` script does this automatically.

The journal files in *JOURNAL\_DIR* should also be backed up if you keep older snapshots of the databases that may have to be reloaded and brought up-to-date with `dmdbrecover`. Preferably, journals should be backed up when DMF activity (apart from recalls) is minimal. The `run_full_dump.sh` and `run_partial_dump.sh` scripts and parameters `DUMP_MIGRATE_FIRST` and `DUMP_FLUSH_DCM_FIRST` help achieve this by processing any queued up migration requests immediately before starting the backup.

*SPOOL\_DIR* contains log files that may be of use for problem diagnosis, as well as history files controlling things like media error recovery and reporting scripts. The loss of these files will not endanger user data, although DMF may act a little differently for a while until it reestablishes them. Back up *SPOOL\_DIR* if you can.

The *TMP\_DIR*, *CACHE\_DIR*, and *MOVE\_FS* filesystems do not require backup.

To use `run_full_dump.sh` or `run_partial_dump.sh` to back up any of these filesystems, simply include the pathnames of their mountpoints in the `DUMP_FILE_SYSTEMS` parameter.



## Installing and Configuring the DMF Environment

This chapter discusses the following:

- "Overview of the Installation and Configuration Steps" on page 165
- "Installation and Configuration Considerations" on page 169
- "Starting and Stopping the DMF Environment" on page 181
- "Using Out-of-Library Tapes" on page 184
- "Customizing DMF" on page 186
- "Importing Data From Other HSMs " on page 189

### Overview of the Installation and Configuration Steps

To install and configure the DMF environment, perform the following steps:

---

**Note:** Also see:

- *COPAN MAID for DMF Quick Start Guide*
  - *SGI 400 VTL for DMF Quick Start Guide*
- 

#### **Procedure 5-1** Configuring the DMF Environment

1. Read "Installation and Configuration Considerations" on page 169.
2. Ensure that the DMF server is running the `xinetd(8)` daemon. If it has been disabled, you must reenale it at boot time via the following command:

```
dmfserver# chkconfig xinetd on
```

If `xinetd` is not running, you can start it immediately via the following command:

```
dmfserver# service xinetd start
```

See also "Set the `xinetd tcpmux instances` Parameter Appropriately" on page 108.

3. Install the DMF server software (which includes the software for TMF and OpenVault) according to the instructions in the *SGI InfiniteStorage Software Platform* release note and any late-breaking caveats posted to the online download page for the release:

<https://support.sgi.com>

See "ISSP DMF Software" on page 169.

4. Determine the DMF drive groups that you want to use.
5. Start the `ident` service on the DMF server:

- RHEL:

- a. Configure the `auth` service to start when the `xinetd` service is started:

```
dmfserver-rhel# chkconfig auth on
```

- b. Modify the `/etc/xinetd.d/pidentd` file and add the `only_from` option to ensure that only the PostgreSQL database server will connect and use `pidentd`. The PostgreSQL server is the `hostname` value for the DMF server (or its IP address); in an HA environment, use the virtual hostname.

For example, in a non-HA environment if the DMF server `hostname` is `dmfserver`:

```
only_from = dmfserver
```

For example, in an HA environment if the virtual hostname used for the active DMF server is `virtual-server`:

```
only_from = virtual-server
```

- c. Verify that the `server_args` parameter in the `/etc/xinetd.d/auth` file **does not** contain `-E` in its argument list.

If `-E` is present, edit the file to remove it and then restart the `xinetd` service:

```
dmfserver-rhel# service xinetd restart
```

- SLES:

- a. Configure the `pidentd` service to start when the `xinetd` service is started:

```
dmfserver-sles# chkconfig pidentd on
```

- b. Modify the `/etc/xinetd.d/auth` file and add the `only_from` option to ensure that only the PostgreSQL database server will connect and use `auth`. The PostgreSQL server is the `hostname` value for the DMF server (or its IP address); in an HA environment, use the virtual hostname.

For example, in a non-HA environment if the DMF server hostname is `dmfserver`:

```
only_from = dmfserver
```

For example, in an HA environment if the virtual hostname for the DMF server is `virtual-server`:

```
only_from = virtual-server
```

- c. Verify that the `server_args` parameter in the file `/etc/xinetd.d/pidentd` **does not** contain `-E` in its argument list.

If `-E` is present, edit the file to remove it and then restart the `xinetd` service:

```
dmfserver-sles# service xinetd restart
```

6. Configure the TMF or OpenVault mounting service (if used) according to the following documentation:
- *TMF 6 Administrator Guide for SGI InfiniteStorage*
  - *OpenVault Administrator Guide for SGI InfiniteStorage*
7. Determine how you want to complete periodic maintenance tasks. See "Automated Maintenance Tasks" on page 175.
8. Make and mount the filesystems required for the DMF administrative directories. See "Configure Filesystems and Directories Appropriately for DMF" on page 94.
9. Install the DMF license (and optional DMF Parallel Data-Mover Option license) on the primary DMF server and the passive DMF server (if applicable). See Chapter 2, "DMF Licensing" on page 67 and "Managing Licenses and Data Capacity with DMF Manager" on page 203.

---

**Note:** Nodes running DMF client software do not require a DMF license.

---

10. Create or modify your configuration file and define objects for the following:

- Pathname and file size parameters necessary for DMF operation (the base object)
- DMF daemon
- Daemon maintenance tasks
- Filesystems
- Automated space management
- Media-specific process (MSP) or library server (LS)
- MSP/LS maintenance tasks

See "Configuring DMF with DMF Manager" on page 210.

Also see " Object Definitions" on page 272.

11. Verify the configuration by selecting the following in DMF Manager, select the following:

**Overview**

> **Configuration ...**

> **Validate Current Configuration**

If there are errors, fix them and repeat the validation until there are no errors.

12. If you are using the DMF Parallel Data-Mover Option, see "Parallel DMF Configuration Procedure" on page 485 and the *SGI InfiniteStorage Software Platform* release note.
13. Start the DMF environment. See "Starting and Stopping the DMF Environment" on page 181.
14. If you want to install the DMF client packages on other systems, see the *SGI InfiniteStorage Software Platform* release note and the client installation instructions.

To administer and monitor DMF, see Chapter 6, "DMF Manager" on page 191.

## Installation and Configuration Considerations

This section discusses the configuration considerations that will affect your system:

- "ISSP DMF Software" on page 169
- "Mounting Service Considerations" on page 170
- "Inode Size Configuration" on page 171
- "Daemon Database Record Length" on page 173
- "Interprocess Communication Parameters" on page 175
- "Automated Maintenance Tasks" on page 175
- "Networking Considerations for Parallel Data-Mover Option" on page 176
- "Passwordless SSH Configuration for DMF" on page 176
- "Suppressing RSCN on Host Port HBAs" on page 177
- "QLogic® Fibre Channel Switch" on page 178
- "IPv6" on page 181

### ISSP DMF Software

The ISSP release includes the following DMF software:

- **DMF Server**, which provides:
  - The full set of DMF server functionality, including the DMF daemon, infrastructure, user and administrator commands, and all man pages. This applies to SGI x86\_64 servers running the operating system as specified in the ISSP and DMF release notes. You should install this software only on those machines that can be the DMF server.
  - Client installers, which download the client software onto the DMF server so that you can later transfer the DMF client software to the DMF client nodes. The client packages are installed along with their installation instructions on the DMF server in the following directory:

*/opt/dmf/client-dist/DMFVERSION/clientOS/clientarchitecture*

The client software contains a limited set of DMF functionality. This applies to all supported operating systems. You should install this software on machines from which you want to give users access to DMF operations, such as migrating and recalling files..

- **DMF Parallel Data-Mover**, which provides the infrastructure for parallel data-mover nodes to move data offline and retrieve it, plus the required underlying CXFS client-only software.

Only one group of software can be installed on a given machine.

## Mounting Service Considerations

Mounting services are available through OpenVault or the Tape Management Facility (TMF)

The LS checks the availability of the mounting service when it is started and after each occurrence in which an LS data-mover process was unable to reserve its drive. The data-mover process may be either:

- A *write child* that migrates data to secondary storage
- A *read child* that recalls data from secondary storage

If the mounting service is unavailable, the LS does not start any new child processes:

- For OpenVault, the LS sends an e-mail message to the administrator, asking that OpenVault be started. It then periodically polls OpenVault until it becomes available, at which time child processes are again allowed to run.
- For TMF, the LS attempts to initiate `tmdaemon` if it is not up (based on the exit status of `tmstat`) and waits until a TMF device in the `configuration pending` state is configured up before it resumes processing. If TMF cannot be started or if no devices are configured up, the LS sends e-mail to the administrator and polls TMF until a drive becomes available.

You can use `MAX_MS_RESTARTS` to configure the number of automatic restarts.

See also Chapter 9, "Mounting Service Configuration Tasks" on page 491



## Inode Size Configuration

In managed filesystems and disk cache manager (DCM) MSP *STORE\_DIRECTORY* filesystems, DMF state information is kept within a filesystem structure called an *extended attribute*.

Extended attributes can be either inside the inode or in attribute blocks associated with the inode. DMF runs much faster when the extended attribute is inside the inode, because this minimizes the number of disk references that are required to determine DMF information. In certain circumstances, there can be a large performance difference between an inode-resident extended attribute and a non-resident extended attribute.

The size of inodes within a filesystem impacts how much room is available inside the inode for storing extended attributes. Smaller inode sizes have much less room available for attributes. Likewise, the legacy inode attribute format (`-i attr=1` option to `mkfs.xfs`) results in less available extended attribute space than does the current default format (`-i attr=2` option).

SGI recommends that you configure your filesystems so that the extended attribute is always inode-resident. Whenever both 256-byte and 512-byte inode sizes will work, you should use the 256-byte inode size (`-i size=256` option to `mkfs.xfs`) because the inode scans will be up to twice as fast. SGI also highly recommends that you use `attr2` (`-i attr=2` option) when possible if it allows 256-byte inode sizes to be used.

For optimal performance, you should create any DCM MSP filesystems with 256-byte inode sizes and `attr2` attribute format. (For other filesystems for DMF administrative directories, the inode size does not matter.) For best performance, you should use 512-byte inode sizes for managed filesystems only under the following circumstances:

- If users require other XFS attributes such as ACLs or other user-specified attributes
- If the filesystem will have large numbers of partial-state files with more partial-state regions than will fit in a 256-byte inode

If you must have a 512-byte inode size for a managed filesystem, you can do so by using the Linux `mkfs.xfs` command with the `-i size=512` option. (Filesystems that already exist must be backed up, recreated, and restored.)

Table 5-1 summarizes the relationship among the inode size, `attr` type, and file regions.

**Table 5-1** Default Maximum File Regions for XFS and CXFS Filesystems

| Size of inode  | attr Type | Default Maximum Number of File Regions |
|----------------|-----------|----------------------------------------|
| 256            | 1         | (Not recommended)                      |
| 256            | 2         | 2                                      |
| 512 or greater | 1         | 8                                      |
| 512 or greater | 2         | 11                                     |

For more information about setting the inode size and the attr type, see the `mkfs.xfs(8)` and `mount(8)` man pages.

## Daemon Database Record Length

A daemon database entry contains one or more fixed-length records:

- The base record (`dbrec`), which consists of several fields, including the `path` field
- Zero or more path segment extension (`pathseg`) records

If the value that is returned to the daemon by the MSP/LS (such as the pathname resulting from the `NAME_FORMAT` value template in a cloud, disk, or FTP `msp` object) can fit into the `path` field of the daemon's `dbrec` record, DMF does not require `pathseg` records. If the MSP/LS supplies a path value that is longer than the `path` field, DMF creates one or more `pathseg` records to accommodate the extra space.

The default size of the `path` field of the `dbrec` is 34 characters. This size allows the default paths returned by `dmatis`, `dmcloudmsp`, `dmdskmsp`, and `dmftpmmsp` to fit in the `path` field of `dbrec` as long as the user name portion of the `dmcloudmsp`, `dmdskmsp`, or `dmftpmmsp` or default path (*username/bit\_file\_identifier*) is 8 characters or fewer. If you choose to use a value for `NAME_FORMAT` that results in longer pathnames, you may want to resize the `path` field in `dbrec` in order to increase performance.

The default size of the `path` field in the `pathseg` record is 64. For MSP path values that are just slightly over the size of the `dbrec` `path` field, this will result in a large amount of wasted space for each record that overflows into the `pathseg` record. The ideal situation would be to have as few `pathseg` records as possible, because retrieving `pathseg` records slows down the retrieval of daemon database records.

The size of the `path` field in the daemon `dbrec` record can be configured at any time before or after installation. (The same holds true for any installation that might be using `dmcloudmsp`, `dmdskmsp`, or `dmftpmmsp` with a different path-generating algorithm or any other MSP that supplies a path longer than 34 characters to the daemon.)

### Procedure 5-2 Configuring the Daemon Database Record Length

The steps to configure the daemon database entry length are as follows:

1. If `dmfdaemon` is running, ensure that DMF is stopped. In an HA environment, see *High Availability Guide for SGI InfiniteStorage*. In a non-HA environment, execute the following:

```
dmfserver# service dmf stop
```



---

**Caution:** For instructions about starting and stopping DMF and the mounting service in an HA environment, see *High Availability Guide for SGI InfiniteStorage*.

---

2. If a daemon database already exists, perform the following commands:

```
dmfserver# cd HOME_DIR/daemon
dmfserver# dmdump -c . > textfile
dmfserver# cp dbrec* pathseg* dmd_db.dbd backup_dir
dmfserver# rm dbrec* pathseg* dmd_db.dbd
```

Where:

- *HOME\_DIR* is the value of `HOME_DIR` returned by the `dmconfig base` command
  - *textfile* is the name of a file that will contain the text representation of the current daemon database
  - *backup\_dir* is the name of the directory that will hold the old version of the daemon database
3. Change to the `rdm` directory:

```
dmfserver# cd /usr/lib/dmf/rdm
```
  4. Back up the `dmd_db.dbd` and `dmd_db.ddl` files that reside in `/usr/lib/dmf/rdm`. This will aid in disaster recovery if something goes wrong.
  5. Edit `dmd_db.ddl` to set the new `path` field lengths for the `dbrec` and/or `pathseg` records.
  6. Regenerate the new daemon database definition, as follows:

```
dmfserver# /usr/lib/dmf/support/dmddlp -drsx dmd_db.ddl
```
  7. Back up the new versions of `dmd_db.dbd` and `dmd_db.ddl` for future reference or disaster recovery.

8. If the daemon database was backed up to text (to *textfile* in step 2), enter the following commands:

```
dmfserver# cd HOME_DIR/daemon
dmfserver# dmdadm -u -c "load textfile"
```

9. If the daemon was running in step 1, ensure that the `dmf` service is started. In a non-HA environment, execute the following:

```
dmfserver# service dmf start
```

## Interprocess Communication Parameters

Ensure that the following interprocess communication kernel configuration parameters are set equal to or greater than the default before running DMF:

```
MSGMAX
MSGMNI
```

For more information, execute `info ipc` and see the `sysctl(8)` and `msgop(2)` man pages.

## Automated Maintenance Tasks

DMF lets you configure parameters for completing periodic maintenance tasks such as the following:

- Making backups (full or partial) of managed filesystems to tape or disk
- Making backups of DMF databases to disk
- Removing old log files and old journal files
- Monitoring DMF logs for errors
- Monitoring the status of volumes in LSs
- Running hard deletes
- Running `dmaudit(8)`
- Merging volumes that have become sparse (and stopping this process at a specified time)

Each of these tasks can be configured in the DMF configuration file (`/etc/dmf/dmf.conf`) through the use of `TASK_GROUPS` parameters for the DMF daemon and the LS. The tasks are then defined as objects.

For each task you configure, a time expression defines when the task should be done and a script file is executed at that time. The tasks are provided in the `/usr/lib/dmf` directory.

The automated tasks are described in "taskgroup Object" on page 304.

## Networking Considerations for Parallel Data-Mover Option

The parallel data-mover nodes communicate with the DMF and OpenVault servers over the network. By default, they use the IP addresses that are associated with the system hostnames. Additionally, depending on your configuration, it is possible that socket merging can occur between hosts. By default, this feature uses the same network as other DMF communication traffic.

It is possible to configure DMF to use an alternative network for general communication between DMF nodes as well as an alternative network for socket merges. See "node Object" on page 294.

If you use an alternative network for DMF communication, the OpenVault server must listen on the same network; in this case, the name you specify for the initial OpenVault prompt (that asks you to supply the name where OpenVault will be listening) will be different from the hostname of the DMF server. See comment 2 in "Configure the OpenVault Server" on page 492.

## Passwordless SSH Configuration for DMF

If configured, DMF will use passwordless secure shell (SSH) to do the following.

- Transfer a copy of nonintegrated disk backups to one or more remote directories (using the optional `DUMP_MIRRORS` DMF configuration file)
- Simplify the use of the `dmatsnf(8)` and `dmatread(8)` commands to verify the integrity of the library server (LS) volumes and recover data from them for a configuration where not all volumes are mountable on the DMF server
- When in an active-active HA configuration with parallel data-mover nodes, DMF Manager can represent the status of both mover nodes

- Gather troubleshooting data via the `dmcollect(8)` command from all potential DMF servers and parallel data-mover nodes.

You must set up SSH keys so that the local `root` user can log in to the remote host as a remote user without a password. Do the following:

1. Generate RSA authentication keys for the `root` user on the DMF server, if the keys do not already exist. Be sure that you **do not** enter a passphrase when prompted (just press `Enter`).

```
dmfserver# ssh-keygen -t rsa
Generating public/private rsa key pair.
Enter passphrase (empty for no passphrase):
Enter same passphrase again:
Your identification has been saved in /root/.ssh/id_rsa.
Your public key has been saved in /root/.ssh/id_rsa.pub.
...
```

2. Install the identity information on all nodes on which passwordless SSH access is required. For example:

- To provide access for the DMF server on two parallel data-mover nodes `pdm1` and `pdm2`:

```
dmfserver# ssh-copy-id -i ~/.ssh/id_rsa.pub root@pdm1
dmfserver# ssh-copy-id -i ~/.ssh/id_rsa.pub root@pdm2
```

- To provide access when using a remote host that has directories in which DMF will place a copy of nonintegrated disk backups (`DUMP_MIRRORS`):

```
dmfserver# ssh-copy-id -i ~/.ssh/id_rsa.pub user@remotehost
```

See the `ssh-keygen(1)` and `ssh-copy-id(1)` man pages for details.

## Suppressing RSCN on Host Port HBAs

To avoid cluster problems when one node in the cluster reboots, enable (turn ON) registered state change notification (RSCN) suppression on host port HBAs. (HBAs do not communicate with HBAs, therefore a port registration request does not need to occur between HBAs.) Use the `portcfgshow` command to display the current settings.





|               |                                                                                                                                                                                                                 |
|---------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| PortType      | Enter the appropriate type, usually F. (You cannot use the GL autonegotiated mode.)                                                                                                                             |
| NoClose       | Set to True to prevent the Fibre Channel circuit from shutting down during a host reboot.                                                                                                                       |
| IOStreamGuard | Set to Enable only on ports connected to initiator devices (HBAs). This feature suppresses the generation of RSCN messages on a port basis. (You cannot use Auto mode because most HBAs cannot negotiate this.) |

To modify these parameters, use the `admin` command. For example, for a port connected to an SGI UV® 100 system:

```
SANbox #> admin start
```

```
SANbox (admin) #> config edit
```

```
The config named default is being edited.
```

```
SANbox (admin-config) #> set config port 31
```

A list of attributes with formatting and current values will follow.  
Enter a new value or simply press the ENTER key to accept the current value.  
If you wish to terminate this process before reaching the end of the list  
press 'q' or 'Q' and the ENTER key to do so.

```
Configuring Port Number: 31
```

```
-----
```

```
AdminState      (1=Online, 2=Offline, 3=Diagnostics, 4=Down) [Online]
LinkSpeed       (1=1Gb/s, 2=2Gb/s, 4=4Gb/s, A=Auto)   [Auto ]  2
PortType        (GL / G / F / FL / Donor)                 [GL    ]  F
SymPortName     (string, max=32 chars)                          [Port31] UV100
ALFairness      (True / False)                                     [False ]
DeviceScanEnable (True / False)                                 [True  ]
ForceOfflineRSCN (True / False)                                    [False ]
ARB_FF          (True / False)                       [False ]
InteropCredit   (decimal value, 0-255)                  [0     ]
ExtCredit       (dec value, increments of 15, non-loop only) [0     ]
FANEnable       (True / False)                     [True  ]
AutoPerfTuning  (True / False)                               [True  ]
MSEnable        (True / False)                     [True  ]
```

## 5: Installing and Configuring the DMF Environment

---

```
NoClose          (True / False)          [False ] True
IOStreamGuard    (Enable / Disable / Auto) [Auto ] Enable
PDISCPingEnable  (True / False)          [True  ]
```

Finished configuring attributes.

This configuration must be saved (see config save command) and activated (see config activate command) before it can take effect. To discard this configuration use the config cancel command.

....

```
SANbox (admin-config) #> config save
```

The config named default has been saved.

```
SANbox (admin) #> config activate
```

The currently active configuration will be activated.

Please confirm (y/n): [n] **y**

```
SANbox (admin) #> admin end
```

```
SANbox #> show config port 31
```

Configuration Name: default

-----

Port Number: 31

-----

```
AdminState      Online
LinkSpeed       2Gb/s
PortType        F
SymbolicName    UV100
ALFairness      False
DeviceScanEnabled True
ForceOfflineRSCN False
ARB_FF          False
InteropCredit   0
ExtCredit       0
FANEnabled      True
AutoPerfTuning  True
MSEnabled       True
NoClose         True
```

```
IOStreamGuard      Enabled
PDISCPingEnabled   True
```

## IPv6

To implement DMF with IPv6, do the following:

- Add IPv6 to the `flags` parameter in the `/etc/xinetd.d/tcpmux` file:

```
flags          = IPv6 IPv4
```

- Change to the `/etc/vsftpd.conf` file `listen` parameter to specify IPv6:

```
#listen=YES
listen_ipv6=YES
```

---

**Note:** You should comment-out or remove the `listen` parameter, because it is mutually exclusive with the `listen_ipv6` parameter.

---

## Starting and Stopping the DMF Environment

This section discusses the following:

- "Automatic Start After Reboot" on page 182
- "Preventing Automatic Start After Reboot" on page 182
- "Explicit Start" on page 183
- "Explicit Stop" on page 183

For more information about the mounting services, see:

- *TMF 6 Administrator Guide for SGI InfiniteStorage*
- *OpenVault Administrator Guide for SGI InfiniteStorage*



**Caution:** In an HA environment, procedures differ. For example, you must first remove HA control of the resource group before stopping DMF and the mounting service. See *High Availability Guide for SGI InfiniteStorage*.

---

## Automatic Start After Reboot

---

**Note:** For instructions about starting and stopping DMF and the mounting service in an HA environment, see *High Availability Guide for SGI InfiniteStorage*

---

To enable automatic startup of the DMF environment, execute the following `chkconfig(8)` commands as `root` on indicated nodes in a non-HA environment:

1. DMF server:

```
dmfserver# chkconfig pcp on
dmfserver# chkconfig pcp-storage on (optional)
dmfserver# chkconfig tmf on (if TMF)
dmfserver# chkconfig openvault on (if OpenVault)
dmfserver# chkconfig dmf on
dmfserver# chkconfig dmfman on (optional)
dmfserver# chkconfig dmfsoap on (optional)
```

2. Parallel data-mover nodes:

```
mover# chkconfig openvault on
mover# chkconfig dmf_mover on
```

## Preventing Automatic Start After Reboot

---

**Note:** For instructions about starting and stopping DMF and the mounting service in an HA environment, see *High Availability Guide for SGI InfiniteStorage*.

---

To prevent automatic startup of the DMF environment, execute the following `chkconfig(8)` commands as `root` on the indicated nodes in a non-HA environment:

1. DMF server:

```
dmfserver# chkconfig dmfsoap off
dmfserver# chkconfig dmfman off
dmfserver# chkconfig dmf off
dmfserver# chkconfig openvault off (if OpenVault)
dmfserver# chkconfig tmf off (if TMF)
```

2. Parallel data-mover nodes:

```
mover# chkconfig dmf_mover off
mover# chkconfig openvault off
```

## Explicit Start

---

**Note:** For instructions about starting and stopping DMF and the mounting service in an HA environment, see *High Availability Guide for SGI InfiniteStorage*.

---

To start the DMF environment daemons explicitly, execute the following on the indicated nodes in a non-HA environment:

1. DMF server:

```
dmfserver# service pcp start
dmfserver# service pcp-storage start (optional)
dmfserver# service tmf start (if TMF)
dmfserver# service openvault start (if OpenVault)
```

2. Parallel data-mover nodes:

```
mover# service openvault start
```

3. DMF server:

```
dmfserver# service dmf start
```

4. Parallel data-mover nodes:

```
mover# service dmf_mover start
```

5. DMF server:

```
dmfserver# service dmfman start (optional)
dmfserver# service dmfsoap start (optional)
```

## Explicit Stop

---

**Note:** For instructions about starting and stopping DMF and the mounting service in an HA environment, see *High Availability Guide for SGI InfiniteStorage*.

---

To stop the DMF environment daemons explicitly, execute the following on the indicated nodes in a non-HA environment:

1. DMF server:

```
dmfserver# service dmfssoap stop      (if started)
dmfserver# service dmfmman stop      (if started)
```

2. Parallel data-mover nodes:

```
mover# service dmf_mover stop
```

---

**Note:** Executing `service dmf_mover stop` on a mover node will cause existing data-mover processes to exit after the LS notices this change, which may take up to two minutes. The existing data-mover processes may exit in the middle of recalling or migrating a file; this work will be reassigned to other data-mover processes.

---

3. DMF server:

```
dmfserver# service dmfs stop
```

4. Parallel data-mover nodes:

```
mover# service openvault stop
```

5. DMF server:

```
dmfserver# service openvault stop      (if OpenVault)
dmfserver# service tmf stop            (if TMF)
dmfserver# service pcp-storage stop    (if started)
dmfserver# service pcp stop
```

## Using Out-of-Library Tapes

The mechanism for handling tape volumes that are physically not in the tape library varies depending on the mounting service:

- "TMF and Out-of-Library Tapes" on page 185
- "OpenVault and Out-of-Library Tapes" on page 185

## TMF and Out-of-Library Tapes

When TMF is the mounting service, the `msgd(8)` command displays requests to import volumes. With TMF, DMF has no knowledge of what tapes are out of the library.

## OpenVault and Out-of-Library Tapes

When OpenVault is the mounting service and a recall request is made for a tape that is physically not in the library, DMF will first try to read from copies on other volumes before it requests that the out-of-library tape be imported. If the reads from all other copies fail (for example, because their volumes are locked with the `hlock` flag), then DMF will request that the tape be imported.

If the desired volume is in the process of being written to, DMF will wait before requesting that a tape be imported; this occurs whether or not the `FORWARD_RECALLS` configuration parameter is set to `ON` (see "volume group Object" on page 410). If one of the copies is on a tape that is physically out of the library, DMF will wait for the drives to become usable even if the `REDIRECT_TIME_DG_DOWN` parameter has been set (see "drive group Object Parameters" on page 397).

DMF will request that the tape be imported before waiting for a copy in a library that has been permanently disabled with `ov_library -D`; see the `ov_library(8)` man page.

When a tape must be imported, DMF will send an email and issue an alert; you can use the `dmoper(1)` command to display these requests.

Example scenarios using volume groups named `vgA`, `vgB`, and `vgC`:

- Suppose that:
  - `vgA` contains the primary copy but is not in the library
  - `vgB` contains a secondary copy
  - `FORWARD_RECALLS` is configured `OFF` (the default)
  - The OpenVault library is enabled

In this case, DMF will first try to recall from `vgB`. If that fails (for example, if `vgB`'s hold flags do not permit its use), then DMF will ask that the tape belonging to `vgA` be imported.

- Suppose that:

- `vgA` contains the primary copy but its library is permanently disabled via the `ov_library -D` command
- `vgB` contains a secondary copy whose tape is not in the library
- `vgC` holds a tertiary copy but its tape is currently being written to
- `FORWARD_RECALLS` is configured ON for all three VGs

In this case, DMF will wait for the tape in `vgC` to become available. If that recall fails, then DMF will ask that the tape in `vgB` be imported. If that recall also fails, then DMF will wait for the library containing `vgA` to be enabled.

With OpenVault, also note the following:

- Tapes that are not in the library are not eligible for migrations or merging. See the `hextern` flag in "dmvoladm Directives" on page 555 for more information.
- The tapes that contain volume serial numbers used for backup tasks (as specified by the `DUMP_TAPES` configuration parameter) may not be out of the library.

## Customizing DMF

You can modify the default behavior of DMF as follows:

- "File Tagging" on page 186
- "Site-Defined Policies" on page 187
- "Site-Defined Client Port Assignment in a Secure Environment" on page 188

### File Tagging

*File tagging* allows an arbitrary 32-bit integer to be associated with specific files so that they can be subsequently identified and acted upon. The specific values are chosen by the site; they have no meaning to DMF.

Non-`root` users may only set or change a tag value on files that they own, but the `root` user may do this on any files. The files may or may not have been previously migrated.



To set a tag, use the `dmtag(1)` command or the `libdmfusr.so` library. For example:

```
% dmtag -t 42 myfile
```

To view the tag set for a given file, use the `dmtag` or `dmattr` commands. For example:

```
% dmtag myfile
42 myfile
% dmattr -a sitetag myfile
42
```

You can test a file's tag in the `when` clause of the following configuration parameters by using the keyword `sitetag`:

```
AGE_WEIGHT
CACHE_AGE_WEIGHT
CACHE_SPACE_WEIGHT
SELECT_LOWER_VG
SELECT_MSP
SELECT_VG
SPACE_WEIGHT
```

For example:

```
SELECT_VG fasttape when sitetag = 42
```

You can also access it in site-defined policies, as described below.

For more information, see the `dmtag(1)` man page.

## Site-Defined Policies

*Site-defined policies* allow you to do site-specific modifications by writing your own library of C++ functions that DMF will consult when making decisions about its operation. For example, you could write a policy that decides at migration time which volume group (VG) or MSP an individual file should be sent to, using selection criteria that are specific to your site.

---

**Note:** If you customize DMF, you should inform your users so that they can predict how the user commands will work with your policies in place. You can add error, warning, and informational messages for commands so that the user will understand why the behavior of the command differs from the default.

---

For information about the aspects of DMF that you can modify, see Appendix C, "Site-Defined Policy Subroutines and the `sitelib.so` Library" on page 735.

### Site-Defined Client Port Assignment in a Secure Environment

If you have a secure environment and if you require more than 512 active connections between DMF clients and the DMF server, you can specify that DMF assign a specific range of TCP ports.



---

**Caution:** If the environment is not secure, do not use this feature.

---

When a user executes a remote DMF client command, the user-command mechanism initiates a trusted `setuid root dmusrCmd(8)` process on the client. This `dmusrCmd` process performs all of the access validation required to send the user request the DMF server. By default, the remote `dmusrCmd` process verifies that it connects to the original client `dmusrCmd` process via a reserved port number in the range 512-1023; these port numbers are only available to trusted (`root`) processes. If all of those ports are in use, the `dmusrCmd` process will block until one of the trusted ports is free.

If your environment is secure (and therefore assigning a port that is not reserved for a trusted process is acceptable) and you require more than 512 active ports, you can create a `/usr/lib/dmf/dmf_client_ports` file on every potential DMF server and every DMF client. The file on the potential DMF servers must contain every port on which a client is allowed to connect, and the file on each DMF client must contain the ports that client is allowed to access. The file must be owned by `root` and have an access mode of `0600`.

You can use a range to specify the permitted ports. The format of the file is one or more lines as follows:

*start\_port\_number: end\_port\_number*

The *start\_port\_number* value must be greater than or equal to 512 and must be less than or equal to *end\_port\_number*. The order of the lines in the file is significant in

that `dmusrCmd` will start attempting to assign port numbers with the first line and process the lines in the order they appear in the file.

For example:

- To assign ports in the range 5000–6000:

```
5000:6000
```

- To first assign ports in the range 7000–8000 and then assign ports in the range 5000–6000 (and never assign ports in the range 6001–6999):

```
7000:8000
```

```
5000:6000
```

If the file exists but is empty, `dmusrCmd` will not attempt to bind to any particular port numbers, but will use the non-secure port that is assigned to it by the kernel.

If the file does not exist, the default behavior of only assigning ports 512-1023 will be enforced.

## Importing Data From Other HSMs

DMF has utilities to assist with importing data from filesystems managed by other hierarchical storage management (HSM) packages into DMF, provided that the filesystems to be imported are accessible via FTP or as local or NFS-mounted filesystems. These tools are not distributed with the DMF product. They are for use only by qualified SGI Professional Services personnel who assist sites doing conversions. For more information, contact SGI Professional Services.



## DMF Manager

This chapter discusses the following:

- "Accessing DMF Manager" on page 192
- "Getting Started with DMF Manager" on page 192
- "Running Observer Mode or admin Mode" on page 195
- "Getting More Information in DMF Manager" on page 198
- "Setting Panel Preferences" on page 201
- "Refreshing the View" on page 202
- "Managing Licenses and Data Capacity with DMF Manager" on page 203
- "Configuring DMF with DMF Manager" on page 210
- "Displaying DMF Configuration File Parameters" on page 219
- "Starting and Stopping DMF and the Mounting Service" on page 220
- "Discovering DMF Problems" on page 221
- "Filtering Alerts" on page 225
- "Seeing Relationships Among DMF Components" on page 227
- "Managing Volumes" on page 229
- "Managing Libraries" on page 232
- "Displaying DMF Manager Tasks" on page 233
- "Monitoring DMF Performance Statistics" on page 233
- "Displaying Node Status" on page 252
- "Restoring Filesystems in DMF Manager" on page 255
- "Disaster Recovery in DMF Manager for Basic DMF" on page 262
- "Viewing the DMF Queue" on page 263
- "LTFS in DMF Manager" on page 263

## Accessing DMF Manager

To access DMF Manager, do the following:

1. Point your browser to the following secure address:

`https://YOUR_DMF_SERVER:11109`

2. Accept the security certificate.

---

**Note:** DMF Manager generates its own SSL certificates, rather than having the SSL certificates signed by a commercial certificate authority. Therefore, the certificate warning is safe to ignore.

---

Also see "Running Observer Mode or admin Mode" on page 195.

## Getting Started with DMF Manager

DMF Manager lets you configure DMF, install licenses, view the current state of your DMF system, and make operational changes.

When you initially open DMF Manager, you will see the **Overview** panel, which displays a high-level graphical view of the DMF environment and status for each DMF component, as shown in Figure 6-1. You can also configure DMF from this panel.

Each menu bar selection provides access to a DMF Manager panel, described in Table 6-1. To open a panel, click on the panel name in the menu. Right-click on the tab title to see its menu. Each panel has a key for its symbols.

---


**Note:** Some DMF Manager windows do not automatically update; choose the **Refresh** menu item to update an existing view.

---

Table 6-1 DMF Manager Panel Menus

| Menu Bar Item        | Panel Name               | Description                                                                                                                                                                              |
|----------------------|--------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Configuration</b> | <b>Overview</b>          | High-level graphical view of the DMF environment, status for each DMF component, and configuration capability                                                                            |
|                      | <b>Parameters</b>        | Details about the current parameter settings in the DMF configuration file and status for each DMF component                                                                             |
|                      | <b>Licenses</b>          | Information about installed DMF, CXFS, and SGI Management Center licenses and the ability to add and delete licenses (when logged in as <code>admin</code> )                             |
| <b>Storage</b>       | <b>Volumes</b>           | Status of <i>volumes</i> : physical tapes, SGI 400 virtual tape library (VTL) virtual tapes, COPAN massive array of idle disks (MAID) volumes, LTFS-assigned tapes, and unassigned tapes |
|                      | <b>Libraries</b>         | Status of libraries, DMF drives, and LTFS drives; the ability to manage drives and their assignment to LTFS or DMF                                                                       |
| <b>Messages</b>      | <b>Reports</b>           | Daily activity reports                                                                                                                                                                   |
|                      | <b>Alerts</b>            | Informational messages, warnings, and critical errors                                                                                                                                    |
|                      | <b>DMF Manager Tasks</b> | Status of commands issued via DMF Manager that may take time to complete                                                                                                                 |
| Statistics           | <b>DMF Activity</b>      | Current and historical reports about the state and the performance of the DMF requests and throughput                                                                                    |
|                      | <b>DMF Resources</b>     | Current and historical reports about the state and the performance of the DMF filesystems and hardware                                                                                   |
|                      | <b>DMF I/O</b>           | Statistics about how DMF is using data and various kinds of specific media                                                                                                               |
| <b>QView</b>         | <b>QView</b>             | Reports that provide details about the DMF processing queue and the ability to cancel or change the priority of a given request                                                          |
| <b>Backups</b>       | <b>Recovery</b>          | Capability to restore components from a list of available integrated-backup dumps and to restore filesystems from any DMF backup session                                                 |
| <b>Help</b>          | <b>Getting Started</b>   | This section                                                                                                                                                                             |

| Menu Bar Item | Panel Name               | Description                                      |
|---------------|--------------------------|--------------------------------------------------|
|               | <b>Admin Guide</b>       | This manual                                      |
|               | <b>About DMF Manager</b> | Version and copyright information about the tool |



**Figure 6-1** DMF Manager Overview Panel

Some panels have expandable folders. Click on the “+” symbol to expand a folder or on the “—” symbol to contract it, or use the **Expand All** and **Collapse All** buttons. Click on a report name to display the associated graphs. For example, see Figure 6-21 on page 229.



## Running Observer Mode or admin Mode

You can run DMF Manager in observer mode (the default) or you can log in to admin mode for more functionality, as described in the following sections:

- "Observer Mode Functionality" on page 195
- "admin Mode Functionality" on page 196
- "Admin Mode Access" on page 198

### Observer Mode Functionality

In the default observer mode in DMF Manager, you can do the following:

- View the state of DMF and the mounting service. See:
  - "Getting Started with DMF Manager" on page 192
  - "Discovering DMF Problems" on page 221
- View the fullness of each managed filesystem. See:
  - "Getting Started with DMF Manager" on page 192
  - "Discovering DMF Problems" on page 221
- View the licensed capacity. See "Showing Current DMF Usage and Licensed Capacity" on page 205.
- View installed DMF, CXFS, XVM, and SGI Management Center licenses and the system information required to request a new license. See "Managing Licenses and Data Capacity with DMF Manager" on page 203.
- View DMF's configuration. See "Displaying DMF Configuration File Parameters" on page 219.
- View relationships among DMF components. See "Seeing Relationships Among DMF Components" on page 227.
- Get context-sensitive help and view the DMF administration guide. See "Getting More Information in DMF Manager" on page 198.

- View information about volumes:
  - View each volume's status and fullness
  - Sort which volumes to view
  - Display dump tapes (physical tapes and SGI 400 VTL virtual tapes)
  - View the status of each drive
  - Temporarily create a user-defined query

---

**Note:** Saving the query requires admin mode. See "admin Mode Functionality" on page 196.

---

See:

- "Getting Started with DMF Manager" on page 192
- "Managing Volumes" on page 229
- View the status of libraries, LTFS tapes, and unassigned tapes that could be assigned to LTFS
- View the daily reports (with history) and DMF alerts. See "Discovering DMF Problems" on page 221.
- View the long-running DMF Manager tasks (those currently executing and a history of executed tasks). See "Displaying DMF Manager Tasks" on page 233.
- View current and historical reports about DMF activity and resources. See "Monitoring DMF Performance Statistics" on page 233.

### **admin Mode Functionality**

If you log in to admin mode, you can perform the additional tasks such as the following:

- Add licenses to or delete licenses from the `/etc/lk/keys.dat` system license file or the DMF license file specified by the `LICENSE_FILE` configuration parameter (see "base Object Parameters" on page 278).
- Start/stop DMF and the mounting service. See "Starting and Stopping DMF and the Mounting Service" on page 220.

- Create or modify the DMF configuration. See "Configuring DMF with DMF Manager" on page 210.
- Create and modify the LTFS configuration. See "Configuring LTFS using DMF Manager" on page 265.
- Mount, unmount, and assign LTFS tapes; reserve a drive for LTFS use or reassign a drive to DMF. See "LTFS in DMF Manager" on page 263.
- Manage volumes (physical tapes, SGI 400 VTL virtual tapes, and COPAN MAID volumes):
  - Change the hold flags
  - Manually mark a volume as *sparse*, meaning containing blank or inactive areas after data has been deleted. (The data from a sparse volume will be later moved to another volume via *volume merging*, the mechanism provided by the LS for copying active data from volumes that contain largely obsolete data to volumes that contain mostly active data.) For more information, see "Volume Merging" on page 543.

---

**Note:** Merging is not appropriate for a volume configured as a fast-mount cache.

---

- Empty a damaged volume of all useful data and restore another copy in the volume group (VG)
- Eject physical tape cartridges from the tape library
- Load physical tape cartridges into the tape library and configure them for DMF's use with OpenVault
- Read data to verify the volume's integrity
- Enable/disable drives

See "Managing Volumes" on page 229.

- Acknowledge DMF alerts. See "Discovering DMF Problems" on page 221.
- Control long-running DMF Managed tasks (acknowledge, suspend/resume, or kill). See "Displaying DMF Manager Tasks" on page 233.

## Admin Mode Access

To log in to DMF Manager as the admin user, click the **Log In** button in the upper-right corner of the window, as shown in Figure 6-1 on page 194.

The default admin password is `INSECURE`. You should change the admin password and only provide it to those persons who you want to make administrative changes. (After you change the admin password, you cannot administratively set it to `INSECURE` again.)


---

**Note:** If you are upgrading from a release prior to DMF 5.4, the admin password will be reset to `INSECURE`. You should change the admin password to a site-specific value after upgrading.

---

## Getting More Information in DMF Manager

Each panel that uses icons has a key for its symbols, available via the **Show Key** menu selection. Figure 6-2 shows the key to icons on the **Overview** panel.



**Figure 6-2** Overview Key to Symbols

To display information about an object, you can move the mouse button over the object, as shown for the burn server in Figure 6-3.





Figure 6-3 Displaying Information About an Icon

To get more information about any item, right-click on it and select the **What is this?** option. For example, Figure 6-4 shows the help text for the Alerts icon.



**Figure 6-4** “What Is ...” Information

Each panel also has a **What is 'PanelName'?** menu selection.

For a quick-start to using DMF Manager, select the following from the menu bar:

**Help**  
    > **Getting Started**

To access the DMF administrator guide (this manual), select the following:

**Help**  
    > **Admin Guide**

## Setting Panel Preferences

Each DMF Manager panel (other than the **Help** panels) has a **Set PanelName Preferences** menu item that allows you to vary what is shown on the panel, how it behaves, and how often it is refreshed (see "Refreshing the View" on page 202).

For example, Figure 6-5 shows the preferences that you can set for the **Overview** panel.



Figure 6-5 DMF Manager Overview Preferences Panel

## Refreshing the View

Some DMF Manager panels refresh automatically by default but others do not. To refresh a panel, choose the **Refresh *PanelName*** menu item.



**Caution:** If you refresh the **Overview** panel while in configuration mode, any changes that have been made but not saved or applied will be lost and you will exit from configuration mode.

---



You can use **Set *PanelName* Preferences** menu to set an automatic refresh interval for individual panels. See "Setting Panel Preferences" on page 201.

---

**Note:** A refresh interval that is too short can cause contention between the DMF server and the browser. On heavily used systems, some displays may not be refreshed at extremely low intervals because the time to gather the information exceeds the refresh time. In such cases, you will only see a refresh as often as one can be completed.

---

## Managing Licenses and Data Capacity with DMF Manager

This section discusses the following:

- "Adding New Licenses" on page 203
- "Deleting Existing Licenses" on page 204
- "Viewing the Installed Licenses" on page 205
- "Showing Current DMF Usage and Licensed Capacity" on page 205
- "Showing Remaining Storage Capacity" on page 206

For more information, see Chapter 2, "DMF Licensing" on page 67.

### Adding New Licenses

To add one or more a new licenses, do the following:

1. Gather the required host information by viewing the **Licenses** panel. For more information, see "Gathering the Host Information" on page 74.
2. Obtain the required keys from SGI. See "Obtaining the License Keys" on page 75.
3. Log in to DMF Manager as `admin`.
4. Paste the keys into the text-entry area of the **Licenses** panel, highlighted in Figure 6-6.
5. Click the **Add license** button.




Figure 6-6 Adding a License Key in DMF Manager

In a DMF server HA configuration, you can add licenses to all potential DMF servers. Select the node to be acted on by choosing its name from the **Showing license from /etc/lk/keys.dat on** prompt.

### Deleting Existing Licenses

To delete one or more existing licenses, do the following:

1. Log in to DMF Manager as admin.

2. Select the licenses you want to delete by clicking their check boxes.
3. Right-click anywhere in the table and select **Delete selected licenses**.

In an HA configuration, you can delete licenses from all potential DMF servers in the HA cluster. Select the node to be acted on by choosing its name from the **Showing license from /etc/lk/keys.dat on prompt**.

## Viewing the Installed Licenses

To see the currently installed licenses for the server running DMF Manager, select:

**Configuration**  
> **Licenses**

The **Licenses** panel lists the currently installed DMF, CXFS, XVM, and SGI Management Center licenses. By default, the licenses display in the same order in which they appear in the `/etc/lk/keys.dat` file. You can sort the table by clicking on the desired column header. To resize a column, select the boundary divider in the table header.

In an HA configuration, you can view licenses from all potential DMF servers in the HA cluster. Select the node to be acted on by choosing its name from the **Showing license from /etc/lk/keys.dat on prompt**.

## Showing Current DMF Usage and Licensed Capacity

To determine the current DMF usage and licensed capacity, right-click on the DMF icon in the **Overview** panel and select **Show Usage...**

You can also display this information by selecting the following:

**Configuration**  
> **Licenses**  
> **Show Usage...**

Figure 6-7 shows an example. For more information, see "Displaying Current DMF Data Capacity Use" on page 72.





Figure 6-7 Data Under Management and Data Charged to the Licenses

### Showing Remaining Storage Capacity

To display the total capacity, an estimate of the current total migrated data that is active, and an estimate of the writable space that is currently available, right-click on the DMF icon in the **Overview** panel and select **Show Capacity**. For example, Figure 6-8 shows the reports for two library servers.



**Figure 6-8** DMF Capacity

---

**Note:** To see accurate estimates, you must first set the size of each volume accurately. For details, see the `dmvoladm(8)` man page.


---

This displays an estimate of the remaining storage capacity for each volume group in each LS. It reports the following totals for all volumes in the listed VGs and LSs (data compression of data is not taken into account):

| <b>Field</b> | <b>Description</b>                                                                                     |
|--------------|--------------------------------------------------------------------------------------------------------|
| Volume Group | The name of volume group                                                                               |
| Size         | The total capacity in megabytes (MB)                                                                   |
| Active       | The total migrated data (in MB) that may be recalled (also represented as a percentage)                |
| Avail        | The total writable space (in MB) on all volumes within the VG or LS (also represented as a percentage) |

Locked volumes are noted and an informational message highlights their number for each LS.

For example, Figure 6-9 shows that the C00\_vg0 and C00\_vg0 VGs are almost full and therefore there might not be any more space available for migrations because they each have 2 volumes reserved for merges (set by the RESERVED\_VOLUMES parameter, see "volume group Object" on page 410).



**Figure 6-9** Remaining DMF Capacity

To display more information, such as volume size, select:

**Volumes**  
 > **Set Volumes Preferences**

To see details about specific volumes, select:

**Storage**  
 > **Volumes**

Check the desired items to display.

There may be additional space that can be reclaimed from data that was written and has since been hard deleted. For more information, see "Volume Merging" on page 543.

For more information about how the calculations are made, see the `dmcapacity(8)` man page.

## Configuring DMF with DMF Manager

You can establish and edit the DMF configuration by logging in as the admin user and using the **Overview** panel. If you make a change to the configuration, the background color will change to gray wallpaper displaying "Configuration mode", indicating that you must save or cancel your changes.

This section discusses the following:

- "Limitations to the DMF Configuration Capability" on page 211
- "Showing All Configured DMF Objects" on page 211
- "Setting Up a New DMF Configuration File" on page 212
- "Copying an Object" on page 215
- "Modifying an Object" on page 217
- "Creating a New Object" on page 217
- "Deleting an Object" on page 218
- "Validating Your Changes" on page 218
- "Saving Your Configuration Changes" on page 218
- "Exiting the Temporary Configuration without Saving" on page 219



## Limitations to the DMF Configuration Capability

The configuration capability in DMF Manager has the following limitations:

- Comments are not permitted in the configuration file created or modified by DMF Manager. If you edit an existing configuration file that has comments and save the file, the comments will be deleted from the updated configuration file.

---

**Note:** The original DMF configuration file, including the comments, will be preserved in a time-stamped copy (`/etc/dmf/dmf.conf.TIMESTAMP`).

---

- **Adding** site-specific objects or site-specific parameters is not supported (if site-specific items already exist in the DMF configuration file, they are preserved).
- DMF Manager cannot detect if multiple users have logged in as `admin` and are therefore capable of overwriting each other's changes. At any given time, only one user should log in as `admin` and make configuration changes.

## Showing All Configured DMF Objects

To see all currently configured objects, select:

**Overview**  
    > **Configure...**  
        > **Show All Configured Objects**

By default, all currently configured objects will also be shown after you make a configuration change and select **Continue**.

After you either save or cancel the configuration changes, the icons that are displayed will return to the preferences you have set. See "Setting Panel Preferences" on page 201.

## Setting Up a New DMF Configuration File

---

**Note:** For preliminary required steps, including installing the required software and creating the required filesystems, see "Overview of the Installation and Configuration Steps" on page 165.


---

When you first access DMF Manager, you must enter the DMF Manager admin password, which brings you to the sample configuration page that contains templates for the `base` object and `taskgroup` objects for daemon tasks and migration tasks. To create an appropriate DMF configuration file, individually add the required objects or select one of the preconfigured samples for assistance:

- Overview**
  - > **Configure ...**
    - > **Pre-Configured**
      - > *sample\_name*

You can also access this menu by right-clicking anywhere in the **Overview** panel.

The preconfigured items provide a starting point of objects that you can modify with specific information for your site. For example, Figure 6-10 shows the icons that will appear after you select **DCM MSP Sample**. The gray wallpaper indicates that the sample file has been loaded. The errors displayed will disappear after you validate the configuration.



**Figure 6-10** Temporary Workspace for a Preconfigured DCM MSP Sample

For example, the **DCM MSP Sample** selection includes the following objects:

- base object and dmdaemon object (represented by the DMF shield icon):
- filesystem object named /dmi\_fs
- msp object named dcm\_msp configured for a DCM MSP
- libraryserver object name ls

- `drivegroup` object name `dg0`
- `volume` objects named `vg1a`, `vg1b`, `vg1c`
- `task` objects named `daemon_tasks`, `dump_tasks`, `ls_tasks`, and `dcm_tasks`
- `policy` objects named `space_policy`, `dcm_policy`, and `vg_policy` configured for automated space management and MSP selection

For more information about these objects and their parameters, see Chapter 7, "DMF Configuration File" on page 271.

You can then modify the sample configuration as needed. See:

- "Copying an Object" on page 215
- "Modifying an Object" on page 217
- "Creating a New Object" on page 217
- "Deleting an Object" on page 218
- "Validating Your Changes" on page 218
- "Saving Your Configuration Changes" on page 218

To exit a preconfigured sample without saving any of your changes, select:

```
Overview
  > Configure...
      > Cancel Configuration
```

## Copying an Object

To copy an object, right-click on it and select:

**Configure ...**  
**> Copy**

Then name the new object and enter the values you desire for the object's parameters. For example, Figure 6-11 shows naming a copied filesystem object `/dmi_fs2`.

---

**Note:** Many parameters have default values, but these are not necessarily shown in the DMF Manager windows. Only explicitly specified values are shown by DMF Manager. If a parameter has no value specified, its default value is assumed.

---




Figure 6-11 Naming a Copied Object

To get more information about a parameter, right-click on it and select the **What is this?** option. See "Getting More Information in DMF Manager" on page 198.

To make your changes appear in the **Overview** display, select **Continue**. To permanently save your changes, see "Saving Your Configuration Changes" on page 218.

## Modifying an Object

To edit the parameters for an existing object, right-click on it and select:

**Configure ...**  
> **Modify**

Then enter the values you desire for the parameters shown. To get more information about a parameter, right-click on it and select the **What is this?** option. See "Getting More Information in DMF Manager" on page 198.

To rename an object, delete it and create a new object. See:

- "Copying an Object" on page 215
- "Creating a New Object" on page 217
- "Deleting an Object" on page 218

To make your changes in the temporary configuration view, select **Continue**. To permanently save your changes, see "Saving Your Configuration Changes" on page 218.

## Creating a New Object

To create a new object, right-click on blank space anywhere in the **Overview** panel and select the object. Also see "Setting Up a New DMF Configuration File" on page 212.

You can also right-click on an existing object and create another empty object of the same type by selecting:

**Configure ...**  
> **Add New**

Then name the object and enter the values you desire for the parameters shown. To get more information about a parameter, right-click on it and select the **What is this?** option. See "Getting More Information in DMF Manager" on page 198.

To make your changes appear in the **Overview** display, select **Continue**. To permanently save your changes, see "Saving Your Configuration Changes" on page 218. Also see "Exiting the Temporary Configuration without Saving" on page 219.

## Deleting an Object

To delete an object, right-click on it and select:

**Configure ...**  
> **Delete**

## Validating Your Changes

To verify that your changes to the temporary configuration are valid, select the following:

**Overview**  
> **Configure ...**  
> **Validate Configuration**

## Saving Your Configuration Changes

To make your changes appear in the **Overview** display for this DMF Manager session, click **Continue** after creating or modifying an object. (This does not change the DMF configuration file.)

To save the temporary configuration so that you can work on it later, select:

**Overview**  
> **Configure ...**  
> **Save Temporary Configuration**

To permanently save your changes and apply them to the DMF configuration file, do the following:

1. Verify that your changes are valid. See "Validating Your Changes" on page 218.



2. Select:

**Overview**  
    > **Configure ...**  
        > **Apply Configuration**

### Exiting the Temporary Configuration without Saving

To exit the temporary configuration entirely without saving any of your changes, select:

**Overview**  
    > **Configure...**  
        > **Cancel Configuration**

The **Configure** menu is also available by right-clicking within the **Overview** display. If you refresh the screen, the temporary configuration will also be canceled.

### Displaying DMF Configuration File Parameters

The following menu bar selection displays the contents of the DMF configuration file:

**Configuration**  
    > **Parameters**

For example, Figure 6-12 shows the configuration parameters for a drive group. For information about any individual parameter, right-click on it and select the **What is** option.




Figure 6-12 DMF Configuration Parameters in DMF Manager

## Starting and Stopping DMF and the Mounting Service

To start or stop DMF and the mounting service, do the following:

1. Log in as the admin user.
2. Right-click on the DMF icon in the **Overview** panel.
3. Select the desired action.

## Discovering DMF Problems

DMF Manager denotes issues by adding a red or yellow icon next to the component that is experiencing problems. For example, Figure 6-13 shows that although DMF is still running, there is a potential problem. To investigate, hover the mouse over the shield icon to display pop-up help that details the warning.




Figure 6-13 DMF Manager Showing Problems in the DMF System

For more information, right-click the **Alerts** icon flag and select **Show Alerts...** or choose the following from the menu bar:

**Messages**  
    **> Alerts**


Either action will open the **Alerts** panel, which displays the unacknowledged alerts (by default, grouped by date and message) with the following sortable fields:

- **Time** is the date and time at which a particular alert was issued (by default, alerts are sorted by time from most recent to oldest)
- **Alert Message** is the notice, warning, or critical error reported during the operation of DMF
- **Priority** is an icon as shown in Figure 6-14 that represents the severity of the alert
- **Host** is the node that issues the alert
- **Count** is the number of times this particular alert has been issued within one calendar day

---

**Note:** By default, identical alerts are grouped and only the time that the last alert was issued is displayed. To view all alerts and their corresponding time stamps, deselect the **Group identical alerts within a day** box in the **Alerts Preferences** panel.

---



**Figure 6-14** Alerts Key

Figure 6-15 shows an example of unfiltered alerts.





Figure 6-15 Unfiltered Alerts

For more information about an alert, select it and choose **Help on this alert**, such as shown in Figure 6-16. To customize the display, see "Filtering Alerts" on page 225.



**Figure 6-16** DMF Manager Alerts Panel and Help Information

If you are logged in, you can acknowledge selected alerts or clear all alerts. See "Running Observer Mode or admin Mode" on page 195.

You can also use the following panel to view daily activity reports (those containing critical log errors show red warning symbols):

**Messages**  
**> Reports**


Also see "Viewing the DMF Queue" on page 263.

## Filtering Alerts

You can customize the **Alerts** display by applying one or more filters.

For example, to show critical errors and warnings about OpenVault sent on December 5, you could establish three filters:

1. Click in the filter bar, as shown in Figure 6-17.



**Figure 6-17** Define Filters for Alerts

2. **Rule 1:**


- For **Column**, select **Time**

---

**Note:** If you click in the filter bar below a column header, the column name will be selected automatically in the **Filter** dialog.

---

- For **Condition**, select **is**
  - For **Value**, select December 5
3. Click the green plus sign to add another rule, as shown in Figure 6-18.



**Figure 6-18** Adding Another Filter Rule

4. **Rule 2:**
  - For **Column**, select **Priority**
  - For **Condition**, select **is less than**
  - For **Value**, select **3**
5. Click the green plus sign to add another rule.



### 6. Rule 3:

- For **Column**, select **Alert Message**
- For **Condition** select **contains**
- For **Value**, enter `openvault`

7. Click **Filter** to apply the rules. The display would then reduce to that shown in Figure 6-19.



Figure 6-19 Filtered Alerts

## Seeing Relationships Among DMF Components

To see the relationships among DMF components, click on a component icon in the **Overview** panel and select its **Show Relationships** menu item. Figure 6-20 shows the relationships for the `ftp1` FTP MSP.

To remove the relationship lines, click **Hide Relationships**.




Figure 6-20 Relationships Among DMF Components

## Managing Volumes

To manage volumes, select the following:

**Storage**  
**> Volumes**

Figure 6-21 shows an example.

Panel tabs → Volumes x

Click to navigate → Library Servers

Click to select → C00P1R

Select to limit the report to those with this hold flag → hsite2

Hover the mouse pointer over the icon to see an explanation of the graphic → [Tooltip]

Select to specify the number of reports per page → 10 | 25 | 50 | 100

Click to log out → Log Out

DMF status → [Shield Icon]

| Volume ID                | Summary | Hold Flags     | Update Age     |
|--------------------------|---------|----------------|----------------|
| No filter applied        |         |                |                |
| <input type="checkbox"/> | C00N1R  | [Progress Bar] | -----2-- 2d    |
| <input type="checkbox"/> | C00N2F  | [Progress Bar] | -----u--2-- 2d |
| <input type="checkbox"/> | C00POD  | [Progress Bar] | -----2-- 2d    |
| <input type="checkbox"/> | C00P13  | [Progress Bar] | -----2-- 2d    |
| <input type="checkbox"/> | C00Q1S  | [Progress Bar] | -----2-- 2d    |
| <input type="checkbox"/> | C00NOB  | [Progress Bar] | -----2-- 2d    |
| <input type="checkbox"/> | C00P1R  | [Progress Bar] | -----2-- 2d    |
| <input type="checkbox"/> | C00Q2I  | [Progress Bar] | -----u--2-- 2d |
| <input type="checkbox"/> | C00S0G  | [Progress Bar] | -----2-- 2d    |
| <input type="checkbox"/> | C00S16  | [Progress Bar] | -----2-- 2d    |


| Description       | Percent | Value (MB) | Key                                 |
|-------------------|---------|------------|-------------------------------------|
| Volume Size       | 100%    | 21257      | <input type="checkbox"/>            |
| Data Written      | 46%     | 9808       | <input checked="" type="checkbox"/> |
| Active Data       | 11%     | 2411       | <input checked="" type="checkbox"/> |
| Reclaimable Space | 35%     | 7397       | <input checked="" type="checkbox"/> |

Figure 6-21 DMF Manager Volumes Panel

You can filter the volumes displayed, similar to the information in "Filtering Alerts" on page 225.

When logged in, you can also perform the following actions for selected volumes:

- **Change the Hold Flag (hflag)**, shown in Figure 6-22, sets the hold flag values on individual volumes. Click the **On** column to enable a flag or click the **Off** column to disable a flag. For more information about the hold flags, click the **Help** button or select the **What is** menu for the flags displayed in the **Volumes** panel.



**Figure 6-22** Changing Hold Flags in DMF Manager

- **Merge Data Off Volume** marks a volume as a candidate to be merged with another volume, thereby recovering space that was lost due to holes in the volume from deleted data (a *sparse volume*). These operations will be performed when appropriate. This is the preferred way to move data off of a volume.

---

**Note:** Merging is not appropriate for a volume configured as a fast-mount cache.

---

- **Empty Damaged Volume** forces data to immediately move to another volume.

---

**Note:** Use this as a last resort. You should first try **Merge Data Off Volume**.

---

- **Eject Tape** removes the selected physical tape cartridges from the tape library but keeps their tape IDs (*volume serial numbers*, or *VSNs*) in the VG. (In some cases, this command may cause a door to be unlocked, requiring a human operator to physically extract the cartridge from the library.) This only applies to physical tapes managed by OpenVault.
- **Verify Volume Integrity** runs a verification to make sure that the data on the volume is readable.

See "Running Observer Mode or `admin` Mode" on page 195.

You can also use the following menu bar selection to add volumes that are managed by OpenVault:

```
Volumes
  > Add Volumes ...
```

## Managing Libraries

To view the status of libraries, choose the following from the menu bar:

```
Storage
  > Libraries
```

If you are logged in to DMF Manager, you can enable or disable the selected libraries. See "Running Observer Mode or `admin` Mode" on page 195.

## Displaying DMF Manager Tasks

A given DMF Manager task may require issuing a set of DMF commands, and these commands may take some time to execute. The following panel displays the long-running DMF Manager tasks that have been issued but not yet acknowledged:

**Messages**  
    > **DMF Manager Tasks**

When logged in, you can choose to show the tasks logs or acknowledge, suspend/resume, or kill each selected DMF command, as appropriate. See "Running Observer Mode or admin Mode" on page 195.

## Monitoring DMF Performance Statistics

The **Statistics** menu provides current and historical views of DMF activity and resources. This section discusses the following:

- "Using the Statistics Panels" on page 234
- "Metrics Collection" on page 235
- "DMF Activity" on page 235
- "DMF Resources" on page 238
- "DMF I/O" on page 248

---

**Note:** To see all of the available statistics via DMF Manager, you must set the `EXPORT_METRICS` configuration parameter to `ON`. Do not change this parameter while DMF is running; to change the value, you must stop and restart DMF. See "base Object" on page 277.

---

## Using the Statistics Panels

The **DMF Resources** and **DMF Activity** panels of the **Statistics** menu are divided into the following areas:

- Report tree
- Graphs
- Key

To resize an area, drag the divider lines to the left or right.

Expandable folders in the tree (such as **Requests**) contain reports (such as **Requests Summary**) and subfolders (such as **Filesystem Requests**). Click on the + symbol to expand a folder or on the — symbol to contract it, or use the **Expand All** and **Collapse All** buttons. Click on a report name to display the associated graphs.

Each graph is scaled according to the maximum value in each graph. To scale all of the graphs with a common maximum value, check **Scale graphs equally** at the top of the tree.

White space within a graph means that nothing happened during that time period, or data was unavailable. This does not indicate an error condition.

DMF Manager distinguishes between the following:

- *Current metrics* are either drawn live from the server or are taken from the last few minutes of the metric archives
- *Historic metrics* are taken exclusively from the metric archives

DMF Manager is able to display historical information for the following time periods:

- Last hour
- Last day (the previous 24 hours)
- Last month (the previous 30 days)

---

**Note:** Some DMF configuration parameters use multipliers that are powers of 1000, such as KB, MB, and GB. However, the **DMF Activity**, **DMF Resources**, and **DMF I/O** panels use multipliers that are powers of 1024, such as KiB, MiB, and GiB. In particular, this means that 1 MiB/s is  $2^{20} = 1048576$  bytes per second.

---



## Metrics Collection

SGI Performance Co-Pilot™ continuously gathers performance metrics for the **DMF Activity** and **DMF Resources** panels. See "Monitor the Size of the PCP Metrics Archive" on page 130.

The DMF data movers (the DMF server and any parallel data-mover nodes) collect the metrics displayed in the **DMF I/O** panel. See "Monitor the Size of the PCP Metrics Archive" on page 130.

## DMF Activity

This section discusses the following:

- "Overview of DMF Activity Reports" on page 235
- "Key to DMF Activity Reports" on page 236
- "Example of DMF Activity Report" on page 237

### Overview of DMF Activity Reports

The reports in the **DMF Activity** panel show user-generated DMF activity:

- **Requests** reports show the number of requests being worked on
- **Throughput** reports show the rate of data throughput resulting from those requests

---

**Note:** Values shown are averaged over the previous few minutes, so they are not necessarily integers (as would be expected). This process also causes a slight delay in the display, which means that the values of **DMF Activity** reports do not necessarily match the current activity on the system as seen in the DMF log files.

---

The following types of requests are reflected in these reports:

- Requests from the user to the DMF daemon. These are presented as an aggregate across the DMF server, and on a per-filesystem basis, using the label of **Filesystem**.
- Requests from the DMF daemon to the subordinate daemons that manage the secondary storage (a *back-end request*).

Sometimes, there is a 1:1 correspondence between a daemon request and a back-end request (such as when a file is being recalled from secondary storage back to the

managed filesystem), but this is frequently not the case. For example, migrating a newly created file to secondary storage will result in one back-end request per copy, but deleting a migrated file results in a single daemon request but no back-end request at that time. Volume merges may cause a lot of activity within a VG but none at the daemon level.

In the **Summary** reports, the different types of requests are not distinguished from each other. However, if you zoom in (via one of the subfolders, such as **DCM MSP**), the resulting report shows the broad categories as well as by filesystem or by secondary storage group, as appropriate.

---

**Note:** Some DMF configuration parameters use multipliers that are powers of 1000, such as KB, MB, and GB. However, the **DMF Activity** and **DMF Resources** panels use multipliers that are powers of 1024, such as KiB, MiB, and GiB. In particular, this means that 1 MiB/s is  $2^{20} = 1048576$  bytes per second.

---

### Key to DMF Activity Reports

Each report under the **DMF Activity** tab shows an instantaneous pending-requests graph and history graphs showing the following color-coded amounts of pending requests:

---

**Note:** The exact definitions vary by report. For more a more precise description, click on an individual label.

---

- Summary reports:

| <b>Key</b>                   | <b>Description</b>                                                                |
|------------------------------|-----------------------------------------------------------------------------------|
| <b>Filesystem requests</b>   | Number of all daemon requests that are pending                                    |
| <b>VG &amp; MSP requests</b> | Number of VG and MSP requests that are pending                                    |
| <b>Last hour average</b>     | Marker that shows the average number of pending requests during the last hour     |
| <b>Last day average</b>      | Marker that shows the average number of pending requests during the last 24 hours |

- Aggregate and individual reports:

| <b>Key</b>                  | <b>Description</b>                                                                                                                       |
|-----------------------------|------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Administrative</b>       | Number of daemon requests that are pending or throughput for such requests                                                               |
| <b>Migrations</b>           | Number of migration-related requests that are pending or throughput for such requests                                                    |
| <b>Recalls &amp; copies</b> | Number of requests to recall/copy data or throughput for such requests                                                                   |
| <b>Merges</b>               | Number of merge requests that are pending or throughput for such requests (for VGs only)                                                 |
| <b>Other user activity</b>  | Number of other requests related to user actions (such as daemon remove requests or DCM cancel requests) or throughput for such requests |

#### Example of DMF Activity Report

Figure 6-23 is an example of a filesystem throughput report. It shows that the primary activity for the `/dmfusr` filesystem are migrations, with a smaller number of recalls and copies.




Figure 6-23 DMF Activity

## DMF Resources

The **DMF Resources** panel shows how DMF is using its filesystems and hardware, as described in the following sections:

- "Programs that Update the DMF Resources Reports" on page 239
- "Filesystem Folder" on page 239
- "Libraries Report" on page 242
- "Drive Group Folder" on page 242
- "Volume Group Folder" on page 244

- "DCM MSP Folder" on page 246

### Programs that Update the DMF Resources Reports

The reports in the **DMF Resources** panel are updated at the interval specified in the **DMF Resources Preferences** menu item by those DMF programs that scan the filesystem inodes:

```
dmaudit  
dmdadm  
dmdskfree  
dmfsfree  
dmhdelete  
dmscanfs  
dmselect
```

### Filesystem Folder

Each report under **Filesystem** shows an instantaneous occupancy graph and history graphs showing the following color-coded amounts of space in the managed filesystem:

| <b>Key</b>                       | <b>Description</b>                                                                                                                                                                                             |
|----------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Free</b>                      | Free space                                                                                                                                                                                                     |
| <b>Not migrated</b>              | Space used by files that are not migrated, such as regular files, files that will never be migrated, and files in the process of migration                                                                     |
| <b>Dual- &amp; partial-state</b> | Space used by dual-state files (files where the data resides both on online disk and on secondary storage) and partial-state files (files where the data resides both on online disk and on secondary storage) |

For more information about file states, see "File States" on page 14.

The reports also display the following values:

|                       |                                                                                                                                                                              |
|-----------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Offline</b>        | The amount of space used in secondary storage for files in the managed filesystem                                                                                            |
| <b>Oversubscribed</b> | The amount of space that is <i>oversubscribed</i> , which is a ratio of offline space to the total amount of space for a given DMF filesystem (including space that is free, |

space that is occupied by regular files, space that is occupied by files that are migrated, including dual-state files), calculated as follows:

$$\frac{\text{offline\_space}}{(\text{free\_space} + \text{migrated\_space} + \text{not\_migrated\_space})}$$

---

**Note:** This is a measure of data that *could be* on disk but is not at this moment in time, rather than a measure of the total amount of secondary storage being used. The fact that a migrated file may have more than one copy on the secondary storage is not considered.

---

Typically, the oversubscription ratio is the range of 10:1 to 1000:1, although it can vary considerably from site to site.

The data presented in the graph is gathered periodically by DMF. The time at which this information was gathered is displayed at the top of the page. The default configuration is to update this information once daily (at 12:10 am).

Figure 6-24 is an example of a filesystem resource graph. It shows that the majority of filesystem space for the `/dmfusr` filesystem is used by dual-state or partial-state files. (White space within the graph means that data was unavailable during that time period.)




Figure 6-24 Filesystem Resource Graph

### Libraries Report

---

**Note:** The **Libraries** report is available only if you are using OpenVault. This folder is unavailable if you are using TME.

---

The **Libraries** report displays the number of slots that are used by DMF, used by other applications, and empty, according to information obtained from OpenVault.

### Drive Group Folder

The reports in the **Drive Group** folder provide information for each drive according to the fields you select in the right-hand column:

- **Base**, which provide basic information on drive activity
- **Current**, which provide instantaneous values of drive activity and throughput
- **Total**, which provide aggregate values of drive activity and throughput
- **Averages**, which provide averaged values of drive activity and throughput

---

**Note:** This information is available only for DMF's volumes. Any other use, such as filesystem backups or direct use by users, is not shown.

---

To display a field in the table, click on its check box in the right-hand column. To display all fields for a given category, click on the check box for the category name, such as **Base**. For more information about a field, right-click on its column header in the table and select **What is**.

To sort according to a given column, select the up or down arrow at the upper-right corner of the column header. If you sort by multiple columns, their order is displayed in the column header. To remove sorting for a column, click on the **X** icon.

Figure 6-25 shows that drive `lt01` is in the process of mounting.






Figure 6-25 Drive Group Resource Information

**Volume Group Folder**

Each report under **Volume Group** shows the slot usage for this VG (for all libraries), the allocation group (AG) report (if applicable), and the volume states in an instantaneous occupancy graph and history graphs showing the following color-coded amounts of space in the managed filesystem:

The key is as follows:

| <b>Key</b>                 | <b>Metrics</b>                                                                                                             |
|----------------------------|----------------------------------------------------------------------------------------------------------------------------|
| <b>Empty</b>               | Number of empty volumes assigned to DMF                                                                                    |
| <b>Partial</b>             | Number of partially-filled volumes assigned to DMF                                                                         |
| <b>Merging</b>             | Number of volumes being merged                                                                                             |
| <b>Locked</b>              | Number of volumes waiting for the <code>hlock</code> hold flag to clear                                                    |
| <b>Waiting to be freed</b> | Number of volumes waiting for the <code>hfree</code> hold flag to clear                                                    |
| <b>Read-only</b>           | Number of volumes available for reads only (excluding volumes with the <code>hfull</code> hold flag set)                   |
| <b>Unavailable</b>         | Number of volumes indefinitely unavailable (that is, those with the <code>hoa</code> operator/administrator hold flag set) |

For more information about hold flags, see "dmvoladm Field Keywords" on page 557.

Figure 6-26 is an example of an instantaneous VG resource graph. (White space within the graph means that data was unavailable during that time period.)




Figure 6-26 Volume Group Resource Graph

### DCM MSP Folder

The reports in the **DCM MSP** folder show the DCM MSP occupancy. The key is as follows:

| <b>Key</b>               | <b>Description</b>                                                                                                                                                                                                                         |
|--------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Free</b>              | Amount of space that is free in the DCM MSP <i>STORE_DIRECTORY</i> filesystem                                                                                                                                                              |
| <b>Dual-resident</b>     | Amount of space used in the DCM MSP <i>STORE_DIRECTORY</i> by dual-resident files                                                                                                                                                          |
| <b>Not dual-resident</b> | Amount of space used in the DCM MSP <i>STORE_DIRECTORY</i> by files that are not dual-resident, such as incompletely moved files and files that have been completely moved to the DCM MSP <i>STORE_DIRECTORY</i> but are not in a lower VG |

---

**Note:** The DCM MSP reports have similar issues to filesystem reports with regard to the frequency of updates, as described in "Filesystem Folder" on page 239.

---

Figure 6-27 is an example of a DCM MSP resource graph. It shows the majority of the cache disk space is not dual-resident.




Figure 6-27 DCM MSP Resource Graph

## DMF I/O

The **DMF I/O** panel lets you can create custom charts. One chart can represent multiple data items. You can group similar charts under a folder to view them on a single page. To save a chart, select the following:

- DMF I/O**
- > Save current configuration of charts**

To return to the previous configuration of charts, select the following:

- DMF I/O**
- > Return to previous configuration of charts**

Any DMF user can display, save and overwrite the chart configuration.

---

**Note:** To see I/O statistics via DMF Manager from all data movers, ensure that the `PERFTRACE_METRICS` configuration parameter is set to ON ( the default is OFF). See "base Object" on page 277.

---

The **DMF I/O** panel lets you create custom charts that show how DMF is using data movers and various kinds of specific media:

- Volumes
- Drives
- Filesystems (includes archive filesystems, managed filesystems, and DMF administrative directories configured by the `CACHE_DIR`, `TMP_DIR`, and `MOVE_FS` parameters)
- Servers (potential DMF servers)
- Movers (parallel data-mover nodes)

To create a chart, do the following:

1. Click **Custom Charts** in the left-hand side of the **DMF I/O** panel. This opens the **Add Customized Chart** dialog.
2. Specify the time frame of the chart by selecting one of the following:
  - **Select time range:**

- Enter the starting and ending dates (in *month/date/year* format, such as 2/27/2013) or use the pull-down calendar
  - Enter the time using 24-hour format, (such as 15:59 for 3:59 PM) or use the pull-down list
  - **Select last:** specify the number and unit of measure (minutes, hours, or days). For example, to specify the last three hours, enter 3 and select **hours**.
3. Specify how often the chart should be refreshed (in seconds). This value cannot be less than 60.
  4. Name the folder name that will hold the chart and the individual chart. Permitted names consist of alphanumeric characters, hyphens, underscores (no whitespace is allowed).
  5. Specify the data to be included in the chart:

---

**Note:** The more information you add to a single chart, the longer it will take to draw the entire chart. To reduce clutter and increase readability and responsiveness, specify no more than five data items.


---

You can specify the following:

- **Target:** specify the type of data to be collected. You can select from the pull-down list or enter a specific name from the list.
- **Hosts:** specify the data-mover nodes and DMF server nodes from which to collect data. You can select from the pull-down list or enter a specific name from the list.
- **Read/Write/Aggregate:** For any particular target, select what type of I/O that you want to track, which can be all of the following:
  - Read rate
  - Write rate
  - Aggregate rate (sum of both read and write I/O)
- To add line to the graph, click **Add data item**. To remove lines from the graph, click their check boxes and select **Remove selected data items**.

**Note:** The averaging algorithm attempts to represent most idle time periods. The idle times are excluded from the averages as much as possible.


Figure 6-28 shows an example that creates a chart named `chart1` that will display write data collected for the last 60 minutes for filesystem `/dmfusrl` on the host named `vajra`.



**Figure 6-28** DMF I/O Custom Chart Creation

By default, the chart appears under its group name in the left-hand side of the **DMF I/O** panel, as shown in Figure 6-29.





**Figure 6-29** DMF I/O

To further manipulate the chart, click the **Modify**, **Refresh**, and **Remove** buttons above the chart display.

When you exit this DMF Manager session, the chart configurations you created will be removed. To save your new chart configurations, click **Save current configuration of charts** in the **DMF I/O** panel menu. To go back to the previous set of chart configurations, click **Revert to previous configuration of charts** in the panel menu (only one set is allowed).

To automatically remove old performance records, configure the `PERF_RETENTION` parameter and use the `run_remove_perf.sh` task. See "taskgroup Object Parameters" on page 312.

---

**Note:** An averaging algorithm attempts to represent most idle time periods. The idle times are excluded from the averages as much as possible.

---

## Displaying Node Status

If you are running the Parallel Data-Mover Option, you can display the status of a node from the DMF and (when available) CXFS point of view by hovering the mouse pointer over the node's icon, as shown in Figure 6-30.




Figure 6-30 Node State

The states are as follows:

- DMF states:

- Active
- Inactive
- Disabled

- CXFS states such as:

- Stable
- Establishing membership
- Inactive
- Disabled

Right-click the icon and select **Details...** to display more information, including CXFS mount information for the DMF administrative directories and managed filesystems. Items in green font indicate that all is well; items in red font indicate a problem. Click **Help** for more information about the fields. Figure 6-31 shows an example.

---

**Note:** In a DMF HA environment, only the active DMF server is displayed.

---

Show Details

**DMF Node Information**

| Node Name     | Status | Enabled | Active Since         | Dropouts |
|---------------|--------|---------|----------------------|----------|
| burn (Server) | Active | Yes     | 2012-Feb-02,06:25:00 | 0        |
| thud (Mover)  | Active | Yes     | 2012-Feb-02,06:25:19 | 0        |

**CXFS Node Information**

| Node Name     | Status | Cell ID | Age |
|---------------|--------|---------|-----|
| burn (Server) | Stable | 0       | 1   |
| thud (Client) | Stable | 1       | 1   |

**CXFS Mount Information**

| Filesystem  | Mount Point   | Server | Status                 |
|-------------|---------------|--------|------------------------|
| dcm         | /dcm          | burn   | Mounted [2 of 2 nodes] |
| dcmmsp      | /dcmmsp       | burn   | Mounted [2 of 2 nodes] |
| dmfcache    | /dmf/cache    | burn   | Mounted [2 of 2 nodes] |
| dmfhomedir  | /dmf/home     | burn   | Mounted [2 of 2 nodes] |
| dmfmovefs   | /dmf/move     | burn   | Mounted [2 of 2 nodes] |
| dmfspooldir | /dmf/spool    | burn   | Mounted [2 of 2 nodes] |
| dmftmp      | /dmf/tmp      | burn   | Mounted [2 of 2 nodes] |
| dmi_fs      | /dmi_fs       | burn   | Mounted [2 of 2 nodes] |
| dmi_fs2     | /dmi_fs2      | burn   | Mounted [2 of 2 nodes] |
| journals    | /dmf/journals | burn   | Mounted [2 of 2 nodes] |

Help

Figure 6-31 Node Details

## Restoring Filesystems in DMF Manager

To restore XFS and CXFS filesystems, select the following:

**Backups**  
    > **Recovery**

This panel displays the available dumps (with panes for dumps produced via the integrated backup method and dumps produced via any backup method) and the status of restore processes. You must log in to complete the following administrative actions:

- "Restore a Filesystem Component (Integrated Backups)" on page 255
- "Restore a Filesystem Component (Nonintegrated Backups)" on page 260
- "Stop a Restoration Process" on page 261
- "View Restoration Logs" on page 262

### Restore a Filesystem Component (Integrated Backups)

To restore a filesystem or any subcomponent from the filesystem recovery pane, do the following:

1. Click **Available Dumps (Integrated Method)** and select the desired dump.


---

**Note:** When using integrated backups, the dumps will also be available from the **Available Dumps (All Methods)** pane, but it has fewer available actions.

---

2. Right-click and choose the desired action:
  - Show the dump log
  - Restore the filesystem at any level of granularity
  - Restore the DMF databases
  - Restore the `xfsdump` inventory
  - Restore configuration files

Figure 6-32 shows an example.



**Figure 6-32 Restoring a File from Available Dumps (Integrated Method)**

For example, the **Restore filesystem** action displays the name of the source filesystems that were included in the chosen dump, the time of the dump, the dump level, the dump method, and the status of DMF management. You can choose or supply the following:

**Source filesystem**

Specifies the filesystem from which to obtain data

**Source directory or file relative to the filesystem**

Specifies a subdirectory or the path to a file that you want to restore from the selected dump. If you want to restore the entire filesystem, leave this field empty.

---

**Note:** If the file or subdirectory is not available in this dump, an error will occur and be logged in the restore log.

---

**Destination filesystem**

Specifies the filesystem into which the restored component will be placed. By default, the name of the source filesystems is used as the destination filesystem.

**Destination directory relative to the destination filesystem**

Specifies the location where the component will be restored within the destination filesystem. If the path provided is not found, it is dynamically created. By default, the target will be relative to the top level of the destination filesystem.

**Overwrite options**

You can optionally choose to overwrite existing files or overwrite only if the source files being restored are newer than the existing files at the destination. By default, no existing files will be overwritten.

**Pane behavior**

You can choose to have the pane stay open until the process completes or close the pane immediately after launching the process.

The following sections show examples:

- "Example: Restoring to the Original Location" on page 258
- "Example: Restoring to a New Location" on page 260

**Example: Restoring to the Original Location**

For example, suppose you want to restore the `Day4` directory to its original location within the `/dmfusr1` filesystem. You would do the following:

1. Select the appropriate dump.
2. Enter `Day4` in the source field.
3. Click **Restore**

Figure 6-33 shows an example.






Figure 6-33 Restoring a Filesystem Component using DMF Manager (Integrated Backups)

**Example: Restoring to a New Location**

For example, suppose you want to restore the `Day4` directory to a new location, beneath a new directory named `/dmfusr1/newdir` that does not yet exist:

```
# pwd
/dmfusr1
# ls
Day1 Day2 Day3 Day4 Day5
```

You would do the following:

1. Select the appropriate dump.
2. Enter `Day4` in the source field.
3. Enter `newdir` in the destination directory.
4. Click **Restore**.

You would then see the following:

```
# pwd
/dmfusr1
# ls
Day1 Day2 Day3 Day4 Day5 newdir
# ls newdir
Day4
```

**Restore a Filesystem Component (Nonintegrated Backups)**

When using nonintegrated tape or disk backups, you can restore the filesystem at any level of granularity but you cannot perform other actions. Click **Available Dumps (All Methods)**. The filesystem component restoration procedure is similar to the above.

For example, the **Restore filesystem** action displays the name of the source filesystems that were included in the chosen dump, the time of the dump, the dump level, the dump method, and the status of DMF management. For a dump to tape, you must also supply the drive group.

The screenshot displays the DMF Manager web interface. The browser address bar shows `https://augusta.americas.sgi.com:11109`. The navigation menu includes Configuration, Storage, Messages, Statistics, Backups, QView, and Help. The main content area is divided into two panels:

**Available Dumps (All Methods)**

| Filesystem    | Level | Date                |
|---------------|-------|---------------------|
| /dmf_journals | 1     | 2015-06-22T00:00:00 |
| /dmfusr       | 0     | 2015-06-22T00:00:00 |
| /dmf_journals | 0     | 2015-06-21T00:00:00 |
| /dmfusr       | 0     | 2015-06-21T00:00:00 |
| /dmf_journals | 0     | 2015-06-20T00:00:00 |
| /dmfusr       | 0     | 2015-06-20T00:00:00 |
| /dmf_journals | 0     | 2015-06-19T00:00:00 |
| /dmfusr       | 0     | 2015-06-19T00:00:00 |
| /dmfusr       | 0     | 2015-06-10T04:35:13 |
| /dmf_journals | 0     | 2015-06-10T04:35:12 |
| /dmfusr       | 0     | 2015-06-10T04:28:12 |
| /dmf_journals | 0     | 2015-06-10T04:28:12 |
| /dmf_journals | 0     | 2015-06-10T02:34:57 |
| /dmfusr       | 0     | 2015-06-10T02:34:57 |
| /dmf_journals | 1     | 2015-06-10T00:00:01 |
| /dmfusr       | 0     | 2015-06-10T00:00:01 |
| /dmfusr       | 0     | 2015-06-09T11:05:40 |
| /dmf_journals | 0     | 2015-06-09T11:05:39 |
| /dmfusr       | 0     | 2015-06-09T11:04:08 |
| /dmf_journals | 0     | 2015-06-09T11:04:07 |

**Status of restore processes**

| Destination    | Status | Time Started        | Time Ended          |
|----------------|--------|---------------------|---------------------|
| /dmf_journals/ | ✓      | 2015-06-19T09:42:32 | 2015-06-19T09:42:35 |
| DMF database   | ✓      | 2015-06-19T09:38:01 | 2015-06-19T09:38:50 |
| DMF database   | ✓      | 2015-06-19T09:05:19 | 2015-06-19T09:06:11 |
| DMF database   | ✓      | 2015-06-19T08:14:44 | 2015-06-19T08:15:32 |
| DMF database   | ✓      | 2015-06-19T08:08:16 | 2015-06-19T08:09:04 |
| DMF database   | ✓      | 2015-06-19T07:28:35 | 2015-06-19T07:28:44 |
| DMF database   | ✓      | 2015-06-19T07:20:03 | 2015-06-19T07:20:56 |
| DMF database   | ✓      | 2015-06-19T07:18:53 | 2015-06-19T07:19:42 |
| DMF database   | ✓      | 2015-06-19T07:13:49 | 2015-06-19T07:14:16 |
| DMF database   | ✓      | 2015-06-19T07:06:16 | 2015-06-19T07:06:44 |
| DMF database   | ✓      | 2015-06-19T07:00:57 | 2015-06-19T07:01:26 |
| DMF database   | ✓      | 2015-06-19T07:00:13 | 2015-06-19T07:00:42 |
| DMF database   | ✓      | 2015-06-19T06:35:10 | 2015-06-19T06:35:26 |
| DMF database   | ✓      | 2015-06-19T06:31:30 | 2015-06-19T06:31:51 |
| DMF database   | ✓      | 2015-06-19T06:30:40 | 2015-06-19T06:30:56 |
| DMF database   | ✓      | 2015-06-19T06:27:38 | 2015-06-19T06:27:55 |

Figure 6-34 Restoring a Filesystem Component using DMF Manager (Nonintegrated Backups)

## Stop a Restoration Process

To stop currently running processes, do the following in the **Status of restore processes** panel:

1. Select the check box for each the processes that you want to stop.

2. Right-click and choose **Kill**.

## View Restoration Logs

To view a log for a completed process, do the following:

1. Select the check box for process.
2. Right-click and choose **Show log**.

## Disaster Recovery in DMF Manager for Basic DMF

If you are using basic DMF in a non-HA environment, the following menu selection lets you perform disaster recovery tasks when you are logged in to DMF Manager

```
Backups  
  > Recovery  
    > Disaster Recovery ...
```

See "Disaster Recovery for Basic DMF without HA" on page 651.

Also see:

- "Disaster Recovery for Parallel DMF" on page 655
- "Disaster Recovery for DMF with HA" on page 657

## Viewing the DMF Queue

The **QView** tab displays information about the internal DMF processing queues, equivalent to the `dmqview(8)` command. You must log in DMF Manager to use **QView**.

The **QView** page lets you directly cancel and reprioritize requests; the `dmcancel(8)` and `dmrepri(8)` commands provide the same functionality for the command line.

For details, see Chapter 17, "DMF Queue Viewing" on page 605.

## LTFS in DMF Manager

This section discusses the following for the SGI Linear Tape File System (LTFS):

- "Showing LTFS Information in DMF Manager" on page 263
- "Showing LTFS Progress in DMF Manager" on page 264
- "Configuring LTFS using DMF Manager" on page 265
- "Mounting an Unassigned Tape for LTFS Use in DMF Manager" on page 267
- "Unmounting an LTFS Tape in DMF Manager" on page 269

For more information and additional functions, see Chapter 18, "SGI LTFS" on page 631 and the `sgi-ltfs(8)` man page.

## Showing LTFS Information in DMF Manager

You can display information about LTFS with the following selection:

```
Storage
  > Volumes
    > Show LTFS Information
```

You can also view this information by clicking on **LTFS Assigned Tapes** or **Unassigned Tapes** in the navigation tree. Figure 6-35 shows an example of the information page.




Figure 6-35 LTFS Information

### Showing LTFS Progress in DMF Manager

When LTFS commands are launched from DMF Manager, they are launched as asynchronous processes. You can display their progress in the DMF Manager Tasks:

**Messages**  
 > **DMF Manager Tasks**

Figure 6-36 shows an example.

| ID  | Time Started        | Time Completed      | Command                                | Status                                  |
|-----|---------------------|---------------------|----------------------------------------|-----------------------------------------|
| 101 | 2014-04-16T12:25:26 | T                   | /usr/bin/sgi-ltfs unmount DMF604       | Running... Wait for return of cartridge |
| 100 | 2014-04-16T12:13:37 | 2014-04-16T12:14:29 | /usr/bin/sgi-ltfs import, mount DMF604 | Completed successfully                  |
| 99  | 2014-04-16T11:27:23 | 2014-04-16T11:28:18 | /usr/bin/sgi-ltfs unmount DMF604       | Completed successfully                  |
| 98  | 2014-04-16T11:25:11 | 2014-04-16T11:26:07 | /usr/bin/sgi-ltfs import, mount DMF604 | Completed successfully                  |

**Figure 6-36** LTFS Messages

All progress and errors will be detailed in the log associated with the running command. To access the log, select a message, click, and select **Show logs**. For more information, see "Displaying DMF Manager Tasks" on page 233.

## Configuring LTFS using DMF Manager


To configure LTFS, log in and use the following menu selection:

```
Storage
> Volumes
> Configure LTFS ...
```

Then enter the values you desire for the parameters shown. To get more information about a parameter, right-click on it and select the **What is this?** option.

**Note:** Mounting requires that LTFS has access to a drive in a valid OpenVault drive group. Valid drive groups can be reserved exclusively for LTFS use (specified by the `LTFS_DRIVE_GROUP` parameter) or can belong to another application, such as DMF (specified the `BORROW_FROM_DG` parameter), that will permit the drives to be borrowed temporarily. See "sgi-ltfs.conf Parameters" on page 634.

Figure 6-37 shows an example of configuring three DMF drive groups from which LTFS may borrow drives; LTFS may borrow a maximum of 1 drive from `dg1` or `dg1` (the default for a specified drive) and a maximum of 2 drives from `dg3`, with a total maximum number of 3 LTFS drives from any source.



**Figure 6-37** Configuring LTFS in DMF Manager



---

## Mounting an Unassigned Tape for LTFS Use in DMF Manager

---

**Note:** Mounting requires that LTFS has access to a drive in a valid OpenVault drive group. Valid drive groups can be reserved exclusively for LTFS use (specified by the `LTFS_DRIVE_GROUP` parameter) or can belong to another application, such as DMF (specified the `BORROW_FROM_DG` parameter), that will permit the drives to be borrowed temporarily. See "Configuring LTFS using DMF Manager" on page 265 and "`sgi-ltfs.conf` Parameters" on page 634.

---

To mount an unassigned tape for LTFS use, log in and do the following:

1. View the unassigned tapes by using the following menu selection:

**Storage**  
    > **Volumes**

2. Click on the unassigned tape name in the left-hand tree.
3. Select the drive. By default, a valid drive will be selected for you if LTFS has been configured correctly, as noted above.
4. Select the cartridge type.
5. Specify the mount point. By default, the mount point is the same as the volume serial number (VSN).
6. Select the notification method. By default, no notification will be sent.
7. You can optionally choose to format the tape:



**Warning:** Formatting the tape destroys any data on the tape.

---

- If the tape has already been formatted for LTFS, you can simply mount it (which by default is selected)
- If the tape has never been formatted, you must select **Format** to mount the tape and format it for LTFS
- If the tape has already been formatted for LTFS but you want to delete all of its data and reuse the tape, select **Force** to mount the tape and format it for LTFS
- If you want to simply assign the tape to LTFS but not mount it or format it at this time, select **Import Only**

8. Click **Apply**. The tape will be imported and mounted or formatted, as specified above. The view will switch to the information page. To verify the completion, see "Showing LTFS Progress in DMF Manager" on page 264.

For example, Figure 6-38 shows an example of mounting an Ultrium5-1500 tape in any available drive and having email notification sent to the assigned address.




Figure 6-38 Mounting an LTFS Tape

## Unmounting an LTFS Tape in DMF Manager

To unmount an LTFS tape, log in and do the following:

1. View the assigned LTFS tapes by using the following menu selection:

**Storage**  
    > **Volumes**

2. Click on the mounted tape name in the left-hand tree.
3. (Optional) To eject the tape, select the **Eject** check box. After ejection, the tape can be physically removed from the library.
4. Click **Apply and Unmount**. To verify the completion, see "Showing LTFS Progress in DMF Manager" on page 264.

Figure 6-39 shows an example.

## 6: DMF Manager




Figure 6-39 Unmounting an LTO6 Tape

## DMF Configuration File

This chapter discusses the following:

- "Configuration File Overview" on page 272
- "base Object" on page 277
- "dmdaemon Object" on page 289
- "node Object" on page 294
- "services Object" on page 299
- "taskgroup Object" on page 304
- "dumpgroup Object" on page 342
- "device Object" on page 347
- "filesystem Object" on page 350
- "policy Object" on page 364
- "fastmountcache Object" on page 390
- "Objects Related to an LS" on page 392
  - "libraryserver Object" on page 392
  - "drivegroup Object" on page 395
  - "volumegroup Object" on page 410
  - "migrategroup Object" on page 426
  - "resourcescheduler Object" on page 432
  - "resourcewatcher Object" on page 433
  - "allocationgroup Object" on page 434
  - "Examples of Configuring an LS" on page 436
  - "LS Tasks" on page 441
  - "LS Database Records" on page 444

- "msp Objects" on page 446
- "Summary of the Configuration-File Parameters" on page 472

## Configuration File Overview

This section discusses the following:

- " Object Definitions" on page 272
- "Stanza Format" on page 274
- "Units of Measure" on page 275
- "Device Block-Size Defaults and Bandwidth" on page 276

## Object Definitions

The DMF configuration file (`/etc/dmf/dmf.conf`) defines a set of configuration objects required by DMF. Each object is defined by a sequence of parameters and definitions; this sequence is called a *stanza*. There is one stanza for each object.

The objects defined are as follows:

- The `base` object defines pathname and file-size parameters necessary for DMF operation. See "base Object" on page 277.
- The `dmdaemon` object defines parameters necessary for `dmdaemon(8)` operation. See "dmdaemon Object" on page 289.
- The `node` objects defines a host functioning as a data mover when using the Parallel Data-Mover Option (*Parallel DMF*). There is a `node` object for every system in the DMF configuration, excluding DMF clients. See "node Object" on page 294.
- The `services` object defines parameters for `dmnode_service` and other DMF services. For Parallel DMF configurations, multiple `services` objects may be defined. For basic DMF configurations, only one `services` object may be defined. (The `services` parameters all have defaults, so a `services` object is only required to change those defaults.) See "services Object" on page 299.
- The `taskgroup` objects define parameters necessary for automatic completion of specific maintenance tasks. See "taskgroup Object" on page 304.

- The `dumpgroup` object defines dump parameters that apply to a specific subset of filesystems.
- The `device` objects define parameters necessary for automatic use of tape devices. Normally, the backup scripts would refer to a DMF drive group (DG) to define parameters necessary for accessing tape drives, but if they are to use drives that are not in use by DMF, you can use a `device` object to define these parameters. See "device Object" on page 347.
- The `filesystem` object defines parameters related to DMF's use of that filesystem. See "filesystem Object" on page 350.
- The `policy` objects specify parameters to determine media-specific process (MSP) or volume group (VG) selection, automated space-management policies, and/or file weight calculations in automated space management. See "policy Object" on page 364.
- The `fastmountcache` object defines the migrate groups (MGs) and independent VGs (that is, those VGs that are not in an MG) that are members of the fast-mount cache. See "fastmountcache Object" on page 390.
- The following objects are related to a library server (LS):
  - The `libraryserver` object defines parameters relating to a library for an LS. See "libraryserver Object Parameters" on page 393.
  - The `drivegroup` object defines parameters relating to a pool of devices in a specific LS. See "drivegroup Object Parameters" on page 397.
  - The `volumegroup` object defines parameters relating to a pool of volumes mountable on the drives of a specific DG that are capable of holding, at most, one copy of user files. See "volumegroup Object" on page 410.
  - The `migrategroup` object defines parameters that combine a set of MSPs and VGs into an MG so that they can be used as a single destination for a migrate request. See "migrategroup Object" on page 426.
  - The `resourcescheduler` object defines parameters relating to the scheduling of devices in a DG when requests from VGs exceed the number of devices available. See "resourcescheduler Object Parameters" on page 432.
  - The `resourcewatcher` object defines parameters relating to the production of files informing the administrator about the status of the LS and its components. See "resourcewatcher Object Parameters" on page 434.

- The `allocationgroup` object only applies if an `ALLOCATION_GROUP` parameter is specified in the `volume` object. You should specify the `allocationgroup` stanza if you want to change the default value of its `VOL_MSG_TIME` parameter. See "allocationgroup Object" on page 434.
- The `msp` object defines parameters necessary for an MSP's operation. See:
  - "msp Object for a Cloud MSP" on page 448
  - "msp Object for an FTP MSP" on page 455
  - "msp Object for a DCM MSP" on page 459
  - "msp Object for a Disk MSP" on page 466

See also "Use Sample DMF Configuration Files" on page 101.

## Stanza Format

A stanza has the following general format:

```
define object_name
    TYPE          object_type
    parameter    value
    ...
enddef
```

where:

- *object\_name* varies by stanza. Most names are chosen by the system administrator and may contain up to 8 uppercase or lowercase alphanumeric characters or underscores; they cannot begin with an underscore or contain any white space. Some require a specific name (such as `base`) and some may have longer names. All object names must be unique. See the individual object subsections in this chapter for details.
- *object\_type* identifies the type. Each type has a unique type identifier, detailed in the following subsections.
- *parameter* is an argument to the object. Each object has a list of potential parameters, defined later in this chapter.
- *values* is the value of the *parameter*. Where a *value* may be a list, separate the list items by white space or tabs unless otherwise noted. If the default value of a



given parameter is appropriate for your site, you do not need to specify the parameter in the DMF configuration file.

The configuration file is case-sensitive with the exception of the following parameter values, which can appear in uppercase, lowercase, or mixed case:

|     |       |
|-----|-------|
| ON  | TRUE  |
| OFF | FALSE |
| YES | 1     |
| NO  | 0     |

For simplicity, this chapter only refers to the values ON and OFF.

Lines within the configuration file can be indented for readability and the fields can be separated by spaces and/or tabs. Blank lines and all text between a hash character (#) and the end of that line are ignored. Except for comments, any line ending in a back-slash (\) continues onto the next line.

For a summary of the parameters discussed in this chapter, see Table 7-4 on page 472. For the most current set of parameters, see the `dmf.conf(5)` man page.

You can add site-specific parameters to any existing stanza or you can create a new stanza. You should choose parameter and stanza names that will not cause conflict with future SGI DMF parameters and stanzas. See "Start Site-Specific Configuration Parameters and Stanzas with "LOCAL\_" on page 125.

---

**Note:** Before placing a new configuration into production, it is important to verify it by running `dmcheck`. The `dmcheck` command will point out parameters and stanzas that it does not recognize.

---

## Units of Measure

Several parameters allow you to specify the unit of measure, which can be any of the following (all of which are powers of 1000, not 1024):

k or K for thousand ( $10^3$ )  
m or M for million ( $10^6$ )  
g or G for billion ( $10^9$ )  
t or T for trillion ( $10^{12}$ )  
p or P for quadrillion ( $10^{15}$ )

## Device Block-Size Defaults and Bandwidth

DMF uses the following values as the default `BLOCK_SIZE` value and as the bandwidth consumed in relation to the `HBA_BANDWIDTH` and `NODE_BANDWIDTH` values.

| Device          | Default<br>Block Size | Bandwidth |
|-----------------|-----------------------|-----------|
| AMPEX DIS/DST   | 1199840               | 160000000 |
| COPAN MAID      | 1048576               | 160000000 |
| DLT2000         | 131072                | 1250000   |
| DLT4000         | 131072                | 1500000   |
| DLT7000         | 131072                | 5000000   |
| DLT8000         | 131072                | 6000000   |
| HP ULTRIUM 2    | 262144                | 15000000  |
| HP ULTRIUM 3    | 524288                | 80000000  |
| HP ULTRIUM 4    | 524288                | 120000000 |
| HP ULTRIUM 5    | 524288                | 140000000 |
| HP ULTRIUM 6    | 524288                | 160000000 |
| IBM 03590B1A    | 16384                 | 90000000  |
| IBM 03590E1A    | 32768                 | 13500000  |
| IBM 03590H1A    | 16384                 | 13500000  |
| IBM 03592E05    | 131072                | 100000000 |
| IBM 03592E06    | 262144                | 160000000 |
| IBM 03592E07    | 524288                | 250000000 |
| IBM ULTRIUM-TD1 | 131072                | 15000000  |
| IBM ULT3580-TD1 | 131072                | 15000000  |
| IBM ULTRIUM-TD2 | 262144                | 30000000  |
| IBM ULT3580-TD2 | 262144                | 30000000  |
| IBM ULTRIUM-TD3 | 262144                | 80000000  |
| IBM ULT3580-TD3 | 262144                | 80000000  |
| IBM ULTRIUM-TD4 | 524288                | 120000000 |
| IBM ULT3580-TD4 | 524288                | 120000000 |
| IBM ULTRIUM-TD5 | 524288                | 140000000 |
| IBM ULTRIUM-HH5 | 524288                | 140000000 |
| IBM ULT3580-TD5 | 524288                | 140000000 |
| IBM ULT3580-HH5 | 524288                | 140000000 |
| IBM ULTRIUM-TD6 | 524288                | 160000000 |
| IBM ULTRIUM-HH6 | 524288                | 160000000 |

|                   |         |           |
|-------------------|---------|-----------|
| IBM ULT3580-TD6   | 524288  | 160000000 |
| IBM ULT3580-HH6   | 524288  | 160000000 |
| JBFS              | 1048576 | 160000000 |
| QUANTUM SuperDLT1 | 131072  | 11000000  |
| QUANTUM SDLT320   | 131072  | 16000000  |
| QUANTUM SDLT600   | 131072  | 36000000  |
| SEAGATE ULTRIUM   | 262144  | 16000000  |
| SONY SDX-700C     | 131072  | 12000000  |
| SONY SDZ-100      | 131072  | 30000000  |
| SONY SDZ-130      | 262144  | 30000000  |
| SONY SDZ-200      | 524288  | 45000000  |
| SONY SDZ-230      | 524288  | 45000000  |
| STK 9840          | 126976  | 10000000  |
| STK T9840B        | 126976  | 19000000  |
| STK T9840C        | 262144  | 30000000  |
| STK T9840D        | 262144  | 30000000  |
| STK T9940A        | 262144  | 10000000  |
| STK T9940B        | 262144  | 30000000  |
| STK T10000A       | 524288  | 120000000 |
| STK T10000B       | 524288  | 120000000 |
| STK T10000C       | 524288  | 240000000 |
| STK T10000D       | 524288  | 300000000 |
| Other devices     | 65536   | 160000000 |

## base Object

This section discusses the following:

- "base Object Name" on page 277
- "base Object Summary" on page 278
- "base Object Parameters" on page 278
- "base Object Examples" on page 286

## base Object Name

The name of the base object must be base.

## base Object Summary

Following is a summary of the potential parameters for the `base` object:

```
base
    TYPE
    ADMDIR_IN_ROOTFS
    ADMIN_EMAIL
    DB_SERVER_BIN
    DB_SERVER_HOST
    DB_SERVER_PORT
    DIRECT_IO_MAXIMUM_SIZE
    EXPORT_METRICS
    HBA_BANDWIDTH
    HOME_DIR
    JOURNAL_DIR
    JOURNAL_SIZE
    LICENSE_FILE
    METRICS_RETENTION
    NODE_BANDWIDTH
    OV_KEY_FILE
    OV_SERVER
    PERFTRACE_METRICS
    SERVER_NAME
    SPOOL_DIR
    TMP_DIR
    VALID_ROOT_HOSTS
```

## base Object Parameters

The `base` object's parameters define pathnames and file sizes necessary for DMF operation. It is expected that you will modify the pathnames, although those provided will work without modification. All pathnames must be unique.



**Warning:** Never change pathnames or server names in `base` object parameters while DMF is running; making changes of this type can result in data corruption or data loss.

---

| Parameter        | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
|------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| TYPE             | Specifies <code>base</code> (required name for this type of object). There is no default.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| ADMDIR_IN_ROOTFS | <p>Specifies which DMF administrative directories and store directories can reside in the root (/) filesystem. By default, the DMF daemon does not permit a DMF administrative directory or disk MSP store directory to reside in the root filesystem, which avoids the situation where a misconfigured or incorrectly mounted filesystem could fill the root filesystem. You can override this default action by using the <code>ADMDIR_IN_ROOTFS</code> parameter to specify a list of directories. The DMF daemon will abort if the directory specified by any of the following parameters resides in the root filesystem but does not appear in the <code>ADMDIR_IN_ROOTFS</code> list:</p> <ul style="list-style-type: none"><li>• <code>CACHE_DIR</code></li><li>• <code>HOME_DIR</code></li><li>• <code>JOURNAL_DIR</code></li><li>• <code>SPOOL_DIR</code></li><li>• <code>Disk MSP STORE_DIRECTORY</code></li><li>• <code>TMP_DIR</code></li></ul> <p>Do not change this parameter while DMF is running.</p> |
| ADMIN_EMAIL      | Specifies the e-mail address to receive output from administrative tasks (see "Automated Maintenance Tasks" on page 175). The mail can include errors, warnings, and output from any configured tasks. You can specify a list of addresses. When using Parallel DMF, data movers (the DMF server node and the parallel data-mover nodes) may send email to the <code>ADMIN_EMAIL</code> addresses. Therefore, choose addresses that can receive email from any data mover in the configuration.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |

|                        |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
|------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| DB_SERVER_BIN          | Specifies the directory where the binaries related to the Postgres database server are installed. The default is /usr/bin.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| DB_SERVER_HOST         | Specifies the hostname where the Postgres database server should be configured to run. The default is localhost.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
| DB_SERVER_PORT         | Specifies the port on which the Postgres database server should be configured to run. The default is 5432.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| DIRECT_IO_MAXIMUM_SIZE | Specifies the maximum size of I/O requests when using O_DIRECT I/O to read from any managed filesystem or when migrating files down the hierarchy from the <i>STORE_DIRECTORY</i> of the disk cache manager (DCM) MSP. <i>DIRECT_IO_MAXIMUM_SIZE</i> is ignored for a particular filesystem or DCM MSP store when <i>DIRECT_IO_SIZE</i> is specified in the configuration stanza for that filesystem or DCM MSP. The legal range of values is 262144–18446744073709551615. The default is 1048576. By default, the unit of measure is bytes; see "Units of Measure" on page 275.                                                                                                                           |
| EXPORT_METRICS         | Enables DMF's use of the common arena for use by dmstat, dmarenadump, and other commands. You can set this parameter to ON or OFF. The default is OFF. If set to OFF, some statistics in DMF Manager cannot be displayed. Do not change this parameter while DMF is running.                                                                                                                                                                                                                                                                                                                                                                                                                               |
| HBA_BANDWIDTH          | <i>(OpenVault only)</i> Specifies the default I/O bandwidth capacity of an HBA port that is connected to drives on the node. The value is in bytes per second. All of the HBA ports connected to drives on a node are assumed to have the same bandwidth capacity. If <i>HBA_BANDWIDTH</i> is not specified anywhere, the default is 1024000000000000; for more information, see "Device Block-Size Defaults and Bandwidth" on page 276. For a complete description, see "node Object" on page 294. An <i>HBA_BANDWIDTH</i> value specified in a node object overrides the default value specified in the base object. Also see <i>BANDWIDTH_MULTIPLIER</i> in "drivegroup Object Parameters" on page 397. |

**HOME\_DIR**

Specifies the base pathname for directories in which files related to the daemon database and LS database reside. This directory must not be in a managed filesystem. By default, this value must not reside in the root filesystem (see the description of `ADMDIR_IN_ROOTFS` above). The best practice is for *HOME\_DIR* to be the mount point of a filesystem that is used only by DMF. In this way, it is much less likely that the filesystem will become full and cause DMF to abort. If you choose to use *HOME\_DIR* for storing HA files or scripts that must be visible on a failover platform, you must use naming conventions that will not likely conflict with present or future DMF files and you must ensure that the files do not cause the filesystem to become full. Performance characteristics of the *HOME\_DIR* filesystem will impact DMF database transaction performance and may become a limiting factor in achievable DMF database transaction rates. When using Parallel DMF, *HOME\_DIR* must either be a CXFS filesystem or be in a CXFS filesystem.

For guidelines about the size of *HOME\_DIR*, see "Configure Filesystems and Directories Appropriately for DMF" on page 94.

---

**Note:** *HOME\_DIR* must be on a separate physical device from *JOURNAL\_DIR*.

---

Do not change this parameter while DMF is running.

**JOURNAL\_DIR**

Specifies the base pathname for directories in which the journal files for the daemon database and LS database will be written. This directory must not be in a managed filesystem. By default, this value must not reside in the root filesystem (see the description of `ADMDIR_IN_ROOTFS` above). The best practice is for *JOURNAL\_DIR* to be the mount point of a filesystem that is used only by DMF. In this way, it is much less likely that the filesystem will become full and cause DMF to abort. The appropriate size of this filesystem is

a function of the expected daily DMF transaction activity and the number of days that journals are kept.

---

**Note:** *JOURNAL\_DIR* must be on a separate physical device from *HOME\_DIR*.

---

Do not change this parameter while DMF is running.

|                   |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
|-------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| JOURNAL_SIZE      | Specifies the maximum size (in bytes) of the database journal file before DMF closes it and starts a new file. The default is 64000000 (or 64m). By default, the unit of measure is bytes; see "Units of Measure" on page 275.                                                                                                                                                                                                                                                                                                                                                                                                     |
| LICENSE_FILE      | Specifies the full pathname of the file containing the licenses used by DMF. The default is <code>/etc/lk/keys.dat</code> . Do not change this parameter while DMF is running.                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| METRICS_RETENTION | <p>Specifies the retention time for the DMF tape drive cumulative metrics. The cumulative metrics are reset to zero after this interval has passed since the creation of the arena object. This parameter is evaluated when a new drive object is created in the arena, typically during daemon startup. Valid values are integer followed by one of:</p> <p>h[ours]<br/>d[ays]<br/>w[eeks]</p> <p>For example, to specify five days, you could use either of the following:</p> <pre>METRICS_RETENTION 5d METRICS_RETENTION 5days</pre> <p>By default, the cumulative metrics will be retained until the DMF daemon restarts.</p> |



---

**Note:** METRICS\_RETENTION is used internally by DMF for its cumulative/averaged metrics and does not change the duration for which PCP metric archives are maintained.

---

|                |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
|----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| NODE_BANDWIDTH | <p><i>(OpenVault only)</i> Specifies the default I/O bandwidth capacity of the node. If NODE_BANDWIDTH is not specified anywhere, the default is 1024000000000000; for more information, see "Device Block-Size Defaults and Bandwidth" on page 276. For a complete description, see "node Object" on page 294. A NODE_BANDWIDTH value specified in a node object overrides the default value specified in the base object. Also see BANDWIDTH_MULTIPLIER in "drivegroup Object Parameters" on page 397.</p> |
| OV_KEY_FILE    | <p><i>(OpenVault only)</i> Specifies the file containing the OpenVault security keys used by DMF. It is usually located in HOME_DIR and called ov_keys. There is no default. When using Parallel DMF, this file must be visible to the DMF server and all parallel data-mover nodes, therefore it must be in a CXFS filesystem. Use dmov_keyfile to create or update this file. The file should be updated if the OpenVault server name changes. Do not change this parameter while DMF is running.</p>      |
| OV_SERVER      | <p><i>(OpenVault only)</i> Specifies the name associated with the Internet Protocol (IP) address on which the OpenVault server is listening. This should only be set if the OpenVault server is not on the same system as the DMF server. Do not change this parameter while DMF is running.</p>                                                                                                                                                                                                             |

---

**Note:** More configuration steps are necessary to configure DMF to use OpenVault; see "OpenVault Configuration Tasks" on page 491.

---

`PERFTRACE_METRICS` Enables collection of performance tracking information from DMF. Performance over time of individual components (filesystems, cartridges, tape drives, and so on) can then be graphically viewed using DMF Manager. You can set this parameter to `ON` or `OFF`. The default is `OFF`. If set to `OFF`, detailed I/O information will not be recorded by DMF and the **I/O panel** in DMF Manager cannot display certain information. See "DMF I/O" on page 248.

---

**Note:** After you change this parameter, you must restart DMF.

---

`SERVER_NAME` Specifies the hostname of the system on which the DMF server is running. In an HA configuration, `SERVER_NAME` must be the HA virtual hostname rather than the output of the `hostname` command. This parameter is only required for HA configurations or configurations using Parallel DMF.

---

**Note:** If you change this parameter, you must copy the DMF configuration file manually to each parallel data-mover node and then restart the DMF services.

Do not change this parameter while DMF is running.

---

`SPOOL_DIR` Specifies the base pathname for directories in which DMF log files are kept. This directory must not be in a managed filesystem. By default, this value must not reside in the root filesystem (see the description of `ADMDIR_IN_ROOTFS` above). The best practice is for `SPOOL_DIR` to be the mount point of a filesystem that is used only by DMF. In this way, it is much less likely that the filesystem will become full and cause DMF to abort. The appropriate size of this filesystem is a function of the expected daily DMF transaction activity, the `MESSAGE_LEVEL` parameter setting, and the number of days that logs are kept. When using Parallel DMF, `SPOOL_DIR` must either be a CXFS filesystem or

be in a CXFS filesystem. Do not change this parameter while DMF is running.

TMP\_DIR

Specifies the base pathname for directories in which DMF puts temporary files for its own internal use. It is also used by DMF commands and scripts and is the directory used by default by the LS for caching files if the `CACHE_DIR` parameter is not defined. This directory must not be in a managed filesystem. By default, this value must not reside in the root filesystem (see the description of `ADMDIR_IN_ROOTFS` in "base Object Parameters" on page 278). The best practice is for *TMP\_DIR* to be the mount point of a filesystem that is used only by DMF. *TMP\_DIR* filesystem performance will impact the performance of many of the internal DMF administrative tasks, particularly tasks that involve the need to sort DMF databases. When using Parallel DMF, *TMP\_DIR* must either be a CXFS filesystem or be in a CXFS filesystem.

Many DMF operations that do analysis on the DMF database contents use *TMP\_DIR* as their work directory. Because most of these involve large buffered I/O, SGI recommends that you configure *TMP\_DIR* on a fast disk, with bandwidth at the RAID level. Do not change this parameter while DMF is running.

VALID\_ROOT\_HOSTS

Specifies hostnames whose `root` users may perform certain tasks and who may also use the `dmprojid` command or equivalent `libdmfusr.so` functions.

Tasks include the following:

- Specify nondefault priority on DMF commands (such as `dmget`)
- Specify the MSPs, VGs, and MGs to which files should be migrated when using the `dmput` or `dmarchive` command, or equivalent `libdmfusr.so` functions.
- Override the order of the MSPs, VGs, and MGs from which to try to recall files on the `dmarchive`, `dmcopy`, `dmget`, `dmmove`, and `dmunput` commands,

or equivalent `libdmfusr.so` functions, overriding the default order as defined in the DMF configuration file.

The `root` user on the DMF server may always perform these actions, and therefore the DMF server name does not need to be included in `VALID_ROOT_HOSTS`. By default, only the `root` user on the DMF server may perform these actions.

---

**Note:** Customizable policies may cause this behavior to be overridden.

---

Changes to `VALID_ROOT_HOSTS` will take effect immediately for new requests and after no more than 10 minutes for long-running processes.

When an MSP, LS, daemon, or configuration file object (such as the `taskgroup` object named `dump_tasks` in Example 7-10, page 333) obtains a path such as `HOME_DIR` from the configuration file, the actual path used is `HOME_DIR` plus the MSP/LS/daemon object name appended as a subdirectory. For example, if `HOME_DIR` was set to `/dmf/home` in the configuration file, and the `taskgroup` object named `dump_tasks` used a value of `HOME_DIR/tapes` for the `DUMP_TAPES` parameter, then the actual path for `DUMP_TAPES` would resolve to `/dmf/home/dump_tasks/tapes`.

---

**Note:** Do not use automated space management to manage the `HOME_DIR`, `SPOOL_DIR`, or `JOURNAL_DIR` directories, because DMF daemon processes will deadlock if files that they are actively using within these directories are migrated. The `dmcheck` command reports an error if any of the `HOME_DIR`, `SPOOL_DIR`, or `JOURNAL_DIR` directories are also configured as managed filesystems. You should configure a `taskgroup` object for daemon tasks to manage old log files and journal files in these directories. See "taskgroup Object" on page 304 for more information.

---

## base Object Examples

This section discusses the following examples:

- "base Object for Basic DMF" on page 287
- "base Object for Parallel DMF" on page 287

- "base Object for Parallel DMF in an HA Cluster" on page 288

### base Object for Basic DMF

#### Example 7-1 base Object for Basic DMF

```
define base
    TYPE                base
    ADMIN_EMAIL         root@dmfserver
    HOME_DIR            /dmf/home
    TMP_DIR             /dmf/tmp
    SPOOL_DIR           /dmf/spool
    JOURNAL_DIR         /dmf/journals
    JOURNAL_SIZE        10m
    OV_KEY_FILE         /dmf/home/ov_keys
enddef
```

In the above example:

- A new journal file will be created after the present file reaches 10 million bytes
- The `OV_KEY_FILE` parameter is necessary if OpenVault is used as the mounting service
- The OpenVault server is on the same system as the DMF server, so `OV_SERVER` is not specified

### base Object for Parallel DMF

#### Example 7-2 base Object for Parallel DMF

```
define base
    TYPE                base
    SERVER_NAME         server1
    ADMIN_EMAIL         root@dmfserver
    HOME_DIR            /dmf/home
    TMP_DIR             /dmf/tmp
    SPOOL_DIR           /dmf/spool
    JOURNAL_DIR         /dmf/journals
    JOURNAL_SIZE        10m
    OV_KEY_FILE         /dmf/home/ov_keys
enddef
```

In the above example:

- The `SERVER_NAME` parameter is required when using Parallel DMF. The hostname of the node that is running DMF is `server1`. OpenVault is running on the same system, so `OV_SERVER` is not specified.
- `/dmf/tmp` must either be a CXFS filesystem or be in a CXFS filesystem when using Parallel DMF.
- The `/dmf/spool` directory must either be a CXFS filesystem or be in a CXFS filesystem when using Parallel DMF.
- A new journal file will be created after the present file reaches 10 million bytes.
- OpenVault must be configured as the mounting service for drives that are used by parallel data-mover nodes. The `/dmf/home/ov_keys` file must be visible to the DMF server node and all parallel data-mover nodes, therefore it must be in a CXFS filesystem.

#### base Object for Parallel DMF in an HA Cluster

**Example 7-3** base Object for Parallel DMF in an HA Cluster

```
define base
    TYPE                base
    SERVER_NAME         virtual-server
    ADMIN_EMAIL        root@dmfserver
    HOME_DIR            /dmf/home
    TMP_DIR             /dmf/tmp
    SPOOL_DIR          /dmf/spool
    JOURNAL_DIR        /dmf/journals
    JOURNAL_SIZE       10m
    OV_KEY_FILE        /dmf/home/ov_keys
enddef
```

In the above example:

- The `SERVER_NAME` parameter is required when using Parallel DMF. Because this configuration is using HA, it must be set to the HA virtual hostname (in this case `virtual-server`).

---

**Note:** The `INTERFACE` parameter in the node objects for the DMF servers must correspond to `SERVER_NAME`.

---

- `/dmf/tmp` must either be a CXFS filesystem or be in a CXFS filesystem when using Parallel DMF.
- The `/dmf/spool` directory must either be a CXFS filesystem or be in a CXFS filesystem when using Parallel DMF.
- OpenVault must be configured as the mounting service for drives that are used by parallel data-mover nodes. The `/dmf/home/ov_keys` file must be visible to the DMF server and all parallel data-mover nodes, therefore it must be in a CXFS filesystem.
- The OpenVault server is on the same system as the DMF server, so `OV_SERVER` is not specified.

## **dmdaemon Object**

This section discusses the following:

- "dmdaemon Object Name" on page 289
- "dmdaemon Object Summary" on page 289
- "dmdaemon Object Parameters" on page 290
- "dmdaemon Object Example" on page 293

### **dmdaemon Object Name**

The name of the `dmdaemon` object is chosen by the administrator and may contain uppercase or lowercase alphanumeric characters or underscores. It cannot begin with an underscore or contain any white space.

### **dmdaemon Object Summary**

Following is a summary of the potential parameters for the `dmdaemon` object:

```
dmdaemon
    TYPE
    EXPORT_QUEUE
    LS_NAMES or MSP_NAMES
    MESSAGE_LEVEL
```

MIGRATION\_LEVEL  
 MOVE\_FS  
 PARTIAL\_STATE\_FILES  
 RECALL\_NOTIFICATION\_RATE  
 TASK\_GROUPS

### dmdaemon Object Parameters

The `dmdaemon` object defines the configuration parameters that are necessary for operation of the DMF daemon. It is expected that you will modify the values for the pathnames and MSP names.

| Parameter             | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
|-----------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| TYPE                  | Specifies <code>dmdaemon</code> (required name for this type of object). There is no default.<br><br><b>Note:</b> This cannot be specified as <code>dmfdaemon</code> . It must be <code>dmdaemon</code> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
| EXPORT_QUEUE          | Instructs the daemon to export details of its internal request queue to <code>SPOOL_DIR/daemon_exports</code> every two minutes, for use by <code>dmstat</code> and other utilities. On a busy system, the responsiveness of the daemon may be improved by disabling this feature. You can set this parameter to <code>ON</code> or <code>OFF</code> . The default is <code>OFF</code> .                                                                                                                                                                                                                                                                                           |
| LS_NAMES or MSP_NAMES | Names the LSs and MSPs used by the DMF daemon. You must specify either <code>LS_NAMES</code> or <code>MSP_NAMES</code> , but not both parameters (however, the value of either parameter can be a mixture of both LSs and MSPs). There is no default.<br><br>The order of the names is significant. Where there are multiple copies of the data of migrated files, recalls will normally be directed to the first-named LS/MSP that is applicable. If more than one VG within an LS/MSP contains copies, the order of the names in the <code>libraryserver</code> object's <code>DRIVE_GROUPS</code> parameter and the <code>drivegroup</code> object's <code>VOLUME_GROUPS</code> |



parameter are also significant. DMF supports up to 1024 MSPs, VGs and/or MGs.

---

**Note:** See "Ensure that the Cache Copy is Recalled First" on page 116.

---

Do not change these parameters while DMF is running.

MESSAGE\_LEVEL

Specifies the highest message level that will be written to the daemon log. It must be an integer in the range 0–6; the higher the number, the more messages written to the log file. The default is 2. For more information on message levels, see Chapter 10, "Message Log Files" on page 507.

MIGRATION\_LEVEL

Sets the highest level of migration service allowed on all DMF filesystems. From highest level of migration to least:

- auto (automated space management)
- user (requests from `dmput` or `dmmigrate` only)
- none (no migration)

You can also configure a lower level of migration for a specific filesystem by using the `MIGRATION_LEVEL` parameter in the `filesystem` stanza, which also permits a setting of `archive` that is used for DMF direct-archiving of unmanaged filesystems via the `dmarchive` command. See "filesystem Object Parameters" on page 351.

The default is `auto`.

See "policy Object" on page 364 for information about configuring automated space management.

MOVE\_FS

Specifies one or more scratch filesystems that may be used when moving files between MSPs/VGs. The first filesystem named for this parameter is used as the default if the `-f` option is not specified on the `dmmove` command. This filesystem must reside in the root filesystem. Each filesystem specified must be the root of

a DMAPI-mounted filesystem (mounted with `dmi,mtpt=/MOVE_FS`). You must specify a value for `MOVE_FS` if you intend to use the `dmmove` command; there is no default. When using Parallel DMF, `MOVE_FS` if specified must be a CXFS filesystem.

The size of `MOVE_FS` is a function of expected `dmmove` activity. `MOVE_FS` must be mounted when a `dmmove` command is run. The best practice when using `MOVE_FS` is for it to be dedicated to the `dmmove` function. (The `dmmove` command calculates the available space in `MOVE_FS` when selecting move candidates; if other processes are allocating space in `MOVE_FS`, those calculations can become inaccurate, causing errors.)

If the scratch filesystem is managed by DMF, SGI highly recommends that you use the `-s` option when executing the `dmmove` or `dmemptytape` commands to prevent the filesystem free-space minimum from being reached as a result of the command's execution. For more information, see the `dmmove(8)` and `dmemptytape(8)` man pages.

`PARTIAL_STATE_FILES`

Enables or disables the DMF daemon's ability to produce partial-state files. The possible values are:

- `ON`, which means that the daemon will correctly process `put` and `get` requests that would result in a partial-state file. The default is `ON`.
- `OFF`, which means that all `put` and `get` requests that require a change to the online status of the file will result in a file that is completely online or offline. That is, any `put` request that makes any part of the file offline will result in the entire file being made offline. Any `get` request that would result in any part of the file being brought back online will result in the entire file being brought back online.

`RECALL_NOTIFICATION_RATE`

Specifies the approximate rate (in seconds) at which regions of a file being recalled are put online. This allows for access to part of a file before the entire file is

recalled. The default is 30 seconds. Specify a value of 0 if you want the user process to be blocked until the entire recall is complete. The optimum setting of this parameter is dependent on many factors and must be determined by trial and error. The actual rate at which regions being recalled are put online may vary from the value of `RECALL_NOTIFICATION_RATE`.

`TASK_GROUPS`

Names the `taskgroup` objects that contain tasks the daemon should run. By default, no tasks are run. For more information, see "taskgroup Object" on page 304. SGI recommends that you use the task groups specified in the sample configuration files, changing the parameters as necessary for your site.

## dmdaemon Object Example

### Example 7-4 dmdaemon object

```
define daemon
    TYPE                dmdaemon
    MOVE_FS             /dmmove_dir
    LS_NAMES            lib1 ftp2
    TASK_GROUPS         daemon_tasks dump_tasks
enddef
```

In the above example:

- The name of the dmdaemon object is `daemon`.
- The `dmmove` command will use the `/dmmove_dir` filesystem as a scratch filesystem.
- The names of the LSs are `lib1` and `ftp2`.
- The daemon will run the tasks specified by the `daemon_tasks` and `dump_tasks` objects (see Example 7-13, page 336 and Example 7-10, page 333). In the example, `daemon_tasks` defines the tasks such as scanning and managing log files and journal files. The `dump_tasks` object defines tasks that back up managed filesystems.
- The `MIGRATION_LEVEL` level is not explicitly set, so the default of `auto` is used.

## node Object

- "node Object Name" on page 294
- "node Object Summary" on page 294
- "node Object Parameters" on page 294
- "node Object Examples" on page 297

### node Object Name

The name of the `node` object must be the same as the output of the `hostname` command.

### node Object Summary

Following is a summary of the potential parameters for the `node` object:

```
node
    TYPE
    HBA_BANDWIDTH
    INTERFACE
    MERGE_INTERFACE
    NODE_BANDWIDTH
    SERVICES
```

### node Object Parameters

---

**Note:** The `node` object is only for Parallel DMF configurations. Basic DMF configurations do not use the `node` object.

---

The name of the `node` object must match the name returned by `hostname` on the system. In a Parallel DMF configuration, there must be a `node` object for the DMF server and every parallel data-mover node. In a Parallel DMF configuration in an HA cluster, the `node` objects for the DMF servers will have identical parameter values.

| Parameter       | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
|-----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| TYPE            | Specifies <code>node</code> (required name for this type of object). There is no default.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| HBA_BANDWIDTH   | <p><i>(OpenVault only)</i> Specifies the I/O bandwidth capacity of an HBA port that is connected to drives on the node. The value is in bytes per second. All of the HBA ports connected to drives on a node are assumed to have the same bandwidth capacity. The LS uses this value when determining which drives to use. The maximum is 1024000000000000. The minimum is 0, which means that the HBA will not be used.</p> <p>HBA_BANDWIDTH can also be specified in the <code>base</code> object, in which case the value there is used as the default (values specified in a <code>node</code> object override the default for that node); see "base Object Parameters" on page 278. If HBA_BANDWIDTH is not specified in the <code>base</code> object, the default is 1024000000000000. For more information, see "Device Block-Size Defaults and Bandwidth" on page 276. Also see BANDWIDTH_MULTIPLIER in "drivegroup Object Parameters" on page 397.</p> |
| INTERFACE       | Specifies the IP address or associated name of this node to be used for communication between DMF components. By default, the system hostname will be used. If this node is a potential DMF server in an HA configuration, this parameter must match the virtual hostname used for <code>SERVER_NAME</code> in the <code>base</code> object. See "Use a Private Network Interface in a Parallel Environment" on page 121.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| MERGE_INTERFACE | Specifies the IP address or associated name on this node to be used when merging sparse volumes via sockets. The default is to use the same interface used for other DMF communication (see <code>INTERFACE</code> above). See "Use a Private Network Interface in a Parallel Environment" on page 121.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
| NODE_BANDWIDTH  | <i>(OpenVault only)</i> Specifies the I/O bandwidth capacity of this node, in bytes per second. The LS uses this value to calculate how many drives it can                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |

simultaneously use on a node. The maximum is 1024000000000000. The minimum is 0, which means that the node will not be used.

NODE\_BANDWIDTH can also be specified in the base object, in which case the value there is used as the default (values specified in a node object override the default for that node); see "base Object" on page 277. If NODE\_BANDWIDTH is not specified in the base object, the default is 1024000000000000. For more information, see "Device Block-Size Defaults and Bandwidth" on page 276. Also see BANDWIDTH\_MULTIPLIER in "drivegroup Object Parameters" on page 397.

SERVICES

Specifies the name of the services object used to configure DMF services on this node. Multiple nodes may refer to the same services object. For node-specific configuration, each node can refer to a different services object. If no SERVICES parameter is defined, the default values for the services object parameters are used.

## node Object Examples

This section discusses the following examples:

- "node Objects for Parallel DMF" on page 297
- "node Objects for Parallel DMF in an HA Cluster" on page 298

### node Objects for Parallel DMF

#### Example 7-5 node Objects for Parallel DMF

```
define server1
    TYPE                node
    INTERFACE            server1-dmfnet
    SERVICES             server1_services
enddef

define pdm1
    TYPE                node
    INTERFACE            pdm1-dmfnet
    SERVICES             pdm1_services
enddef
```

In the above example:

- There are two data movers: the DMF server `server1` and the parallel data-mover node `pdm1`.
- The DMF services on the `server1` node use the parameters defined in the `server1_services` object. The DMF services on the `pdm1` node use the parameters defined in the `pdm1_services` object.
- Because `INTERFACE` is defined, the nodes will communicate on the IP addresses associated with the hostnames `server1-dmfnet` and `pdm1-dmfnet`. (If `INTERFACE` was not defined, they would communicate using `server1` and `pdm1`.)

**node Objects for Parallel DMF in an HA Cluster****Example 7-6** node Objects for Parallel DMF in an HA Cluster

```
define server1
    TYPE                node
    INTERFACE           virtual-server
    SERVICES            dmfservice_services
endef

define server2
    TYPE                node
    INTERFACE           virtual-server
    SERVICES            dmfservice_services
endef

define pdm1
    TYPE                node
    SERVICES            pdm1_services
endef
```

In the above example:

- The following nodes are data movers:
  - Either the potential DMF server `server1` or the potential DMF server `server2` (for example, `server1` could be the active DMF server and `server2` could be the passive DMF server)
  - The parallel data-mover node `pdm1`

---

**Note:** At any given time, only one of the potential DMF server nodes (either `server1` or `server2`) may provide data mover functionality.

---

- The virtual hostname in the HA cluster is `virtual-server`. The `INTERFACE` parameter is required in an HA cluster for the potential DMF servers and it must match the value for `SERVER_NAME` in the base object (see "base Object" on page 277).
- The potential DMF server nodes provide the tasks that are described by the `dmfservice_services` object. The parallel data-mover node provides the DMF services described by the `pdm1_services` object.



- Because `server1` and `server2` are both potential servers in this HA configuration, they should specify identical parameters and parameter values.
- The nodes will communicate using the IP addresses associated with the `virtual-server` and `pdml` hostnames.

## services Object

This section discusses the following:

- "services Object Name" on page 299
- "services Object Summary" on page 299
- "services Object Parameters" on page 300
- "services Object Examples" on page 301

### services Object Name

The name of the `services` object is chosen by the administrator and may contain uppercase or lowercase alphanumeric characters or underscores. It cannot begin with an underscore or contain any white space.

### services Object Summary

Following is a summary of the potential parameters for the `services` object:

```
services
    TYPE
    MESSAGE_LEVEL
    NODE_ANNOUNCE_RATE
    NODE_TIMEOUT
    SERVICES_PORT
    TASK_GROUPS
```

## services Object Parameters

The `services` object defines parameters for `dmnode_service` and other DMF services. When using Parallel DMF, multiple `services` objects may be defined. For basic DMF configurations, exactly one `services` object may be defined. (The `services` parameters all have defaults, so you only need to define a `services` object if you want to change those defaults.)

| Parameter                       | Description                                                                                                                                                                                                                                                                                                                                                                                   |
|---------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>TYPE</code>               | Specifies <code>services</code> (required name for this type of object). If you include this object, you must specify this parameter.                                                                                                                                                                                                                                                         |
| <code>MESSAGE_LEVEL</code>      | Specifies the highest message level that will be written to the service logs. It must be an integer in the range 0–6; the higher the number, the more messages written to the log file. The default is 2. For more information on message levels, see Chapter 10, "Message Log Files" on page 507.                                                                                            |
| <code>NODE_ANNOUNCE_RATE</code> | Specifies the rate (in seconds) at which the DMF server or parallel data-mover node will contact the <code>dmnode_service</code> on the DMF server to announce its presence. This also determines the rate at which configuration changes are propagated to any parallel data-mover nodes. This value should be less than the value of <code>NODE_TIMEOUT</code> . The default is 20 seconds. |
| <code>NODE_TIMEOUT</code>       | Specifies the number of seconds after which the data mover functionality on the DMF server or on a parallel data-mover node will be considered inactive if it has not contacted the <code>dmnode_service</code> on the DMF server. This value should be larger than the value of <code>NODE_ANNOUNCE_RATE</code> . The default is 180 seconds.                                                |
| <code>SERVICES_PORT</code>      | Specifies the port number on which DMF starts a locator service, which DMF uses to locate other DMF services. It must be an integer in the range 1–65535. The default is 11108.                                                                                                                                                                                                               |

---

**Note:** If you change this parameter, you must copy the DMF configuration file manually to each parallel data-mover node and then restart the DMF services.

Do not change this parameter while DMF is running.

---

TASK\_GROUPS

Names the `taskgroup` objects that contain scripts to be run on the DMF server and every parallel data-mover node. (This is unlike the `TASK_GROUPS` parameters of other objects, which contain scripts to be run on just the DMF server.) If you specify this parameter, you must specify the scripts to be run. For more information, see "taskgroup Object" on page 304. By default, no tasks are run. SGI recommends that you use the task groups specified in the sample configuration files, changing the parameters as necessary for your site.

## services Object Examples

This section discusses the following examples:

- "services object for Parallel DMF" on page 301
- "services Object for Parallel DMF in an HA Cluster" on page 303

### services object for Parallel DMF

#### Example 7-7 services object for Parallel DMF

```
define server1_services
    TYPE                services
    MESSAGE_LEVEL       2
    TASK_GROUPS         node_tasks
enddef

define pdml_services
    TYPE                services
    MESSAGE_LEVEL       4
    SERVICES_PORT       1111
    TASK_GROUPS         node_tasks
```

```
endif
```

In the above example:

- Two services are defined:
  - `server1_services` (which applies to `server1`, as shown in Example 7-5, page 297)
  - `pdml_services` (which applies to `pdml`, as also shown in Example 7-5)
- The `server1` services will log fewer messages than the `pdml` services.
- The `pdml` services use locator port 1111. The `server1` services will use the default port.
- Both services use the tasks described by the `node_tasks` object.

**services Object for Parallel DMF in an HA Cluster****Example 7-8** services Object for Parallel DMF in an HA Cluster

```
define dmfservice_services
    TYPE                services
    MESSAGE_LEVEL       2
    TASK_GROUPS         servernode_tasks
endef

define pdml_services
    TYPE                services
    MESSAGE_LEVEL       4
    SERVICES_PORT       1111
    TASK_GROUPS         movernode_tasks
endef
```

In the above example:

- Two services are defined:
  - dmfservice\_services, which applies to server1 and server2 (as shown in Example 7-6, page 298)
  - pdml\_services, which applies to pdml (as shown in Example 7-6)
- The dmfservice\_services services will log fewer messages than the pdml services.
- The pdml services use locator port 1111. The dmfservice\_services services will use the default port.
- The active DMF server (either server1 or server2) will run the tasks defined by the servernode\_tasks object.
- The parallel data-mover node pdml will run the tasks defined by the movernode\_tasks object.

## **taskgroup Object**

This section discusses the following:

- "Overview of the Tasks" on page 304
- "Backup Tasks" on page 309
- "taskgroup Object Name" on page 310
- "taskgroup Object Summary" on page 310
- "taskgroup Object Parameters" on page 312
- "taskgroup Object Examples" on page 332

See also "Precedence of Objects for Integrated Backups" on page 154.

### **Overview of the Tasks**

You can configure `taskgroup` objects to manage how periodic maintenance tasks are performed. The object that performs the tasks refers to the `taskgroup` name in its stanza. You can configure when each task should run. For some of the tasks, you must provide more information. Table 7-1 summarizes the tasks.

**Table 7-1** Automated Maintenance Task Summary

| Referencing Object Type | Task                             | Purpose                                                                                                                                  | Associated Parameters                                                                                |
|-------------------------|----------------------------------|------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------|
| dmdaemon                | run_audit.sh                     | Audit databases                                                                                                                          |                                                                                                      |
|                         | run_copy_databases.sh            | Back up DMF databases                                                                                                                    | DATABASE_COPIES                                                                                      |
|                         | run_daily_drive_report.sh        | Create a report about physical tape drives that have indicated they need cleaning                                                        | DRIVETAB                                                                                             |
|                         | run_daily_report.sh <sup>1</sup> | Create a report including information on managed filesystems (if run_filesystem_scan.sh has been run recently) and DCM MSPs, and all LSs |                                                                                                      |
|                         | run_daily_tsreport.sh            | Create a report containing the output of the tsreport command, which reports physical tape drive alerts, errors, and statistics          | DRIVETAB<br>TSREPORT_OPTIONS                                                                         |
|                         | run_dmmigrate.sh                 | Run dmmigrate on all filesystems defined with automated space-management or user space-management enabled                                | DMMIGRATE_MINIMUM_AGE<br>DMMIGRATE_TRICKLE<br>DMMIGRATE_UNACK<br>DMMIGRATE_VERBOSE<br>DMMIGRATE_WAIT |

<sup>1</sup> The run\_compact\_tape\_report.sh and run\_tape\_report.sh tasks have been superseded by the run\_daily\_report.sh task.

| Referencing Object Type | Task                   | Purpose                                                                                                  | Associated Parameters                                                                                                                                                                                                                                                                                                            |
|-------------------------|------------------------|----------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                         | run_filesystem_scan.sh | Run dmscanfs on filesystems to collect file information for subsequent use by other scripts and programs | SCAN_FILESYSTEMS<br>SCAN_FOR_DMSTAT<br>SCAN_OUTPUT<br>SCAN_PARALLEL<br>SCAN_PARAMS                                                                                                                                                                                                                                               |
|                         | run_full_dump.sh       | <i>(disk, tape, and integrated backups only)</i> Full backup of filesystems <sup>2</sup>                 | See Table 7-2 on page 309                                                                                                                                                                                                                                                                                                        |
|                         | run_hard_deletes.sh    | Hard-delete files that are no longer on backup media                                                     | Uses DUMP_RETENTION                                                                                                                                                                                                                                                                                                              |
|                         | run_partial_dump.sh    | <i>(disk, tape, and integrated backups)</i> Perform an incremental backup of filesystems                 | Associated with the same parameters as run_full_dump.sh plus UPDATE_CTIME. (If DUMP_MAX_FILESPACE is set but UPDATE_CTIME is not, run_partial_dump.sh will perform a full backup rather than an incremental backup for managed filesystems. See "DUMP_MAX_FILESPACE Requires UPDATE_CTIME for Incremental Backups" on page 148.) |
|                         | run_remove_alerts.sh   | Remove old alert records                                                                                 | ALERT_RETENTION<br>MAX_ALERTDB_SIZE<br>REMALEERT_PARAMS                                                                                                                                                                                                                                                                          |
|                         | run_remove_journals.sh | Remove old journal files                                                                                 | JOURNAL_RETENTION                                                                                                                                                                                                                                                                                                                |
|                         | run_remove_logs.sh     | Remove old log files                                                                                     | LOG_RETENTION                                                                                                                                                                                                                                                                                                                    |
|                         | run_remove_perf.sh     | Remove old performance records                                                                           | MAX_PERFDB_SIZE<br>PERF_RETENTION<br>REMPERF_PARAMS                                                                                                                                                                                                                                                                              |

<sup>2</sup> For restores, see the dmxfrestore(8) man page.



| Referencing Object Type | Task              | Purpose                                                                                                                                      | Associated Parameters                                                                                |
|-------------------------|-------------------|----------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------|
|                         | run_scan_logs.sh  | Scan recent log files for errors                                                                                                             |                                                                                                      |
| drivegroup              | run_merge_mgr.sh  | Merge sparse volumes                                                                                                                         | DATA_LIMIT<br>THRESHOLD<br>VOLUME_LIMIT                                                              |
| libraryserver           | run_merge_stop.sh | Stop volume merges for only those volumes that were previously marked as sparse by either the run_tape_merge.sh or run_merge_mgr.sh scripts. |                                                                                                      |
|                         | run_fmc_free.sh   | Free the volumes in the fast-mount cache that meet the criteria                                                                              | FILE_RETENTION_DAYS<br>FMC_MOVEFS<br>FREE_VOLUME_MINIMUM<br>FREE_VOLUME_TARGET                       |
|                         | run_tape_merge.sh | Merge sparse volumes                                                                                                                         | DATA_LIMIT<br>THRESHOLD<br>VOLUME_LIMIT                                                              |
| DCM msp                 | run_dcm_admin.sh  | Routine DCM MSP administration                                                                                                               |                                                                                                      |
|                         | run_dmmigrate.sh  | Run dmmigrate on the specified <i>STORE_DIRECTORY</i> (for this DCM MSP only)                                                                | DMMIGRATE_MINIMUM_AGE<br>DMMIGRATE_TRICKLE<br>DMMIGRATE_UNACK<br>DMMIGRATE_VERBOSE<br>DMMIGRATE_WAIT |
| filesystem              | run_dmmigrate.sh  | Run dmmigrate on the specified filesystem if it is defined with a <i>MIGRATION_LEVEL</i> of auto or user                                     | DMMIGRATE_MINIMUM_AGE<br>DMMIGRATE_TRICKLE<br>DMMIGRATE_UNACK<br>DMMIGRATE_VERBOSE<br>DMMIGRATE_WAIT |

| Referencing Object Type | Task               | Purpose                                                         | Associated Parameters                                                          |
|-------------------------|--------------------|-----------------------------------------------------------------|--------------------------------------------------------------------------------|
| services                | run_remove_logs.sh | Remove old log files                                            | LOG_RETENTION                                                                  |
| volume group            | run_fmc_free.sh    | Free the volumes in the fast-mount cache that meet the criteria | FILE_RETENTION_DAYS<br>FMC_MOVEFS<br>FREE_VOLUME_MINIMUM<br>FREE_VOLUME_TARGET |

## Backup Tasks

You can schedule backups to be performed via `xfsdump` in the DMF configuration file. When defining a backup task, you must provide information such as:

- Tape and device names
- Retention times for output
- Whether to migrate files before backing up the filesystem
- Locations for inventory files

Not all tasks and parameters apply to each backup method. Table 7-2 lists backup parameters according to method.

**Table 7-2** Dump Parameters According to DMF Backup Method

| DMF Backup Method                  | Parameters                                                                                                                     |
|------------------------------------|--------------------------------------------------------------------------------------------------------------------------------|
| Disk, tape, and integrated backups | DUMP_FILE_SYSTEMS<br>DUMP_FLUSH_DCM_FIRST<br>DUMP_MIGRATE_FIRST<br>DUMP_RETENTION<br>DUMP_MAX_FILESPACE<br>DUMP_XFSDUMP_PARAMS |
| Disk and integrated backups only   | DUMP_COMPRESS<br>DUMP_CONCURRENCY<br>DUMP_DESTINATION<br>DUMP_MIRRORS<br>DUMP_STREAMS<br>DUMP_WORKSPACE                        |

| DMF Backup Method       | Parameters                                                                                                                                                                                      |
|-------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Integrated backups only | DUMP_DR_EMAIL<br>DUMP_DR_EMAIL_MAX_SIZE<br>DUMP_DR_MINIMAL<br>DUMP_DR_MIRRORS<br>DUMP_GROUPS<br>DUMP_MISC_LOCATIONS<br>DUMP_POST_BACKUP_SCRIPT<br>DUMP_POST_DR_SCRIPT<br>DUMP_PRE_BACKUP_SCRIPT |
| Tape backups only       | DUMP_DEVICE<br>DUMP_INVENTORY_COPY<br>DUMP_TAPES<br>DUMP_VSNS_USED                                                                                                                              |

For more information, see Chapter 4, "Backups and DMF" on page 141.

### taskgroup Object Name

The name of the `taskgroup` object is chosen by the administrator and may contain uppercase or lowercase alphanumeric characters or underscores. It cannot begin with an underscore or contain any white space.

### taskgroup Object Summary

Following is a summary of the potential parameters for the `taskgroup` object:

```
taskgroup
    TYPE
    ALERT_RETENTION
    DATA_LIMIT
    DATABASE_COPIES
    DMMIGRATE_MINIMUM_AGE
    DMMIGRATE_MIN_OFFLINE_AGE
    DMMIGRATE_MIN_OFFLINE_SIZE
    DMMIGRATE_QUEUE_MAX
    DMMIGRATE_TRICKLE
    DMMIGRATE_UNACK
    DMMIGRATE_VERBOSE
```

DMMIGRATE\_WAIT  
DRIVETAB  
DUMP\_COMPRESS  
DUMP\_CONCURRENCY  
DUMP\_DESTINATION  
DUMP\_DEVICE  
DUMP\_DR\_EMAIL  
DUMP\_DR\_EMAIL\_MAX\_SIZE  
DUMP\_DR\_MINIMAL  
DUMP\_DR\_MIRRORS  
DUMP\_FILE\_SYSTEMS  
DUMP\_FLUSH\_DCM\_FIRST  
DUMP\_GROUPS  
DUMP\_INVENTORY\_COPY  
DUMP\_MAX\_FILESPACE  
DUMP\_MIGRATE\_FIRST  
DUMP\_MIRRORS  
DUMP\_MISC\_LOCATIONS  
DUMP\_POST\_BACKUP\_SCRIPT  
DUMP\_POST\_DR\_SCRIPT  
DUMP\_PRE\_BACKUP\_SCRIPT  
DUMP\_RETENTION  
DUMP\_STREAMS  
DUMP\_TAPES  
DUMP\_VSNS\_USED  
DUMP\_WORKSPACE  
DUMP\_XFSDUMP\_PARAMS  
FILE\_RETENTION\_DAYS  
FMC\_MOVEFS  
FMC\_NAME  
FREE\_VOLUME\_MINIMUM  
FREE\_VOLUME\_TARGET  
JOURNAL\_RETENTION  
LOG\_RETENTION  
MAX\_ALERTDB\_SIZE  
MAX\_PERFDB\_SIZE  
PERF\_RETENTION  
REMALENT\_PARAMS  
REMPERF\_PARAMS  
RUN\_TASK  
SCAN\_FILESYSTEMS

SCAN\_FOR\_DMSTAT  
SCAN\_OUTPUT  
SCAN\_PARALLEL  
SCAN\_PARAMS  
THRESHOLD  
TSREPORT\_OPTIONS  
VOLUME\_LIMIT

### taskgroup Object Parameters

---

**Note:** For integrated backups, you can override many of the dump parameters for a particular filesystem by setting the parameters in other objects, as noted below. See:

- "Precedence of Objects for Integrated Backups" on page 154
  - "dumpgroup Object Parameters" on page 343
  - "filesystem Object Parameters" on page 351
  - "msp Object Parameters for a DCM MSP" on page 460.
- 

The taskgroup object parameters are as follows:

|                 |                                                                                                                                                                                                                                                                                                                                                         |
|-----------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| TYPE            | Specifies taskgroup (required name for this type of object). There is no default.                                                                                                                                                                                                                                                                       |
| ALERT_RETENTION | Specifies the age of alert records that are preferred to be kept when the run_remove_alerts.sh task is run. The run_remove_alerts.sh task uses but does not require this parameter. This parameter is evaluated only when run_remove_alerts.sh is run. Valid values are an integer followed by one of:<br><br>m[inutes]<br>h[ours]<br>d[ays]<br>w[eeks] |

---

**Note:** The set of records chosen for deletion is the union of the records that are older than the `ALERT_RETENTION` value and the oldest records when the database reaches the `MAX_ALERTDB_SIZE` threshold size:

- If you specify `ALERT_RETENTION` without `MAX_ALERTDB_SIZE`, older records will be deleted no matter how small the database is
  - If you specify `MAX_ALERTDB_SIZE` without `ALERT_RETENTION`, records will be kept no matter how old they are, so long as the database remains below the threshold size
  - If you specify neither parameter, no records will be deleted (and `REMALEERT_PARAMS` is ignored)
- 

|                                        |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|----------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>DATA_LIMIT</code>                | Specifies the maximum amount of data (in bytes) that should be selected for merging at one time. By default, there is no limit.                                                                                                                                                                                                                                                                                                                                                                                       |
| <code>DATABASE_COPIES</code>           | Specifies one or more directories into which the <code>run_copy_databases.sh</code> task will place a copy of the DMF databases. The <code>run_copy_databases.sh</code> task copies a snapshot of the current DMF databases to the directory with the oldest copy. If you specify multiple directories, you should spread the directories among multiple disk devices in order to minimize the chance of losing all copies of the databases. There is no default. This directory must not be in a managed filesystem. |
| <code>DMMIGRATE_MINIMUM_AGE</code>     | Specifies the value used for the <code>-m</code> option (in minutes) when <code>dmmigrate</code> is executed by the <code>run_dmmigrate.sh</code> task. The default is 10. For more information, see the <code>dmmigrate(8)</code> man page.                                                                                                                                                                                                                                                                          |
| <code>DMMIGRATE_MIN_OFFLINE_AGE</code> | Specifies the value used for the <code>-p</code> option (in minutes) when <code>dmmigrate</code> is executed by the <code>run_dmmigrate.sh</code> task. This value is a file's minimum age in order for its data blocks to be released, making the file offline. This value must be a positive                                                                                                                                                                                                                        |

|                                         |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
|-----------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                                         | <p>integer equal to or greater than the value of <code>DMMIGRATE_MINIMUM_AGE</code>. The default is to never release the data blocks. For more information, see the <code>dmigrate(8)</code> man page.</p>                                                                                                                                                                                                                                                                                                   |
| <code>DMMIGRATE_MIN_OFFLINE_SIZE</code> | <p>Specifies the value used for the <code>-s</code> option (in bytes) when <code>dmigrate</code> is executed by the <code>run_dmigrate.sh</code> task. This value is a file's minimum size in order for its data blocks to be released, making the file offline. By default, there is no size limit. The value may have a trailing scaling character. For more information, see the <code>dmigrate(8)</code> man page.</p>                                                                                   |
| <code>DMMIGRATE_QUEUE_MAX</code>        | <p>Specifies the maximum number of <code>dmigrate</code> requests that can be outstanding in the DMF daemon queue at any given time when <code>dmigrate</code> is executed by the <code>run_dmigrate.sh</code> task; when this threshold is reached, the command waits before issuing more requests. By default, the queue may contain 2 million <code>dmigrate</code> requests. The minimum is the <code>DMMIGRATE_UNACK</code> value (if specified), or else 1; the maximum is 2 billion (2000000000).</p> |
| <code>DMMIGRATE_TRICKLE</code>          | <p>Specifies the value used for the <code>-t</code> option when <code>dmigrate</code> is executed by the <code>run_dmigrate.sh</code> task. You can set this parameter to <code>ON</code> or <code>OFF</code>. The default is <code>ON</code>. For more information, see the <code>dmigrate(8)</code> man page.</p>                                                                                                                                                                                          |
| <code>DMMIGRATE_UNACK</code>            | <p>Specifies the value used for the <code>-r</code> option when <code>dmigrate</code> is executed by the <code>run_dmigrate.sh</code> task. Valid values are 1–200000, the default is 10. This parameter is valid only when <code>DMMIGRATE_TRICKLE</code> is set to <code>ON</code>. For more information, see the <code>dmigrate(8)</code> man page.</p>                                                                                                                                                   |
| <code>DMMIGRATE_VERBOSE</code>          | <p>Specifies the value used for the <code>-v</code> option when <code>dmigrate</code> is executed by the <code>run_dmigrate.sh</code> task. You can set this parameter to <code>ON</code> or <code>OFF</code>. The default is <code>OFF</code>. For more information, see the <code>dmigrate(8)</code> man page.</p>                                                                                                                                                                                         |
| <code>DMMIGRATE_WAIT</code>             | <p>Specifies the value used for the <code>-w</code> option when <code>dmigrate</code> is executed by the <code>run_dmigrate.sh</code></p>                                                                                                                                                                                                                                                                                                                                                                    |



task. You can set this parameter to ON or OFF. The default is OFF. For more information, see the `dmmigrate(8)` man page.

DRIVETAB

Provides the name of a file that is used with the `tsreport --drivetab` option, which causes the `run_daily_drive_report` and `run_daily_tsreport` output to contain the drive name instead of the device name, making the report more readable. By default, the device name is reported.

DUMP\_COMPRESS

*(disk and integrated backups only)* Specifies the compression type and level to be used when dumping the filesystems. The following values are accepted:

|                            |                                                                                                                            |
|----------------------------|----------------------------------------------------------------------------------------------------------------------------|
| OFF                        | No compression.                                                                                                            |
| ON                         | Equivalent to <code>gzip:1</code> (default).                                                                               |
| <code>gzip[:level]</code>  | Use <code>gzip(1)</code> with the specified compression level. If you do not specify <i>level</i> , a value of 1 is used.  |
| <code>bzip2[:level]</code> | Use <code>bzip2(1)</code> with the specified compression level. If you do not specify <i>level</i> , a value of 9 is used. |

For more information about legal values for *level*, see the man page for the compression tool.

For example, for a compression level of 3 with `bzip2`, you would use the following:

```
DUMP_COMPRESS      bzip2:3
```

---

**Note:** On backups consisting largely of migrated files, `gzip:1` (or ON) gives by far the best performance without sacrificing compression.

---

For integrated backups, the value set in a `dumpgroup` object or `filesystem` object overrides the value set here (the `dumpgroup` object has the highest precedence).

DUMP\_CONCURRENCY

*(disk and integrated backups only)* Specifies the maximum number of filesystems that will be backed up simultaneously. By default, there is no limit.

DUMP\_DESTINATION

*(disk and integrated backups only)* Specifies the directory in which to store backups, according to backup method:

- **Disk backup:** this directory must not be in a managed filesystem. If the filesystem is listed in `/etc/fstab` and is not mounted when backups or restores are started (using the `noauto` mount option), it will be mounted automatically for the duration of the operation; if the filesystem is on a COPAN RAID set, it must be a local filesystem and it will consume 1 unit from the power budget whenever it is mounted.

To ensure optimal dump performance for a disk backup, SGI recommends that the `DUMP_DESTINATION` directory is not in an NFS filesystem. However, if an NFS filesystem is required, you should set the `DUMP_WORKSPACE` parameter to a local filesystem that can hold the temporary files created during the dump process.

- **Integrated backups:** this directory must be the top-level directory (that is, not subdirectory) of a managed filesystem that is already mounted, and `USE_AS_DUMP_DEST` must be set to `ON` (see "filesystem Object Parameters" on page 351).

---

**Note:** Integrated backups are not normally used with COPAN massive array of idle disks (MAID). However, if the filesystem is on a COPAN RAID set, it must be a constantly mounted managed filesystem and it will consume 1 unit from the power budget.

---

|                        |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
|------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| DUMP_DEVICE            | <i>(tape backups only)</i> Specifies the name of the <code>drivegroup</code> or <code>device</code> object in the configuration file that defines how to mount the tapes that the backup tasks will use.                                                                                                                                                                                                                                                                                                            |
| DUMP_DR_EMAIL          | <i>(integrated backups only)</i> Specifies one or more email addresses to which the disaster-recovery (DR) bundle is sent.                                                                                                                                                                                                                                                                                                                                                                                          |
| DUMP_DR_EMAIL_MAX_SIZE | <i>(integrated backups only)</i> Specifies the maximum size of the DR bundle that will be attached to the email sent to the addresses specified by <code>DUMP_DR_EMAIL</code> . By default, there is no limit on the size of the bundle.                                                                                                                                                                                                                                                                            |
| DUMP_DR_MINIMAL        | <i>(integrated backups only)</i> Specifies whether or not the backup process produces a DR bundle of the smallest possible size. When set to <code>ON</code> , the bundle will contain only a dump of the <code>DUMP_DESTINATION</code> filesystem and the filesystem's metadata. When set to <code>OFF</code> (the default), the bundle will also include the configuration details and the XFS inventories. You can set this parameter to <code>ON</code> or <code>OFF</code> . The default is <code>OFF</code> . |
| DUMP_DR_MIRRORS        | <i>(integrated backups only)</i> Specifies one or more directories in which to place a copy of the DR bundle. This should be a remote filesystem accessible through passwordless <code>ssh</code> . After the initial copy is made to the <code>DUMP_DESTINATION</code> directory, a copy will be made in each of the disaster-recovery mirrors, specified with the following syntax:<br><br><code>[ user@ ] hostname : directoryname</code>                                                                        |

---

**Note:** For data security, SGI recommends that you do not specify a local directory.

---

For example:

```
admin@myhost : /usr/mirrorA
```

DMF transfers files by using SSH. You must set up SSH keys so that the local `root` user can log in to the remote host as a remote user without a password.

See the `ssh-keygen(1)` and `ssh-copy-id(1)` man pages for details. This parameter is required when using integrated backups.

DUMP\_FILE\_SYSTEMS

*(disk, tape, and integrated backups)* Specifies one or more filesystems to back up, according to the backup method:

- **Disk/tape backups:** Specifies one or more filesystems to back up. By default, the tasks will back up all of the managed filesystems configured in the configuration file. Use this parameter only if your site needs different backup policies (such as different backup times) for specific filesystems or wishes to back up filesystems that are not managed by DMF. It is safest not to specify this parameter and therefore back up all filesystems configured for management by DMF.
- **Integrated backups:** By default, the task will back up all of the managed filesystems. Use this parameter only if your site needs different backup policies (such as different compression type) for different filesystems or wishes to back up filesystems that are not managed by DMF. It is safest to exclude this parameter and therefore back up all filesystems configured for management by DMF. If DUMP\_GROUPS is configured but DUMP\_FILE\_SYSTEMS is not, only those filesystems defined by the DUMP\_FILE\_SYSTEMS parameters in the specified `dumpgroup` objects will be dumped; see "dumpgroup Object" on page 342.

For integrated backups, the value set in a `dumpgroup` object or `filesystem` object overrides the value set here (the `dumpgroup` object has the highest precedence).

DUMP\_FLUSH\_DCM\_FIRST

*(disk, tape, and integrated backups)* Specifies whether or not the `dmmigrate` command is run before dumping the filesystems specified. Running `dmmigrate` first ensures that all non-dual-resident files in the DCM MSP caches are migrated to a lower tier. If DUMP\_MIGRATE\_FIRST is also enabled, it is processed

|                     |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
|---------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| DUMP_GROUPS         | <p>first. You can set this parameter to ON or OFF. The default is ON. For integrated backups, the value set in an msp object for a DCM MSP overrides the value set here.</p> <p><i>(integrated backups only)</i> Specifies a list of dumpgroup objects separated by spaces. Each dumpgroup specifies one or more filesystems that should be dumped with specific characteristics that override the settings in this taskgroup object for any of the following parameters:</p> <p>DUMP_COMPRESS<br/>DUMP_MAX_FILESPACE<br/>DUMP_MIGRATE_FIRST<br/>DUMP_STREAMS<br/>DUMP_XFSDUMP_PARAMS</p> <p>See:</p> <ul style="list-style-type: none"><li>• "Precedence of Objects for Integrated Backups" on page 154</li><li>• "dumpgroup Object Parameters" on page 343</li></ul> |
| DUMP_INVENTORY_COPY | <p><i>(tape backups only)</i> Specifies the pathnames of one or more directories into which are copied the XFS inventory files for the backed-up filesystems. If you specify multiple directories, spreading the directories among multiple tape devices minimizes the chance of losing all copies of the inventory. The backup scripts choose the directory with the oldest inventory copy and copy the current one to it.</p> <hr/> <p><b>Note:</b> For disk backup, copies of the inventory are maintained in the directory specified by DUMP_DESTINATION.</p> <hr/>                                                                                                                                                                                                |
| DUMP_MAX_FILESPACE  | <p><i>(disk, tape, and integrated backups)</i> Specifies the maximum size of regular files to be included in a dump. (This limit does not apply to offline, dual-state, and partial-state files.) Regular files using more than this space are silently left out. This value applies to all filesystems being dumped except for the DMF</p>                                                                                                                                                                                                                                                                                                                                                                                                                            |

databases. The value is in bytes. You may also specify multiples of KB, MB, or GB by specifying a suffix of *k*, *m*, or *g*, respectively; however, DMF will round up the value to 1 KB if you provide a value that equates to less than 1 KB. If this parameter is not provided, there is no limit.

For integrated backups, the value set in a `dumpgroup` object or `filesystem` object overrides the value set here (the `dumpgroup` object has the highest precedence). **This parameter can be dangerous** because files are omitted silently and the limit applies to all of the filesystems specified by this object (which by default is all filesystems). Therefore SGI recommends that you set this limit only for specific filesystems.

When this parameter is defined, you must set the `UPDATE_CTIME` parameter to `ON` in the `filesystem` object if you want to use incremental dumps on managed filesystems; see "filesystem Object Parameters" on page 351.

`DUMP_MIGRATE_FIRST`

*(disk, tape, and integrated backups)* Specifies whether or not the `dmmigrate` command is run before dumping the filesystems. Running `dmmigrate` first ensures that all migratable files in the managed filesystems are migrated, thus reducing the amount of backup media space and making it run much faster. You can set this parameter to `ON` or `OFF`. The default is `ON`. For integrated backups, the value set in a `dumpgroup` object or `filesystem` object overrides the value set here (the `dumpgroup` object has the highest precedence).

`DUMP_MIRRORS`

*(disk and integrated backups only)* Specifies one or more directories in which to place a copy of the dumps. After the initial copy is made to the `DUMP_DESTINATION` directory, a copy will be made in each of the mirrors, which may be local or remote:

- A **local** directory is specified by beginning with a `'/'` character. If the filesystem containing this directory is listed in `/etc/fstab` and is not mounted when

mirroring begins, it will be mounted automatically for the duration of the mirror operation.

- A **remote** directory is specified with the following syntax:

```
[ user@ ] host : path
```

For example:

```
admin@myhost : /usr/mirrorA
```

DMF transfers files by using SSH. You must set up SSH keys so that the local `root` user can log in to the remote host as a remote user without a password. See the `ssh-keygen(1)` and `ssh-copy-id(1)` man pages for details.

If `DUMP_DESTINATION` is a managed filesystem configured with `USE_AS_DUMP_DEST` set to ON, the user is responsible for managing space in `DUMP_MIRRORS`.

`DUMP_MISC_LOCATIONS`

*(integrated backups only)* Specifies one or more full pathnames that must be included in the dump. The dumps of these files and directories are archived under the `DUMP_DESTINATION/misc` directory are migrated to volumes along with other dumps, but are not part of the DR bundle. (The `DUMP_DESTINATION/misc` directory and its contents are migrated like other files in the backup filesystem. The procedure to retrieve this directory is the same as the procedure to retrieve other filesystem dumps and DMF databases. See "Disaster Recovery Procedures" on page 650.)

`DUMP_POST_BACKUP_SCRIPT`

*(integrated backups only)* Specifies the full pathname to a user script that is run after the filesystem dumps, database snapshots, and so on are complete but just before the DR bundle is created. Hard links to files created by the dump process are placed under `DUMP_DESTINATION/current`. For example, you can use this script to store these files in a remote location, to place other files in the

*DUMP\_DESTINATION* filesystem, or to prune older files based on a custom dump-retention policy. However, you must manage the pruning of files that you explicitly add to the *DUMP\_DESTINATION* filesystem if those files are not included and managed by the dump process. Normally the dump sessions prune files in the following directories that are older than *DUMP\_RETENTION*:

```
configs
databases
filesystems
inventories
misc
```

If there are additional files or directories that are placed in *DUMP\_DESTINATION*, they are migrated during the dump session but are not pruned during the normal pruning process.

`DUMP_POST_DR_SCRIPT` (*integrated backups only*) Specifies the full pathname to a user script that is run just after the DR bundle is created. For example, you could use this script to transfer the DR bundle to one or more safe locations. The dump script calls *DUMP\_POST\_DR\_SCRIPT* with just one argument, which is the temporary location of the DR bundle. You can write your script accordingly if you want to put the DR bundle in a safe place using some mechanism other than `ssh` (such as using `ftp`).

`DUMP_PRE_BACKUP_SCRIPT` (*integrated backups only*) Specifies the full pathname to a user script that is run just before the backup is performed. For example, you can use this script to store user or administrative files in one of the dumped filesystems before the backup session begins.



## DUMP\_RETENTION

*(disk, tape, and integrated backups)* Specifies how long the filesystem backups will be kept before the tape or disk space is reused. This parameter is evaluated as follows:

- For tape backups, this parameter is evaluated after a successful **full** backup (but not after incremental backups). Also, if at the start of the backup process it is found that no tape is available, a prune is attempted in order to free tapes that are holding data older than the specified DUMP\_RETENTION period.
- For disk backups and integrated backups, this parameter is evaluated at the end of every full backup, every incremental backup, and every prune-only backup (a prune is attempted at the end of every partial or full backup).

You can specify this value as follows:

- As a single value, in which case all backups older than the value will be removed (supported for all methods)
- As a pair of minimum and maximum values (separated by a space), in which case backups will be kept for the minimum age and up to the maximum age as space permits (supported for disk backup only)

The `run_hard_deletes.sh`, `run_partial_dump.sh`, and `run_full_dump.sh` tasks require this parameter.

Valid values are an integer followed by one of:

m[inutes]  
h[ours]  
d[ays]  
w[EEKS]

## DUMP\_STREAMS

*(disk and integrated backups only)* Specifies the number of `xfsdump` streams (threads) to use when dumping a filesystem. Using multiple streams can reduce backup and restore times. The default is 1 and the maximum is 20. For integrated backups, the value set in a

|                     |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
|---------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                     | <p>dumpgroup object or filesystem object overrides the value set here (the dumpgroup object has the highest precedence).</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| DUMP_TAPES          | <p><i>(tape backups only)</i> Specifies the path of a file that contains tape volume serial numbers (VSNs), one per line, for the backup tasks to use. A VSN line in the specified file that begins with a comment character (#) is considered to be a temporarily disabled VSN that is unavailable for backups but whose <code>xfsdump</code> inventory records should be preserved if they exist. Any other text in the file after a comment character is considered to be a comment. For example, the file could contain the following:</p> <pre>VSN001 VSN002 # a comment  # the following VSN is temporarily disabled: # VSN003</pre> |
| DUMP_VSNS_USED      | <p><i>(tape backups only)</i> Specifies a file in which the VSNs of tapes that are used are written. By default, <code>/dev/null</code> is used, effectively disabling this feature.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
| DUMP_WORKSPACE      | <p><i>(disk and integrated backups only)</i> Specifies a local directory used to store temporary files created during a dump process before moving them to the <code>DUMP_DESTINATION</code> filesystem. SGI recommends that you set this parameter for a disk backup that uses an NFS filesystem as its <code>DUMP_DESTINATION</code> filesystem. (The <code>DUMP_WORKSPACE</code> parameter is not normally required for integrated backups, but could be used if you require a staging area to tune performance.)</p>                                                                                                                   |
| DUMP_XFSDUMP_PARAMS | <p><i>(disk, tape, and integrated backups)</i> Passes parameters to the <code>xfsdump</code> program. The value is not checked for validity, so you should use this parameter with care. Make sure that there are no conflicts with the <code>xfsdump</code> parameters generated by the DMF scripts. For integrated backups, the value set in a dumpgroup object or filesystem object overrides the value set here (the dumpgroup object has the highest precedence).</p>                                                                                                                                                                 |

---

`FILE_RETENTION_DAYS` (*fast-mount cache only*) Specifies the access age (in days) of a file that will be kept in the fast-mount cache during the process of freeing volumes. Files that have been accessed in fewer days will be moved onto another volume in the fast-mount cache. The `run_fmc_free.sh` task will use the `dmemptytape(8)` command to move those files into another volume within the fast-mount cache before completely freeing the full volume. By default, all files within the volume are deleted.

---

**Note:** Be aware of the following when specifying this parameter:

- There may be a significant performance impact on the `run_fmc_free.sh` task.
- If the `dmmove(8)` command is used to move files and if there is another simultaneous `dmmove` active that is using the same `MOVE_FS` directory, the two processes will compete for the same disk space without any knowledge of each other. The result is that each process may encounter unexpected `ENOSPACE` errors. You can use the `FMC_MOVEFS` parameter to minimize this problem.

---

`FMC_MOVEFS` (*fast-mount cache only*) Specifies the specific `MOVE_FS` scratch directory to be used by the `dmemptytape -f` option when moving files to another volume in the fast-mount cache, when required by the setting of `FILE_RETENTION_DAYS`. Also see `MOVE_FS` in "dmdaemon Object Parameters" on page 290.

`FMC_NAME` (*fast-mount cache only*) Specifies the name of the `fastmountcache` object. See "fastmountcache Object Parameters" on page 390.

`FREE_VOLUME_MINIMUM` (*fast-mount cache only*) Specifies the minimum percentage of free volumes in the fast-mount cache that must be available. When this threshold is reached, `run_fmc_free.sh` begins freeing full volumes in order to meet the percentage set for

|                    |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|--------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| FREE_VOLUME_TARGET | <p>FREE_VOLUME_TARGET. You should set FREE_VOLUME_MINIMUM so that it is less than the value for FREE_VOLUME_TARGET.</p> <p><i>(fast-mount cache only)</i> Specifies the percentage of free volumes in the fast-mount cache that run_fmc_free.sh will try to achieve when the FREE_VOLUME_MINIMUM threshold is reached.</p>                                                                                                                                                                                  |
| JOURNAL_RETENTION  | <p>Specifies the age of files that will be kept when the run_remove_journals.sh task removes journals. The run_remove_journals.sh task requires this parameter. This parameter is evaluated when run_remove_journals.sh is run. Valid values are an integer followed by one of:</p> <p>m[inutes]<br/>h[ours]<br/>d[ays]<br/>w[EEKS]</p> <p>You must specify a value that equates to at least seven days. (If you specify a value that equates to less time, DMF will round the value up to seven days.)</p> |
| LOG_RETENTION      | <p>Specifies the age of files that will be kept when the run_remove_logs.sh task is run. This parameter is evaluated when run_remove_logs.sh is run. Valid values are an integer followed by one of:</p> <p>m[inutes]<br/>h[ours]<br/>d[ays]<br/>w[EEKS]</p> <p>You must specify a value that equates to at least seven days. (If you specify a value that equates to less time, DMF will round the value up to seven days.)</p>                                                                            |
| MAX_ALERTDB_SIZE   | <p>Specifies the maximum size of the alerts database. The run_remove_alerts.sh task uses but does not require this parameter. For more information, see the <b>Note</b> under ALERT_RETENTION and "Restrict the Size of the Alerts and Performance Records Databases" on</p>                                                                                                                                                                                                                                |

---

|                  |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
|------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| MAX_PERFDB_SIZE  | <p>page 117. By default, the unit of measure is bytes; see "Units of Measure" on page 275.</p> <p>Specifies the maximum size of the performance database. For more information, see the <b>Note</b> under <code>PERF_RETENTION</code> and "Restrict the Size of the Alerts and Performance Records Databases" on page 117. By default, the unit of measure is bytes; see "Units of Measure" on page 275.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| PERF_RETENTION   | <p>Specifies the age of performance records that are preferred to be kept when the <code>run_remove_perf.sh</code> task is run. This parameter is evaluated when <code>run_remove_perf.sh</code> is run. This task uses but does not require this parameter. Valid values are an integer followed by one of:</p> <pre>m[inutes] h[ours] d[ays] w[eeks]</pre> <hr/> <p><b>Note:</b> The set of records chosen for deletion is the union of the records that are older than the <code>PERF_RETENTION</code> value and the oldest records when the database reaches the <code>MAX_PERFDB_SIZE</code> threshold size:</p> <ul style="list-style-type: none"> <li>• If you specify <code>PERF_RETENTION</code> without <code>MAX_ALERTDB_SIZE</code>, older records will be deleted no matter how small the database is</li> <li>• If you specify <code>MAX_PERFDB_SIZE</code> without <code>PERF_RETENTION</code>, records will be kept no matter how old they are, so long as the database remains below the threshold size</li> <li>• If you specify neither parameter, no records will be deleted (and <code>REMPERF_PARAMS</code> is ignored)</li> </ul> <hr/> <p><code>PERF_RETENTION</code> has no relationship to <code>METRICS_RETENTION</code>, the arena data, or PCP metrics.</p> |
| REMALEERT_PARAMS | <p>Specifies additional parameters to be executed by <code>run_remove_alerts.sh</code>. The only possible value is</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |

-V, which will remove unused space from the alerts database. By default, no space is removed.

---

**Note:** There is a performance penalty commensurate with the size of the reduction and other activity on the alerts database.

---

REMPERF\_PARAMS

Specifies additional parameters to be executed by `run_remove_perf.sh`. The only possible value is -V, which will remove unused space from the performance database. By default, no space is removed.

---

**Note:** There is a performance penalty commensurate with the size of the reduction and other activity on the alerts database.

---

RUN\_TASK

Specifies the tasks to be run. All of the `RUN_TASK` parameters have the same syntax in the configuration file:

```
RUN_TASK $ADMINDIR/task_name time_expression
```

The *task\_name* is the script to be executed.

The *time\_expression* defines when a task should be done. It is a schedule expression that the following form:

```
[every n period] [at hh:mm[:ss] ...] [on day ...]
```

*n* is an integer.

*period* is one of:

```
minute[s]  
hour[s]  
day[s]  
week[s]  
month[s]
```

*hh:mm:ss* is hour, minutes, seconds.

*day* is a day of the month (1 through 31) or day of the week (sunday through saturday).

The following are examples of valid time expressions:

```
at 2:00
at 1:00 on tuesday
every 5 minutes
every day at 1:00
```

---

**Note:** When using an expression that contains both an every and an at clause, the valid values for *period* in the every clause are `day[s]` or `week[s]`.

---

If you create your own scripts to be executed via the `RUN_TASK` parameter, be aware that DMF will equate `$ADMINDIR` to the appropriate directory, which is `/usr/lib/dmf`. When the task is run, DMF passes it the name of the object that requested the task and the name of the task group. The task itself may use the `dmconfig(8)` command to obtain further parameters from either of these objects.

You may comment-out the `RUN_TASK` parameters for any tasks you do not want to run.

`SCAN_FILESYSTEMS`

Specifies for the `run_filesystem_scan.sh` task the filesystems that `dmscanfs(8)` will scan. The default is to scan all managed filesystems.

`SCAN_FOR_DMSTAT`

Specifies for the `run_filesystem_scan.sh` task whether additional output files may be created (ON) or not (OFF). The default is ON.

If bit-file identifiers (BFIDs) and pathnames are included in the output file and `SCAN_FOR_DMSTAT` is enabled, an additional output file named `bfid2path` will be created in the daemon's `SPOOL_DIR` directory; this file is optimized for use by `dmstat(8)`.

If file handles and BFIDs are in the output file and `SCAN_FOR_DMSTAT` is enabled, an additional output file named `fhandle2bfid+path` will be created in the

|               |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |    |                                                        |               |                                                                                                                                      |     |                           |
|---------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----|--------------------------------------------------------|---------------|--------------------------------------------------------------------------------------------------------------------------------------|-----|---------------------------|
|               | daemon's <i>SPOOL_DIR</i> directory; this file is optimized for use by <i>dmemptytape(8)</i> .                                                                                                                                                                                                                                                                                                                                                                                                            |    |                                                        |               |                                                                                                                                      |     |                           |
| SCAN_OUTPUT   | <p>Specifies for the <i>run_filesystem_scan.sh</i> task the name of the file into which <i>dmscanfs</i> will place output. The default is <i>/tmp/dmcanfs.output</i>.</p> <p>This file, if it exists, is used by <i>run_daily_report.sh</i> and <i>dmstat(8)</i> and may be of use to site-written scripts or programs. Although DMF does not require this file, the output from <i>run_daily_report.sh</i> and <i>dmstat</i> will be incomplete if it is unavailable.</p>                                |    |                                                        |               |                                                                                                                                      |     |                           |
| SCAN_PARALLEL | <p>Specifies for the <i>run_filesystem_scan.sh</i> task whether <i>dmscanfs</i> will scan filesystems in parallel or not. You can specify one of the following:</p> <table><tr><td>ON</td><td>Enables parallel scanning on all available filesystems</td></tr><tr><td><i>number</i></td><td>Enables parallel scanning but limits the scan to the specified number of filesystems in order to reduce the load on system resources</td></tr><tr><td>OFF</td><td>Does not scan in parallel</td></tr></table> | ON | Enables parallel scanning on all available filesystems | <i>number</i> | Enables parallel scanning but limits the scan to the specified number of filesystems in order to reduce the load on system resources | OFF | Does not scan in parallel |
| ON            | Enables parallel scanning on all available filesystems                                                                                                                                                                                                                                                                                                                                                                                                                                                    |    |                                                        |               |                                                                                                                                      |     |                           |
| <i>number</i> | Enables parallel scanning but limits the scan to the specified number of filesystems in order to reduce the load on system resources                                                                                                                                                                                                                                                                                                                                                                      |    |                                                        |               |                                                                                                                                      |     |                           |
| OFF           | Does not scan in parallel                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |    |                                                        |               |                                                                                                                                      |     |                           |
|               | <hr/> <p><b>Note:</b> Enabling this parameter for a daemon task <i>taskgroup</i> may result in the filesystem scan completing in a shorter period of time, but it may also result in the task generating an unacceptable level of filesystem activity that interferes with user processes.</p> <hr/>                                                                                                                                                                                                      |    |                                                        |               |                                                                                                                                      |     |                           |
| SCAN_PARAMS   | <p>Specifies additional <i>dmscanfs</i> parameters for the <i>run_filesystem_scan.sh</i> task. By default, <i>dmscanfs</i> is run with the <i>-o stat</i> option, which is suitable for use with <i>run_daily_report.sh</i>. SGI recommends that you use the default unless you require pathnames in the output or plan to use the <i>dmstat(8)</i> or <i>dmemptytape(8)</i> commands (which</p>                                                                                                          |    |                                                        |               |                                                                                                                                      |     |                           |



require pathname for some operations); in these cases, SGI recommends that you set `SCAN_PARAMS` as follows:

```
SCAN_PARAMS      -o stat,path
```

If `SCAN_PARAMS` contains `-o all` or `-o path`, `dmscanfs` will do a recursive scan of the filesystems, which is much slower than the regular inode scan but results in pathnames being included in the output.

---

**Note:** SGI recommends that you do not specify the `-q` option (which suppresses the `dmscanfs` header line) as a value for `SCAN_PARAMS` because it makes the output file harder to parse with general-purpose scripts. The `run_daily_report.sh` task requires that this header line be present.

---

If BFIDs and pathnames are included in the output file and `SCAN_FOR_DMSTAT` is enabled, an additional output file named `bfid2path` will be created in the daemon's `SPOOL_DIR` directory. The `bfid2path` file is optimized for use by `dmstat(8)`.

THRESHOLD

Specifies the integer percentage of active data on a volume. DMF will consider a volume to be sparse when it has less than this percentage of data that is still active.

TSREPORT\_OPTIONS

Specifies for the `run_daily_tsreport.sh` task additional options that will be added to the end of the `tsreport` command line. For example, specifying `--host` will add an additional column with the hostname to the report. (This parameter is optional).

|              |                                                                                                                      |
|--------------|----------------------------------------------------------------------------------------------------------------------|
| VOLUME_LIMIT | Specifies the maximum number of volumes that can be selected for merging at one time. By default, there is no limit. |
|--------------|----------------------------------------------------------------------------------------------------------------------|

### taskgroup Object Examples

You can give the `taskgroup` object any name you like, but do not change the script names. You may comment-out the `RUN_TASK` parameters in the sample configuration files for any tasks you do not want to run. This section discusses the following:

- "taskgroup Object Example for Integrated Backups" on page 332
- "taskgroup Object Example for Tape Backups" on page 333
- "taskgroup Object Example for Disk Backups" on page 335
- "taskgroup Object Example for Disk Backups Using NFS"
- "taskgroup Object Example for Daemon Tasks" on page 336
- "taskgroup Object Example for Node Tasks" on page 339
- "taskgroup Object Example for Fast-Mount Cache Tasks" on page 339
- "taskgroup Object Example for Fast-Mount Cache Tasks Using File Retention" on page 340
- "taskgroup Object Example for Periodic `dmigrate` Tasks" on page 341
- "taskgroup Object Example for Removing Alerts and Performance Records" on page 341

### taskgroup Object Example for Integrated Backups

#### Example 7-9 taskgroup Object for Integrated Backups

```
define integrated_tasks
    TYPE                taskgroup
    RUN_TASK             $ADMINDIR/run_full_dump.sh on \
                        sunday at 00:01
    RUN_TASK             $ADMINDIR/run_partial_dump.sh on \
                        monday tuesday wednesday thursday \
                        friday saturday at 00:01
    RUN_TASK             $ADMINDIR/run_hard_deletes.sh \
```

```

                                at 23:00
DUMP_DESTINATION      /dmf_backups
DUMP_DR_MIRRORS       root@node1:/tmp/mymirrors
DUMP_DR_EMAIL         admin@company.com

enddef

```

In the above example:

- The name of this task group is `integrated_tasks`. This can be any name you like, but it must be the same as one of the names provided for the `TASK_GROUPS` parameter of the `dmdaemon` object. See Example 7-4 on page 293.
- The `RUN_TASK` tasks specify the following:
  - The `run_full_dump.sh` task runs a full backup of managed filesystems each week on Sunday morning one minute after midnight.
  - The `run_partial_dump.sh` task backs up only those files in managed filesystems that have changed since the time a full backup was completed and is run each day of the week except Sunday, at one minute after midnight.
  - The `run_hard_deletes.sh` task removes soft-deleted entries from the DMF databases after the backup-media retention period, in this case 4 weeks. For more information, see "Cleaning Up Obsolete Database Entries" on page 586.
- The `/dmf_backups` filesystem must have a `filesystem` object, because it must be a managed filesystem that is already mounted.
- The DR bundle will be sent to the `/tmp/mymirrors` location on the machine named `node1` and to the admin email address

## taskgroup Object Example for Tape Backups

### Example 7-10 taskgroup Object for Tape Backups

```

define  dump_tasks
        TYPE                taskgroup
        RUN_TASK             $ADMINDIR/run_full_dump.sh on \
                             sunday at 00:01
        RUN_TASK             $ADMINDIR/run_partial_dump.sh on \
                             monday tuesday wednesday thursday \
                             friday saturday at 00:01
        RUN_TASK             $ADMINDIR/run_hard_deletes.sh \

```

```
                                at 23:00
DUMP_TAPES                       HOME_DIR/tapes
DUMP_RETENTION                   4w
DUMP_DEVICE                      SILO_2
DUMP_MIGRATE_FIRST              on
DUMP_INVENTORY_COPY             /save/dump_inventory
endif
```

In the above example:

- The name of this task group is `dump_tasks`. This can be any name you like, but it must be the same as the name provided for the `TASK_GROUPS` parameter of the `dmdaemon` object. See Example 7-4 on page 293.
- The `RUN_TASK` tasks specify the following:
  - The `run_full_dump.sh` task runs a full backup of managed filesystems each week on Sunday morning one minute after midnight.
  - The `run_partial_dump.sh` task backs up only those files in managed filesystems that have changed since the time a full backup was completed and is run each day of the week except Sunday, at one minute after midnight.
  - The `run_hard_deletes.sh` task removes soft-deleted entries from the DMF databases after the backup-media retention period, in this case 4 weeks. For more information, see "Cleaning Up Obsolete Database Entries" on page 586.
- The other parameters determine how the data from the filesystem backups will be managed:
  - `HOME_DIR` is defined in the base object (see "base Object" on page 277). For example, if `HOME_DIR` is `/dmf/home`, then `DUMP_TAPES` would resolve to `/dmf/home/dump_tasks/tapes`.
  - The DG that defines how to mount the tapes is `SILO_2`
  - The `dmmigrate` command will be run before the backups are taken
  - The XFS inventory files will be copied into `/save/dump_inventory`

**taskgroup Object Example for Disk Backups****Example 7-11** taskgroup Object for Disk Backups

```

define dump_tasks
    TYPE                taskgroup
    RUN_TASK             $ADMINDIR/run_full_dump.sh on \
                        sunday at 00:01
    RUN_TASK             $ADMINDIR/run_partial_dump.sh on \
                        monday tuesday wednesday thursday \
                        friday saturday at 00:01
    RUN_TASK             $ADMINDIR/run_hard_deletes.sh \
                        at 23:00
    DUMP_DESTINATION    /dmf/backups
    DUMP_MIRRORS         /mirror1 user@remotehost:/mirror2
    DUMP_RETENTION      4w
    DUMP_MIGRATE_FIRST  yes
    DUMP_COMPRESS       yes
endef

```

The above example is similar to Example 7-10, page 333, except for the following:

- `DUMP_DESTINATION` rather than `DUMP_TAPES` specifies the location of the filesystem and database backup files. `/dmf/backups` must be a non-managed filesystem that is visible from the DMF server.
- Additional copies of the backup files will be placed in the following:
  - The `/mirror1` directory, which is visible to the DMF server.
  - The remote `mirror2` directory on the node named `remotehost`. The root user on the DMF server must be able to log in to `remotehost` as `user` using passwordless SSH.
- The backup files will be compressed using the default method (`gzip -l`).

**taskgroup Object Example for Disk Backups Using NFS****Example 7-12** taskgroup Object for Disk Backups Using NFS

```

define dump_tasks
    TYPE                taskgroup
    RUN_TASK             $ADMINDIR/run_full_dump.sh on \
                        sunday at 00:01

```

```

RUN_TASK          $ADMINDIR/run_partial_dump.sh on \
                  monday tuesday wednesday thursday \
                  friday saturday at 00:01
RUN_TASK          $ADMINDIR/run_hard_deletes.sh \
                  at 23:00
DUMP_DESTINATION /nfs/backups
DUMP_WORKSPACE   /dumtmp
DUMP_MIRRORS     /mirror1 user@remotehost:/mirror2
DUMP_RETENTION   4w
DUMP_MIGRATE_FIRST yes
DUMP_COMPRESS    yes
enddef

```

The above example is similar to Example 7-11, except that `DUMP_DESTINATION` is in an NFS filesystem, which requires that `DUMP_WORKSPACE` is set to a local filesystem in order to achieve best performance.

#### taskgroup Object Example for Daemon Tasks

##### Example 7-13 taskgroup Object for Daemon Tasks

```

define daemon_tasks
  TYPE          taskgroup
  RUN_TASK      $ADMINDIR/run_filesystem_scan.sh at 2:00
  RUN_TASK      $ADMINDIR/run_daily_report.sh at 3:00
  RUN_TASK      $ADMINDIR/run_daily_drive_report.sh at 4:00
  RUN_TASK      $ADMINDIR/run_audit.sh every day at 23:00
  RUN_TASK      $ADMINDIR/run_scan_logs.sh at 00:01
  RUN_TASK      $ADMINDIR/run_remove_logs.sh every \
                day at 1:00
  RUN_TASK      $ADMINDIR/run_daily_tsreport.sh every \
                day at 5:00
  LOG_RETENTION 4w
  RUN_TASK      $ADMINDIR/run_remove_journals.sh every \
                day at 1:00
  JOURNAL_RETENTION 4w
  RUN_TASK      $ADMINDIR/run_copy_databases.sh \
                every day at 3:00 12:00 21:00
  DATABASE_COPIES /save/dmf_home /alt/dmf_home
enddef

```

In the above example:

- The name of this task group is `daemon_tasks`. This can be any name you like, but it must be the same as the name provided for the `TASK_GROUPS` parameter of the `dmdaemon` object. See Example 7-4 on page 293.
- The tasks specify the following:
  - At 2:00 AM, the `run_filesystem_scan.sh` task runs `dmscanfs(8)` on all managed filesystems and writes the output to `/tmp/dmscanfs.output` (using the defaults for `SCAN_FILESYSTEMS` and `SCAN_OUTPUT` because they are not specified).

Because `SCAN_FOR_DMSTAT` (a misnomer) is not specified, its default value of `ON` means that the `fhandle2bfid+path` file will be created in the daemon's `SPOOL_DIR` directory because file handles and BFIDs are in the output file by default; however, the `bfid2path` file will not be created because by default pathnames are not included in the output file.

- At 3:00 AM, the `run_daily_report.sh` task reports on DCM MSPs and managed filesystems (if `run_filesystem_scan.sh` has been run recently) and on all LSs.
- At 4:00 AM, the `run_daily_drive_report.sh` task generates a report showing tape drives that have requested or required cleaning since the report was last run. If the time that the report was last run cannot be determined, or if this is the first time that the report was run, the reporting period is the previous 24 hours.

The report uses information that the program `dmtscopy` copies from files in `/var/spool/ts/pd/log` to the directory `SPOOL_DIR/tspdlogs`. Only events from files in `SPOOL_DIR/tspdlogs` are reported. Information is not reported from tape drives that are not used with `ts`.

- The `run_audit.sh` task runs `dmaudit` each day at 11:00 PM. If it detects any errors, the `run_audit.sh` task mails the errors to the e-mail address defined by the `ADMIN_EMAIL` parameter of the base object (described in "base Object" on page 277).
- The `run_scan_logs.sh` task scans the DMF log files for errors at 12:01 AM. If the task finds any errors, it sends e-mail to the e-mail address defined by the `ADMIN_EMAIL` parameter of the base object.

- At 1:00 A.M., the `run_remove_logs.sh` task will remove logs that are more than 4 weeks old.
- At 5:00 AM, the `run_daily_tsreport.sh` task generates a report containing the output of the `tsreport` command. The reporting period covers the time since the task was last run. If that cannot be determined, the reporting period is the previous 24 hours.

The report uses information that the program `dmtscopy` copies from files in `/var/spool/ts/pd/log` to the directory `SPOOL_DIR/tspdlogs`. Only events from files in `SPOOL_DIR/tspdlogs` are reported. Information is not reported from tape drives that are not used with `ts`.

The task uses the following options for the `tsreport` command:

```
--noverison
--options
--wide
--tapestats
--drivestats
--errors
--tapealert
--startdate
--starttime
```

- At 1:00 A.M. the `run_remove_journals.sh` task removes journals that are more than 4 weeks old.

---

**Note:** The `run_remove_journals.sh` and `run_remove_logs.sh` tasks are not limited to the daemon journals and logs; they also clear the journals and logs for MSPs/LSs.

---

- The `run_copy_databases.sh` task makes a copy of the DMF databases each day at 3:00 AM, 12:00 noon, and 9:00 PM. The task copies a snapshot of the current DMF databases to either `/save/dmf_home` or `/alt/dmf_home`, whichever contains the oldest copy. Integrity checks are done on the databases before the copy is saved. If the checks fail, the copy is not saved, and the task sends e-mail to the address defined by the `ADMIN_EMAIL` parameter of the base object.



**taskgroup Object Example for Node Tasks****Example 7-14** taskgroup Object for Node Tasks with Parallel DMF

```
define node_tasks
    TYPE                taskgroup
    RUN_TASK             $ADMINDIR/run_remove_logs.sh every day at 1:00
    LOG_RETENTION       4w
enddef
```

In the above example:

- The name of this task group is `node_tasks`. This can be any name you like, but it must be the same as the name provided for the `TASK_GROUPS` parameter of the `services` object. See "services Object" on page 299.
- Log files more than 4 weeks old are deleted each day at 1:00 A.M.

When using Parallel DMF, you should define the `run_remove_logs.sh` task for the `taskgroup` that applies to the `node` object rather than for the `taskgroup` that applies to the `dmdaemon` object.

---

**Note:** The `run_remove_logs.sh` task is the only task available for service objects.

---

**taskgroup Object Example for Fast-Mount Cache Tasks****Example 7-15** taskgroup Object for Fast-Mount Cache

```
define fmc_task
    TYPE                taskgroup
    RUN_TASK             $ADMINDIR/run_fmc_free.sh at 23:00
    FMC_NAME             copan_fmc
    FREE_VOLUME_MINIMUM 10
    FREE_VOLUME_TARGET   20
enddef
```

In the above example:

- The name of this task group is `fmc_task`. This can be any name you like, but it must be the same as the name provided for the `TASK_GROUPS` parameter of the `dmdaemon` object. See "dmdaemon Object" on page 289.

- The name of the fast-mount cache (`copan_fmc`) must match the name defined for the `fastmountcache` object. See "fastmountcache Object" on page 390.
- The `run_fmc_free.sh` task will be executed each day at 11:00 PM.
- When only 10% of the volumes in the fast-mount cache are free, DMF will free the volumes with the oldest write dates until 20% of the volumes are free.

### taskgroup Object Example for Fast-Mount Cache Tasks Using File Retention

#### Example 7-16 taskgroup Object for Fast-Mount Cache Using File Retention

```
define fmc_task
    TYPE                taskgroup
    RUN_TASK             $ADMINDIR/run_fmc_free.sh at 23:00
    FMC_NAME             copan_fmc
    FREE_VOLUME_MINIMUM 10
    FREE_VOLUME_TARGET  20
    FILE_RETENTION_DAYS 3
    FMC_MOVEFS           /dmf/copanmove
enddef
```

In the above example:

- The `run_fmc_free.sh` task will be executed at the same time and using the same minimum threshold and target as in Example 7-15, page 339.
- Before deleting the data from a given volume, DMF will determine if any files should be retained in the fast-mount cache. If a volume to be freed contains files that have been accessed within the last 3 days, DMF will first move those files to another volume within the VG.

---

**Note:** This may have a performance impact.

---

- If there are files that must be retained, the special scratch directory `/dmf/copanmove` will be used. This directory must be defined in the `MOVE_FS` parameter in the `dmdaemon` object. See "dmdaemon Object" on page 289.

**taskgroup Object Example for Periodic dmmigrate Tasks****Example 7-17** taskgroup Object for Periodic dmmigrate Example

```
define dmmigrate_task
    TYPE                taskgroup
    RUN_TASK             $ADMINDIR/run_dmmigrate.sh every 4 hours
    DMMIGRATE_MINIMUM_AGE 25
    DMMIGRATE_WAIT      ON
enddef
```

In the above example:

- The name of the task is `dmmigrate_task`. If this task is called from the `dmdaemon` object, it will process all filesystems defined with automated space-management or user space-management enabled. If it is called from a specific filesystem or DCM `mzp` object, it will migrate data from that object only.
- The `run_dmmigrate.sh` task will run every four hours.
- The minimum age of a file that will be migrated is 25 minutes.
- The task will wait for all migrations to complete before exiting.

**taskgroup Object Example for Removing Alerts and Performance Records****Example 7-18** taskgroup Object for Removing Alerts and Performance Records

```
define remove_task
    TYPE                taskgroup

    RUN_TASK             $ADMINDIR/run_remove_alerts.sh every day at 1:00
    ALERT_RETENTION      3w
    MAX_ALERTDB_SIZE     100m

    RUN_TASK             $ADMINDIR/run_remove_perf.sh every day at 2:00
    PERF_RETENTION       4w
    MAX_PERFDB_SIZE      150m
    REMPERF_PARAMS       -V

enddef
```

In the above example, two tasks will be run:

- `run_remove_alerts.sh` will be executed at 1:00 AM every day:
  - All alerts older than 3 weeks will be removed
  - If the alert database reaches 100 MB, the oldest records will be removed until the alert database is smaller than 100 MB
- `run_remove_perf.sh` will be executed at 2:00 AM every day:
  - All performance records older than 4 weeks will be removed
  - If the performance database reaches 150 MB, the oldest records will be removed until the performance database is smaller than 150 MB
  - The unused space in the performance database will be removed, despite the performance penalty

## **dumpgroup Object**

This section discusses the following:

- "dumpgroup Object Name" on page 342
- "dumpgroup Object Summary" on page 343
- "dumpgroup Object Parameters" on page 343
- "dumpgroup Object Example for Integrated Backups" on page 345

See also "Precedence of Objects for Integrated Backups" on page 154.

### **dumpgroup Object Name**

The name of the `dumpgroup` object is chosen by the administrator and may contain uppercase or lowercase alphanumeric characters or underscores. It cannot begin with an underscore or contain any white space.

## dumpgroup Object Summary

Following is a summary of the potential parameters for the `dumpgroup` object:

```
dumpgroup
    TYPE
    DUMP_COMPRESS
    DUMP_FILE_SYSTEMS
    DUMP_MAX_FILESPACE
    DUMP_MIGRATE_FIRST
    DUMP_STREAMS
    DUMP_XFSDUMP_PARAMS
```

## dumpgroup Object Parameters

---

**Note:** This stanza is used for only for integrated backups.

---

The setting of the dump parameters in the `dumpgroup` object overrides the value set by the `filesystem` object and `taskgroup` object for the specified filesystems. See "Precedence of Objects for Integrated Backups" on page 154.

| Parameter                 | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |     |                 |    |                                              |                           |                                                                                                                           |
|---------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----|-----------------|----|----------------------------------------------|---------------------------|---------------------------------------------------------------------------------------------------------------------------|
| TYPE                      | Specifies <code>dumpgroup</code> (required name for this type of object). There is no default.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |     |                 |    |                                              |                           |                                                                                                                           |
| DUMP_COMPRESS             | <p><i>(integrated-backup context only)</i> Specifies the compression type and level to be used when dumping the filesystems specified by this object, overriding the value set by the <code>filesystem</code> and <code>taskgroup</code> objects. The following values are accepted:</p> <table border="0"> <tr> <td>OFF</td> <td>No compression.</td> </tr> <tr> <td>ON</td> <td>Equivalent to <code>gzip:1</code> (default).</td> </tr> <tr> <td><code>gzip[:level]</code></td> <td>Use <code>gzip(1)</code> with the specified compression level. If you do not specify <i>level</i>, a value of 1 is used.</td> </tr> </table> | OFF | No compression. | ON | Equivalent to <code>gzip:1</code> (default). | <code>gzip[:level]</code> | Use <code>gzip(1)</code> with the specified compression level. If you do not specify <i>level</i> , a value of 1 is used. |
| OFF                       | No compression.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |     |                 |    |                                              |                           |                                                                                                                           |
| ON                        | Equivalent to <code>gzip:1</code> (default).                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |     |                 |    |                                              |                           |                                                                                                                           |
| <code>gzip[:level]</code> | Use <code>gzip(1)</code> with the specified compression level. If you do not specify <i>level</i> , a value of 1 is used.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |     |                 |    |                                              |                           |                                                                                                                           |

`bzip2[:level]` Use `bzip2(1)` with the specified compression level. If you do not specify *level*, a value of 9 is used.

For more information about legal values for *level*, see the man page for the compression tool.

For example, for a compression level of 3 with `bzip2`, you would use the following:

```
DUMP_COMPRESS      bzip2:3
```

---

**Note:** On backups consisting largely of migrated files, `gzip:1` (or `ON`) gives by far the best performance without sacrificing compression.

---

`DUMP_FILE_SYSTEMS`

*(integrated-backup context only)* Specifies one or more filesystems to dump using the parameter values supplied by this object, overriding the values set by the `filesystem` and `taskgroup` objects. This parameter is required for a `dumpgroup` object.

`DUMP_MAX_FILESPACE`

*(integrated-backup context only)* Specifies the maximum size of regular files to be included in a dump, overriding the value set for the `filesystem` and `taskgroup` objects. This limit does not apply to offline, dual-state, and partial-state files. Regular files using more than this space are silently left out of the backup. This value applies to all filesystems being dumped except for the DMF databases. The value is in bytes. You may also specify multiples of KB, MB, or GB by specifying a suffix of `k`, `m` or `g`, respectively; however, DMF will round up the value to 1 KB if you provide a value that equates to less than 1 KB. If this parameter is not provided, there is no limit.

**This parameter can be dangerous** because files are omitted silently and the limit applies to all of the filesystems specified by this object. Therefore SGI

recommends that you set this limit only for specific filesystems.

When this parameter is defined, you must set the `UPDATE_CTIME` parameter to `ON` in the `filesystem` object if you want to use incremental dumps for managed filesystems; see "filesystem Object Parameters" on page 351.

|                                  |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
|----------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>DUMP_MIGRATE_FIRST</code>  | <i>(integrated-backup context only)</i> Specifies whether or not the <code>dmmigrate</code> command is run before dumping the filesystems specified by this object, overriding the value set for the <code>filesystem</code> and <code>taskgroup</code> objects. Running <code>dmmigrate</code> first ensures that all migratable files in the managed filesystems are migrated, thus reducing the amount of backup media space and making it run much faster. You can set this parameter to <code>ON</code> or <code>OFF</code> . The default is <code>ON</code> . |
| <code>DUMP_STREAMS</code>        | <i>(integrated-backup context only)</i> Specifies the number of <code>xfsdump</code> streams (threads) to use when dumping the filesystems specified by this object, overriding the value set for the <code>filesystem</code> and <code>taskgroup</code> objects. Using multiple streams can reduce backup and restore times. The default is 1 and the maximum is 20.                                                                                                                                                                                               |
| <code>DUMP_XFSDUMP_PARAMS</code> | <i>(integrated-backup context only)</i> Passes parameters to the <code>xfsdump</code> program when dumping the filesystems specified by this object, overriding the value set for the <code>filesystem</code> and <code>taskgroup</code> objects. The value is not checked for validity, so you should use this parameter with care. Make sure that there are no conflicts with the <code>xfsdump</code> parameters generated by the DMF scripts.                                                                                                                   |

## dumpgroup Object Example for Integrated Backups

### Example 7-19 dumpgroup Object Example for Integrated Backups

```
define daemon
    TYPE                dmdaemon
    MIGRATION_LEVEL     auto
    LS_NAMES             ls
    TASK_GROUPS         daemon_tasks dump_tasks
```

## 7: DMF Configuration File

---

```
...
enddef

define dump_tasks
    TYPE                taskgroup
    RUN_TASK            $ADMINDIR/run_full_dump.sh on sunday at 00:00
    RUN_TASK            $ADMINDIR/run_partial_dump.sh \
                       on monday tuesday wednesday thursday \
                       friday saturday at 00:00
    RUN_TASK            $ADMINDIR/run_hard_deletes.sh at 22:00
    DUMP_DESTINATION   /dmf/backups
    DUMP_RETENTION     4w
    DUMP_COMPRESS      on
    DUMP_GROUPS        dgr_admin dgr_cache
    DUMP_FILE_SYSTEMS  /dmfusr1 /dmfusr2
enddef

define /dmfusr1
    TYPE                filesystem
    MIGRATION_LEVEL     auto
    DUMP_COMPRESS      gzip:1
    POLICIES            space_policy vg_policy
enddef

define dgr_admin
    TYPE                dumpgroup
    DUMP_FILE_SYSTEMS  /dmf/home /dmf/openvault
enddef

define dgr_cache
    TYPE                dumpgroup
    DUMP_FILE_SYSTEMS  /dmf/cache00
    DUMP_STREAMS       8
    DUMP_MAX_FILESPACE 1k
    UPDATE_CTIME       on
enddef
```

In the above example:



- The taskgroup named `dump_tasks` will run full and incremental backups on all of the managed filesystems
- The managed filesystems `/dmfusr1` and `/dmfusr2` as well as `/dmf/home`, `/dmf/openvault`, and `dmf/cache00` will be backed up because they are included in `DUMP_FILE_SYSTEMS` values in the `taskgroup` object and `dumpgroup` object

---

**Note:** The list of filesystems to be dumped is calculated as the union of the `DUMP_FILE_SYSTEMS` value in the `taskgroup` object and the `DUMP_FILE_SYSTEMS` value defined in each `dumpgroup` object that belongs to the `taskgroup`. If `DUMP_FILE_SYSTEMS` is defined in any object, only the explicitly-specified filesystems will be backed up; if `DUMP_FILE_SYSTEMS` is entirely absent from all objects, then all managed filesystems will be backed up by default.

---

- `dump_tasks` will use the default settings when dumping the managed filesystems, except for the following:
  - `/dmfusr`: the scripts will use a compression value of `gzip:1` and will dump files of any size
  - `/dmf/cache00`: regular files that exceed 1 KB will be excluded from the dump, and up to eight threads will be used when dumping the filesystem. This also requires that `UPDATE_CTIME` is enabled, to permit incremental backups of the managed filesystem.

## device Object

This section discusses the following:

- "device Object Name" on page 348
- "device Object Summary" on page 348
- "device Object Parameters" on page 348

### device Object Name

The name of the `device` object is chosen by the administrator and may contain uppercase or lowercase alphanumeric characters or underscores. It cannot begin with an underscore or contain any white space.

### device Object Summary

Following is a summary of the potential parameters for the `device` object:

```
device
      TYPE
      MOUNT_SERVICE
      MOUNT_SERVICE_GROUP
      OV_ACCESS_MODES
      OV_INTERCHANGE_MODES
      TMF_TMMNT_OPTIONS
```

### device Object Parameters

Normally, a `drivegroup` object defines the tape devices to be used by a `taskgroup` object (such as the example `dump_tasks`), with the LS and the backup scripts sharing the same devices. However, if backups are to use different drives from those in use by DMF, they should be defined by a `device` object. The parameters you define are based on the mounting service you intend to use.

| Parameter     | Description                                                                                                                                                                                                                                        |
|---------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| TYPE          | Specifies <code>device</code> (required name for this type of object). There is no default.                                                                                                                                                        |
| MOUNT_SERVICE | Specifies the mounting service. Possible values are <code>openvault</code> and <code>tmf</code> . You must use <code>openvault</code> for those DGs that contain tape drives on parallel data-mover nodes. The default is <code>openvault</code> . |

---

**Note:** TMF is not supported on systems running the Red Hat Enterprise Linux operating system.

---

|                      |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
|----------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| MOUNT_SERVICE_GROUP  | <p>Specifies the name by which the object's devices are known to the mounting service:</p> <ul style="list-style-type: none"> <li>• OpenVault: use the OpenVault drive group name that is listed by the <code>ov_drivegroup</code> command. See "Use Corresponding Drive-Group Names in OpenVault and DMF" on page 121.</li> <li>• TMF: use the device group name that would be used with the <code>-g</code> option on the <code>tmmt</code> command. (TMF is not supported on systems running the Red Hat Enterprise Linux operating system.)</li> </ul> <p>If this parameter is not specified, the <code>device</code> object's name is used.</p>                                                                                    |
| OV_ACCESS_MODES      | <p><i>(OpenVault only)</i> Specifies a list of access mode names that control how data is written to tape. For more information about the possible values, see the description of the <code>access</code> option in the <code>ov_mount(8)</code> man page.</p> <hr/> <p><b>Note:</b> <code>xfsdump</code> does not use this parameter.</p> <hr/>                                                                                                                                                                                                                                                                                                                                                                                        |
| OV_INTERCHANGE_MODES | <p><i>(OpenVault only)</i> Specifies a list of interchange mode values that control how data is written to secondary storage. This optional parameter is applied when a volume is mounted or rewritten. By default, this list is empty.</p> <p>Most drives support a value of either <code>compression</code> or <code>nocompression</code>.</p> <p>For example, to specify that you want data compressed, use:</p> <pre>OV_INTERCHANGE_MODES    compression</pre> <p>Some drives support additional values. For example, the T1000C drive also supports the additional values T1000C, T1000B, and T1000A. For example, if you have a mixture of T1000C and T1000B drives, you could use the following to tell the T1000C drives to</p> |

write in compressed T10000B format so that both drives can then later read the same cartridges:

```
OV_INTERCHANGE_MODES      compression T10000B
```

For more information about the possible values, see the description of the `firstmount` option in the `ov_mount(8)` man page.

TMF\_TMMNT\_OPTIONS

*(TMF only)* Specifies command options that should be added to the `tmmnt` command when mounting a tape. Because DMF uses the `-Z` option to `tmmnt`, options controlling block size and label parameters are ignored. Use `-g` if the group name is different from the device object's name. Use `-i` to request compression.

## filesystem Object

This section discusses the following:

- "filesystem Object Name" on page 350
- "filesystem Object Summary" on page 351
- "filesystem Object Parameters" on page 351
- "filesystem Object Examples" on page 360

See also "Precedence of Objects for Integrated Backups" on page 154.

### filesystem Object Name

The name of the `filesystem` object is the mount point. It may contain uppercase or lowercase alphanumeric characters, underscores, and the slash character (`/`). It cannot begin with an underscore or contain any white space.

---

**Note:** Do not use a symbolic link.

---

## filesystem Object Summary

Following is a summary of the potential parameters for the `filesystem` object:

```
filesystem
    TYPE
    BUFFERED_IO_SIZE
    DIRECT_IO_SIZE
    DUMP_COMPRESS
    DUMP_MAX_FILESPACE
    DUMP_MIGRATE_FIRST
    DUMP_STREAMS
    DUMP_XFSDUMP_PARAMS
    IMMUTABLE_BFIDS
    MAX_MANAGED_REGIONS
    MESSAGE_LEVEL
    MIGRATION_LEVEL
    MIN_ARCHIVE_SIZE
    MIN_DIRECT_SIZE
    POLICIES
    POSIX_FADVISE_SIZE
    RELEASETHREADS
    TASK_GROUPS
    UPDATE_CTIME
    USE_AS_DUMP_DEST
    USE_UNIFIED_BUFFER
```

## filesystem Object Parameters

You must have a `filesystem` object for each filesystem on which DMF can operate:

- A *managed filesystem* is a DMAPAPI-mounted XFS or CXFS filesystem on which DMF can migrate or recall files. (When using Parallel DMF, it must be a CXFS filesystem.) The object parameters specify the migration level for the filesystem, I/O options, and (if applicable) policies for MSP selection, file weighting, and automated space management.
- An *archive filesystem* is a POSIX filesystem (such as Lustre) that is not managed by DMF but from which you can efficiently copy files to secondary storage via the `dmarchive(1)` command. An archive filesystem does not support space management, migrations, or recalls. The `MIGRATION_LEVEL` parameter must be

set to `archive`. When using the Parallel DMF, such a filesystem should be mounted on the DMF server and all mover nodes.

---

**Note:** For integrated backups, the value set in the `dumpgroup` object overrides the value set here. See:

- "Precedence of Objects for Integrated Backups" on page 154
  - "dumpgroup Object Parameters" on page 343
- 

The `filesystem` object parameters are as follows:

| <b>Parameter</b>              | <b>Description</b>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|-------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>TYPE</code>             | Specifies <code>filesystem</code> (required name for this type of object). There is no default.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
| <code>BUFFERED_IO_SIZE</code> | Specifies the size of I/O requests when reading from or writing to this filesystem using buffered I/O. The legal range of values is 4096–16777216. The default is 262144. By default, the unit of measure is bytes; see "Units of Measure" on page 275. However, this parameter is ignored when recalling files if <code>USE_UNIFIED_BUFFER</code> is set to <code>ON</code> (which is the default).                                                                                                                                                                                                                     |
| <code>DIRECT_IO_SIZE</code>   | Specifies the size of I/O requests when reading from this filesystem using direct I/O. The legal range of values is 65536–18446744073709551615. The default value depends on the filesystem's configuration, but will not exceed the value of <code>DIRECT_IO_MAXIMUM_SIZE</code> defined in the <code>base</code> object (see "base Object" on page 277). By default, the unit of measure is bytes; see "Units of Measure" on page 275. This parameter is ignored if the filesystem does not support direct I/O. For more information about direct I/O, see <code>O_DIRECT</code> in the <code>open(2)</code> man page. |
| <code>DUMP_COMPRESS</code>    | <i>(integrated-backup context only)</i> Specifies the compression type and level to be used when dumping this filesystem, overriding the value set for the <code>taskgroup</code> object. The following values are accepted:<br><br><div style="display: flex; justify-content: space-between; margin-top: 10px;"> <span><code>OFF</code></span> <span>No compression.</span> </div>                                                                                                                                                                                                                                     |

|                            |                                                                                                                            |
|----------------------------|----------------------------------------------------------------------------------------------------------------------------|
| ON                         | Equivalent to <code>gzip:1</code> (default).                                                                               |
| <code>gzip[:level]</code>  | Use <code>gzip(1)</code> with the specified compression level. If you do not specify <i>level</i> , a value of 1 is used.  |
| <code>bzip2[:level]</code> | Use <code>bzip2(1)</code> with the specified compression level. If you do not specify <i>level</i> , a value of 9 is used. |

For more information about legal values for *level*, see the man page for the compression tool.

For example, for a compression level of 3 with `bzip2`, you would use the following:

```
DUMP_COMPRESS      bzip2:3
```

---

**Note:** On backups consisting largely of migrated files, `gzip:1` (or ON) gives by far the best performance without sacrificing compression.

---

For integrated backups, the value set in a `dumpgroup` object overrides the value set here.

DUMP\_MAX\_FILESPACE

*(integrated-backup context only)* Specifies the maximum size of regular files to be included when dumping this filesystem, overriding the value set for the `taskgroup` object. (This limit does not apply to offline, dual-state, and partial-state files.) Regular files using more than this space are silently left out of the backup. The value is in bytes. You may also specify multiples of KB, MB, or GB by specifying a suffix of `k`, `m`, or `g`, respectively; however, DMF will round up the value to 1 KB if you provide a value that equates to less than 1 KB. If this parameter is not provided, there is no limit.

When this parameter is defined, you must set the `UPDATE_CTIME` parameter to `ON` in the `filesystem` object if you want to use incremental dumps; see "filesystem Object Parameters" on page 351.

For integrated backups, the value set in a `dumpgroup` object overrides the value set here. This parameter can be dangerous because files are omitted silently.

|                                  |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
|----------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>DUMP_MIGRATE_FIRST</code>  | <i>(integrated-backup context only)</i> Specifies whether or not the <code>dmigrate</code> command is run before dumping this filesystem, overriding the value set for the <code>taskgroup</code> object. Running <code>dmigrate</code> first ensures that all migratable files in the managed filesystem are migrated, thus reducing the amount of backup media space and making it run much faster. You can set this parameter to <code>ON</code> or <code>OFF</code> . The default is <code>ON</code> . For integrated backups, the value set in a <code>dumpgroup</code> object overrides the value set here. |
| <code>DUMP_STREAMS</code>        | <i>(integrated-backup context only)</i> Specifies the number of <code>xfsdump</code> streams (threads) to use when dumping this filesystem, overriding the value set for the <code>taskgroup</code> object. Using multiple streams can reduce backup and restore times. The default is 1 and the maximum is 20. For integrated backups, the value set in a <code>dumpgroup</code> object overrides the value set here.                                                                                                                                                                                            |
| <code>DUMP_XFSDUMP_PARAMS</code> | <i>(integrated-backup context only)</i> Passes parameters to the <code>xfsdump</code> program when dumping this filesystem, overriding the value set for the <code>taskgroup</code> object. The value is not checked for validity, so you should use this parameter with care. Make sure that there are no conflicts with the <code>xfsdump</code> parameters generated by the DMF scripts. For integrated backups, the value set in a <code>dumpgroup</code> object overrides the value set here.                                                                                                                |
| <code>IMMUTABLE_BFIDS</code>     | Specifies whether or not DMF should restrict operations that change the BFIDs of the migrated files in this filesystem. When enabled, the DMF daemon will reject <code>dmunput</code> and <code>dmmtree</code> requests related to this filesystem. (It is possible for BFIDs to change, however, if you use the <code>dmaudit</code> command to correct cases of                                                                                                                                                                                                                                                 |



multiple files with the same BFID.) You can set this parameter to `ON` or `OFF`. The default is `OFF` (disables). You must set this parameter to `ON` if you are using a product that stores BFIDs externally to DMF, such as Arcitecta Mediaflux; in that case, see the product documentation for how to use this parameter and `dmaudit`.

`MAX_MANAGED_REGIONS`

Sets the maximum number of managed regions that DMF will assign to a file in this filesystem. You can set `MAX_MANAGED_REGIONS` to any number that is less than the actual number of regions that will fit in the filesystem attribute. For a XFS or CXFS filesystem, that number is 3275.

By default, DMF allows a DMF attribute to contain the maximum number of managed regions that will still allow the attribute to fit completely inside the inode, based on inode size and `attr` type. The default value for a `filesystem` object that does not have a `MAX_MANAGED_REGIONS` parameter is calculated at filesystem mount time. This value is chosen to ensure that the DMF attribute will fit inside the inode, assuming that no other attribute (such as an ACL) is already occupying the inode's attribute space. Table 5-1 on page 172, lists the default maximum file regions. This parameter does not apply to a filesystem with a `MIGRATION_LEVEL` of `archive`.



---

**Caution:** You should use `MAX_MANAGED_REGIONS` cautiously. If you set this parameter to a value that is larger than the default maximum (see Table 5-1 on page 172), the DMF attribute may not fit inside the inode. If there are many files with DMF attributes outside of the inode, filesystem scan times can increase greatly. To avoid this problem, SGI recommends that a file that has exceeded the maximum default file regions be made offline (that is, having a single region) as soon as possible after the online data has been accessed.

---

|                  |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| MESSAGE_LEVEL    | <p>Specifies the highest message level that will be written to the automated space-management log (<code>autolog</code>). It must be an integer in the range 0-6; the higher the number, the more messages written to the log file. The default is 2. This parameter applies only to a filesystem with a <code>MIGRATION_LEVEL</code> of <code>auto</code>. For more information on message levels, see Chapter 10, "Message Log Files" on page 507.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| MIGRATION_LEVEL  | <p>Specifies the level of migration services for this filesystem. (Recall from offline media is not affected by the value of <code>MIGRATION_LEVEL</code>.) Valid values are:</p> <ul style="list-style-type: none"><li>• <code>archive</code> (only for DMF direct archiving via the <code>dmarchive</code> command)</li><li>• <code>auto</code> (automated space management)</li><li>• <code>none</code> (no migration)</li><li>• <code>user</code> (only user-initiated migration using the <code>dmput</code> or <code>dmmigrate</code> commands)</li></ul> <p>The migration level actually used for this filesystem is the lesser of the <code>MIGRATION_LEVEL</code> value for the <code>dmdaemon</code> object and this value. If you do not want automated space-management for a filesystem, set <code>MIGRATION_LEVEL</code> to <code>user</code> or <code>none</code>. The default is <code>auto</code>.</p> <p>When using Parallel DMF, a managed filesystem (that is, a filesystem where DMF can migrate or recall files) must be a CXFS filesystem.</p> |
| MIN_ARCHIVE_SIZE | <p>Specifies the minimum file size required for the <code>dmarchive</code> command to copy data directly between an archive filesystem and DMF secondary storage. Files smaller than this size will instead be copied between the archive filesystem and a managed filesystem before being possibly migrated or recalled from DMF secondary storage. The legal range of values is 1-18446744073709551615. The default is 1 (meaning that all files will be copied directly to secondary storage with only metadata going to the</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |

---

|                    |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|--------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| MIN_DIRECT_SIZE    | <p>managed filesystem). By default, the unit of measure is bytes; see "Units of Measure" on page 275. This parameter applies only to a filesystem with a <code>MIGRATION_LEVEL</code> value of <code>archive</code>.</p> <p>Determines whether direct or buffered I/O is used when reading from this filesystem. If the number of bytes to be read is smaller than the value specified, buffered I/O is used; otherwise, direct I/O is used. The legal range of values is 0 (direct I/O is always used) through 18446744073709551615 (direct I/O is never used). The default is 0. By default, the unit of measure is bytes; see "Units of Measure" on page 275. This parameter is ignored if the filesystem does not support direct I/O or is a real-time filesystem. For more information about direct I/O, see <code>O_DIRECT</code> in the <code>open(2)</code> man page.</p> <hr/> <p><b>Note:</b> Buffered I/O is always used when writing to a filesystem.</p> <hr/> |
| POLICIES           | <p>Specifies the names of the configuration objects defining policies for this filesystem. Policies are defined with <code>policy</code> objects (see "policy Object"). The <code>POLICIES</code> parameter is required; there is no default value. A policy can be unique to each managed filesystem or it can be reused numerous times. This parameter does not apply to a filesystem with a <code>MIGRATION_LEVEL</code> of <code>archive</code>.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
| POSIX_FADVISE_SIZE | <p>Specifies the number of bytes after which DMF will call <code>posix_fadvise()</code> with advice <code>POSIX_FADV_DONTNEED</code> when recalling files. The minimum is 0, which means that <code>posix_fadvise</code> is never used. The maximum is 18446744073709551615. The default is 100000000, which will call <code>posix_fadvise</code> after each 100,000,000 bytes (approximately) it has written to the file. By default, the unit of measure is bytes; see "Units of Measure" on page 275. If you notice performance problems when recalling files, changing this value may</p>                                                                                                                                                                                                                                                                                                                                                                               |

make an improvement, but this will require testing; see "Poor Recall Performance" on page 669.

DMF does not synchronize the file at this point. If `POSIX_FADVISE_SIZE` is set to a nonzero value, DMF will also call `posix_fadvise` when a region is made online.

---

**Note:** Setting this parameter to a small, nonzero value may have an adverse affect on performance. See the `posix_fadvise(2)` man page for more information.

---

|                             |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
|-----------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>RELEASETHREADS</code> | Specifies the number of threads in the DMF daemon that will be created to handle requests to release filesystem blocks when files are made offline ( <code>OFL</code> ). The default and minimum value is 1. The maximum value is 20. This parameter does not apply to filesystems with a <code>MIGRATION_LEVEL</code> of <code>archive</code> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
| <code>TASK_GROUPS</code>    | Names the <code>taskgroup</code> objects that contain tasks the daemon should run when <code>MIGRATION_LEVEL</code> is set to <code>auto</code> . By default, no tasks are run.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
| <code>UPDATE_CTIME</code>   | <p>Specifies whether or not the <code>st_ctime</code> value of files in this filesystem should be changed when certain operations are performed. (For more information about <code>st_ctime</code>, see the <code>stat(2)</code> man page.) If set to <code>ON</code>, DMF will update the <code>st_ctime</code> value of a file under the following circumstances:</p> <ul style="list-style-type: none"><li>• When the file transitions from a migrating state (<code>MIG</code> or <code>ARC</code>) to a migrated state (<code>DUL</code>, <code>PAR</code>, or <code>OFL</code>)</li><li>• When the file transitions from a migrated state or a migrating state to regular state (<code>REG</code>)</li><li>• When the file's <code>sitetag</code> value changes (for more information, see the <code>dmtag(1)</code> man page)</li></ul> <p>You should set this parameter to <code>ON</code> if you have defined <code>DUMP_MAX_FILESPACE</code> and wish to perform incremental backups. See:</p> |

- "dumpgroup Object Parameters" on page 343
- "filesystem Object Parameters" on page 351
- "taskgroup Object Parameters" on page 312
- "DUMP\_MAX\_FILESPACE Requires UPDATE\_CTIME for Incremental Backups" on page 148

This parameter is valid only on managed filesystems. You can set this parameter to ON or OFF. The default is OFF.

USE\_AS\_DUMP\_DEST

*(integrated backups only)* Determines if this filesystem can be used for storing dumps. The value can be one of the following:

- ON, which means that DMF can be configured in a taskgroup object to use this filesystem for storing dumps. You can set this parameter to ON for only one filesystem object in the DMF configuration. This filesystem should not be used for holding ordinary user data and SGI recommends that the MIGRATION\_LEVEL value for this filesystem is set to auto.
- OFF, which means that DMF will not use this filesystem for storing dumps and therefore you cannot configure this filesystem as a DUMP\_DESTINATION value in any dump taskgroup. The default setting is OFF.

USE\_UNIFIED\_BUFFER

Determines how DMF manages its buffers when recalling files in this filesystem. The value can be one of the following:

- ON, which means that DMF will use the same buffer for reading and writing and BUFFERED\_IO\_SIZE is ignored when recalling files. Setting the value to ON will cause the size of I/O requests to be small when recalling data from a cloud, DCM, disk, or FTP MSP. The default setting is ON.
- OFF, which means that DMF uses separate buffers for reading and writing during recall. That is, DMF reads data from its backing store (such as tape) into a buffer and then copies the data into another buffer for writing. An additional thread for writing is also used.

## **filesystem Object Examples**

This section discusses the following examples:

- "filesystem Object Example for a Managed Filesystem" on page 361
- "filesystem Object Example for Integrated Backups" on page 362
- "filesystem Object Example for Incremental Backups that Restrict File Size" on page 362
- "filesystem Object for DMF Direct Archiving" on page 363

### filesystem Object Example for a Managed Filesystem

Example 7-20 defines a `filesystem` object named `/user1` using default values except as noted.

#### Example 7-20 `filesystem` Object for a Managed Filesystem

```
define /user1
    TYPE                filesystem
    MIGRATION_LEVEL     user
    POLICIES            fs_msp
enddef
```

In the above example:

- The `define` parameter must have a value that is the mount point of the filesystem you want DMF to manage, in this case `/user1`. Do not use a symbolic link.
- Only user-initiated migration will be used for migration to offline media.
- The migration policy is set by the `policy` object named `fs_msp`. See "policy Object" on page 364.
- The example uses the default value for the following parameters, which also apply to a `filesystem` object for a managed filesystem:

```
BUFFERED_IO_SIZE
DIRECT_IO_SIZE
MAX_MANAGED_REGIONS
MESSAGE_LEVEL
MIN_DIRECT_SIZE
POSIX_FADVISE_SIZE
TASK_GROUPS
USE_UNIFIED_BUFFER
```

**filesystem Object Example for Integrated Backups**

Example 7-21 defines a `filesystem` object that will be used for integrated backups.

**Example 7-21** `filesystem` Object for Integrated Backups

```
define /dmf/backups
    TYPE                filesystem
    MIGRATION_LEVEL     auto
    POLICIES             backup_space_policy backup_vg_policy
    USE_AS_DUMP_DEST    on
enddef
```

In the above example:

- The `define` parameter must have a value that is the mount point of the filesystem you want to use for backups, in this case `/dmf/backups`. Do not use a symbolic link.
- Automatic migration will be used.
- The migration policy is set by the `policy` objects named `backup_space_policy` and `backup_vg_policy`. `backup_vg_policy` should include at least two VGs to which data from this filesystem will be migrated . See "policy Object" on page 364.
- This filesystem can be configured as a `DUMP_DESTINATION` for an `integrated-backup taskgroup` object. DMF will then use this filesystem for storing dumps.

**filesystem Object Example for Incremental Backups that Restrict File Size**

Example 7-22 defines three `filesystem` objects in a configuration that uses incremental backups. As an illustration, the objects for `/user1` and `/user2` restrict the size of regular files included in the dumps in order to make the backup completion times more consistent.

**Example 7-22** `filesystem` Objects for Incremental Backups that Restrict File Size

```
define /user1
    TYPE                filesystem
    MIGRATION_LEVEL     user
    POLICIES             backup_space_policy backup_vg_policy
```



```
        DUMP_MAX_FILESPACE      1k
        UPDATE_CTIME            on
    endif

define /user2
    TYPE                        filesystem
    MIGRATION_LEVEL             user
    POLICIES                     backup_space_policy backup_vg_policy
    DUMP_MAX_FILESPACE          1k
    UPDATE_CTIME                on
    endif

define /user3
    TYPE                        filesystem
    MIGRATION_LEVEL             user
    POLICIES                     backup_space_policy backup_vg_policy
    endif
```

The above example is similar to previous examples, except for the following:

- Regular files that exceed 1 KB will be excluded from the dumps for /user1 and /user2 (no regular files will be excluded for /user3).
- The `st_ctime` value will be changed on /user1 and /user2 when certain operations are performed, as described in "filesystem Object Parameters" on page 351. This allows the `run_partial_dump.sh` script to perform incremental backups and ensures that the regular files in those filesystems will not be missed. (`UPDATE_CTIME` does not need to be set for /user3 because its object does not have `DUMP_MAX_FILESPACE` set.)

---

**Note:** If `UPDATE_CTIME` was **not set** for the /user1 and /user2 objects, then `run_partial_dump.sh` would always perform full (level-0) backups for those managed filesystems.

---

### filesystem Object for DMF Direct Archiving

Example 7-23 defines a `filesystem` object for an archive filesystem named /lustrefs, using default values except as noted:

**Example 7-23** filesystem Object for DMF Direct Archiving

```
define /lustrefs
    TYPE                filesystem
    MIGRATION_LEVEL     archive
    MIN_ARCHIVE_SIZE    262144
enddef
```

In the above example:

- The `define` parameter must have a value that is the mount point of the archive filesystem, in this case `/lustrefs`. Do not use a symbolic link.
- File data in `/lustrefs` can be copied directly to secondary storage by users via the `dmarchive(1)` command.
- Files that are smaller than 262,144 bytes are never archived via `dmarchive` but instead will be copied to a managed filesystem before being possibly migrated or recalled from DMF secondary storage.
- The example uses the default value for the following parameters, which also apply to a `filesystem` object for DMF direct archiving:

```
BUFFERED_IO_SIZE
DIRECT_IO_SIZE
MIN_DIRECT_SIZE
POSIX_FADVISE_SIZE
USE_UNIFIED_BUFFER
```

## policy Object

This section discusses the following:

- "Functions of `policy` Parameters" on page 365
- "Rules for `policy` Parameters" on page 366
- "`policy` Object Name" on page 368
- "Managed Filesystem `policy` Parameters" on page 368
- "DCM MSP `STORE_DIRECTORY` `policy` Parameters" on page 375
- "when Clause" on page 380

- "ranges Clause" on page 383
- "policy Configuration Examples" on page 385

## Functions of policy Parameters

A policy object specifies behavior for managing the following:

- A managed filesystem
- A DCM STORE\_DIRECTORY

The policy object parameters specify the following functions:

- "Automated Space-Management Overview" on page 365
- "File Weighting Overview" on page 365
- "MSP/VG Selection Overview" on page 366

For details about the parameters, see:

- "Managed Filesystem policy Parameters" on page 368
- "DCM MSP STORE\_DIRECTORY policy Parameters" on page 375

## Automated Space-Management Overview

DMF lets you automatically monitor filesystems and migrate data as needed to prevent filesystems from filling. This capability is implemented by the `dmfsmon(8)` daemon. After the `dmfsmon` daemon has been initiated, it will begin to monitor the managed filesystem in order to maintain the level of free space specified in the configuration file.

---

**Note:** Ideal values for these parameters are highly site-specific, based largely on filesystem sizes and typical file sizes.

---

## File Weighting Overview

When DMF is conducting automated space management, it derives an ordered list of files (called a *candidate list*) and migrates or frees files starting at the top of the list. The ordering of the candidate list is determined by weighting factors that are defined by parameters in the configuration file. You can use the file weighting parameters

multiple times to specify that different files should have different weights. For more details, see Chapter 11, "Automated Space Management" on page 509.

### MSP/VG Selection Overview

DMF can be configured to have many MSPs/VGs, including those specified in an MG (see "migrategroup Object" on page 426).

Each MSP/VG manages its own set of volumes. The MSP/VG selection parameters let you migrate files with different characteristics to different MSPs/VGs. You can use the MSP/VG selection parameters multiple times to specify that different files should have different MSP/VG selection values.

### Rules for policy Parameters

This section discusses the following:

- "Managed Filesystem Rules" on page 366
- "DCM MSP STORE\_DIRECTORY Rules" on page 367

### Managed Filesystem Rules

The rules for a `policy` object that is migrating a managed filesystem are as follows:

- The `POLICIES` parameter for a `filesystem` object must specify one and only one MSP/VG selection policy.
- The `TYPE` parameter is required for any `policy` object:

| Parameter | Description |
|-----------|-------------|
|-----------|-------------|

|                   |                                                                                             |
|-------------------|---------------------------------------------------------------------------------------------|
| <code>TYPE</code> | Specifies <code>policy</code> (required name for this type of object). There is no default. |
|-------------------|---------------------------------------------------------------------------------------------|

- If the `MIGRATION_LEVEL` parameter for a `filesystem` object is `auto`, the `POLICIES` parameter for that object must specify one and only one space-management policy.
- You do not need to specify a weighting policy if the default values are acceptable.

- Providing the above rules are followed, you can have many different combinations of policies. For example, you could configure one policy that defines all three categories of policy parameters (automated space management, MSP/VG selection, and file weighting) and share that policy among all the filesystems, or you could configure any number of individual MSP/VG selection policies and space-management policies (including weighting parameters) that you can apply to one or more filesystems.

### DCM MSP STORE\_DIRECTORY Rules

The rules for a `policy` object that is managing a `DCM MSP STORE_DIRECTORY` are as follows:

- The `TYPE` parameter is required for any `policy` object:

| Parameter | Description |
|-----------|-------------|
|-----------|-------------|

|                   |                                                                                             |
|-------------------|---------------------------------------------------------------------------------------------|
| <code>TYPE</code> | Specifies <code>policy</code> (required name for this type of object). There is no default. |
|-------------------|---------------------------------------------------------------------------------------------|

- If the `MIGRATION_LEVEL` for a `filesystem` object is `auto`, the `POLICIES` parameter for that object must specify one and only one space-management policy.
- You do not need to specify a weighting policy if the default values are acceptable.
- You can configure one policy that defines all three categories of policy parameters (automated space management, file weighting, and VG selection) and share that policy among all the filesystems. Alternatively, you might create a VG selection policy for all filesystems and a space-management policy (including weighting parameters) for all filesystems.
- The DCM MSP supports the concept of *dual-residence*, which means that a cache-resident copy of a migrated file has already been copied to secondary storage and can therefore be released quickly in order to prevent the cache filling, without any need to first copy it to secondary storage. It is analogous to a dual-state file that is managed by the standard disk MSP and has equivalent policy parameters to control it.
- The age and space weighting parameters refer to the copies in the cache, not the originals in the managed filesystem.

## policy Object Name

The name of the `policy` object is chosen by the administrator and may contain uppercase or lowercase alphanumeric characters or underscores. It cannot begin with an underscore or contain any white space.

## Managed Filesystem policy Parameters

This section discusses the following:

- "policy Object Summary for a Managed Filesystem" on page 368
- "Automated Space-Management Parameters for a Managed Filesystem" on page 369
- "File Weighting Parameters for a Managed Filesystem" on page 371
- "MSP/VG Selection Parameters for a Managed Filesystem" on page 374

## policy Object Summary for a Managed Filesystem

Following is a summary of the potential parameters for the `policy` object for a managed filesystem:

```
policy
    TYPE
    AGE_WEIGHT
    FREE_DUALSTATE_FIRST
    FREE_SPACE_DECREMENT
    FREE_SPACE_MINIMUM
    FREE_SPACE_TARGET
    MIGRATION_TARGET
    SELECT_MSP or SELECT_VG
    SITE_SCRIPT
    SPACE_WEIGHT
```

For details, see:

- "Automated Space-Management Parameters for a Managed Filesystem" on page 369
- "File Weighting Parameters for a Managed Filesystem" on page 371
- "MSP/VG Selection Parameters for a Managed Filesystem" on page 374

## Automated Space-Management Parameters for a Managed Filesystem


The following parameters control automated space management for a managed filesystem:

| Parameter                         | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
|-----------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>FREE_DUALSTATE_FIRST</code> | When set to <code>ON</code> , specifies that <code>dmfsfree</code> will first free dual-state and partial-state files before freeing files it must migrate. The default is <code>OFF</code> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
| <code>FREE_SPACE_DECREMENT</code> | Specifies the integer percentage of filesystem space by which <code>dmfsmon</code> or <code>dmdskmsp</code> will decrement <code>FREE_SPACE_MINIMUM</code> if it cannot find enough files to migrate so that the value is reached. The decrement is applied until a value is found that can be achieved. If space later frees up, the <code>FREE_SPACE_MINIMUM</code> is reset to its original value. Valid values are in the range 1 through the value of <code>FREE_SPACE_TARGET</code> . The default is 2.                                                                                                                                                                                                                         |
| <code>FREE_SPACE_MINIMUM</code>   | Specifies the minimum integer percentage of the total filesystem space that <code>dmfsmon</code> tries to maintain as free. When the available free space reaches or falls below this threshold value, <code>dmfsmon</code> will begin to migrate files (freeing data for dual-state files as needed) in order to meet the percentages set for <code>FREE_SPACE_MINIMUM</code> , <code>FREE_SPACE_TARGET</code> , and <code>MIGRATION_TARGET</code> . One and only one of the <code>policy</code> stanzas associated with a given <code>filesystem</code> stanza should have a <code>FREE_SPACE_MINIMUM</code> value if the stanza has a <code>MIGRATION_LEVEL</code> of <code>auto</code> ; in this case, there is no default value. |

You should set `FREE_SPACE_MINIMUM` so that it is less than the values for `FREE_SPACE_TARGET` and `MIGRATION_TARGET`.

Figure 7-1 describes the concepts of free space and migration targets, using as an example a minimum free-space threshold of 10%. For example, if offline files are recalled or regular files are added to the filesystem such that only 10% of it is free, DMF will try to reach the free-space target of 30% by freeing the space

currently held by dual-state files and try to reach the migration target of 80% by migrating regular files so that they become dual-state.



**Figure 7-1** Concepts of Free-Space Minimum and Target

For more details, see Chapter 11, "Automated Space Management" on page 509.

For the information on how this parameter is used when automated space management is not configured, see the `dmf.conf(5)` man page.

`FREE_SPACE_TARGET`

Specifies the integer percentage of total filesystem space that `dmfsfree` or `dmdskfree` tries to free if free space reaches or falls below the `FREE_SPACE_MINIMUM` threshold. You should set `FREE_SPACE_TARGET` so



|                               |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|-------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                               | that it is less than <code>MIGRATION_TARGET</code> . One and only one of the <code>policy</code> stanzas associated with a given <code>filesystem</code> stanza should have a <code>FREE_SPACE_TARGET</code> value if the stanza has a <code>MIGRATION_LEVEL</code> of <code>auto</code> ; in this case, there is no default value.                                                                                                                                                                                                                                                                  |
| <code>MIGRATION_TARGET</code> | Specifies the integer percentage of total filesystem space that <code>dmfsmon</code> tries to maintain as a reserve of space that is free or occupied by dual-state files. (The online space occupied by dual-state files can be freed quickly if free space reaches or falls below <code>FREE_SPACE_MINIMUM</code> .) One and only one of the <code>policy</code> stanzas associated with a given <code>filesystem</code> stanza should have a <code>MIGRATION_TARGET</code> value if the stanza has a <code>MIGRATION_LEVEL</code> of <code>auto</code> ; in this case, there is no default value. |
| <code>SITE_SCRIPT</code>      | Specifies the site-specific script to execute when the <code>dmfsfree</code> , <code>dmdskfree</code> , or <code>dmfsmon</code> command is run: <ul style="list-style-type: none"><li>• If the script returns a zero exit status, the command continues its normal processing</li><li>• If the script returns a nonzero exit status, the command returns immediately, using this value as its own exit status</li></ul> See <code>dmfsfree(8)</code> or <code>dmdskfree(8)</code> for further details. This parameter is optional.                                                                   |

For more details, see Chapter 11, "Automated Space Management" on page 509.

See also:

- "Functions of `policy` Parameters" on page 365
- "Managed Filesystem Rules" on page 366

### File Weighting Parameters for a Managed Filesystem

The following parameters control file weighting for a managed filesystem:

**Parameter**

AGE\_WEIGHT

**Description**

Specifies a floating-point constant and floating-point multiplier to use when calculating the weight given to a file's age, calculated as follows:

$$\text{constant} + (\text{multiplier} * \text{file\_age\_in\_days})$$

The default is a *constant* of 1 and a *multiplier* of 1.

The AGE\_WEIGHT parameter accepts an optional *when* clause, which contains a conditional expression. You can use this clause to select which files should use the AGE\_WEIGHT values. See "when Clause" on page 380.

The AGE\_WEIGHT parameter also accepts an optional *ranges* clause, which specifies the ranges of a file for which the parameter applies. See "ranges Clause" on page 383.

DMF checks each AGE\_WEIGHT parameter in turn, in the order that they occur in the configuration file. If the *when* clause is present and no *ranges* clause is present, DMF determines whether the file matches the criteria in the clause. If no *when* clause is present, a match is assumed. If the file matches the criteria, the file weight is calculated from the parameter values. If they do not match, the next instance of that parameter is examined.

You can configure a negative value to ensure that specific files are never automatically migrated. For example, you might want to set a minimum age for migration. The following parameter specifies that files that have been accessed within 1 day are never automatically migrated:

```
AGE_WEIGHT -1      0.0      when age <= 1
```

---

**Note:** DMF calculates the age weight and space weight separately. If either value is less than zero, the file is **not** automatically migrated and the file or range is **not** automatically freed. Otherwise, the two values are summed to form the file's or range's weight.

---

## SPACE\_WEIGHT

Specifies a floating-point constant and floating-point multiplier to use when calculating the weight given to a file's size, calculated as follows:

$$\text{constant} + (\text{multiplier} * \text{file\_disk\_space\_in\_bytes})$$

The default is a *constant* of 0 and a *multiplier* of 0.

For a partial-state file, *file\_disk\_space\_in\_bytes* is the amount of space occupied by the file at the time of evaluation.

The SPACE\_WEIGHT parameter accepts an optional *when clause*, which contains a conditional expression. See "when Clause" on page 380.

The SPACE\_WEIGHT parameter also accepts an optional *ranges clause*, which specifies the ranges of a file for which the parameter applies. See "ranges Clause" on page 383.

You can configure a negative value to ensure that specific files are never automatically migrated. For example, you might want to set a minimum size for migration. The following parameter specifies that small files are never automatically migrated:

```
SPACE_WEIGHT -1 0 when space <= 4k
```

---

**Note:** DMF calculates the age weight and space weight separately. If either value is less than zero, the file is **not** automatically migrated and the file or range is **not** automatically freed. Otherwise, the two values are summed to form the file's or range's weight.

---

See also:

- "Functions of policy Parameters" on page 365
- "Managed Filesystem Rules" on page 366

### MSP/VG Selection Parameters for a Managed Filesystem

The following parameters control MSP/VG selection for a managed filesystem:

| Parameter                | Description                                                                                                                                                                                                                                                                                                                                                                   |
|--------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| SELECT_MSP,<br>SELECT_VG | Specifies the MSPs, VGs, and MGs to use for migrating a file. If you use an MG, you must not specify overlapping MSPs, VGs, or MGs on the same SELECT_VG and SELECT_MSP statement (taking care to ensure that the statement expands to a set of non-overlapping MSPs and VGs when all of the group members of the MGs are considered). See "migrategroup Object" on page 426. |

---

**Note:** The parameters are not used for defining which MSP/VG to use for recalls; for that, see the definitions of the LS\_NAMES, MSP\_NAMES, DRIVE\_GROUPS, and VOLUME\_GROUPS parameters.

---

The SELECT\_MSP and SELECT\_VG parameters are equivalent. VGs, cloud MSPs, disk MSPs, FTP MSPs, and MGs may be specified by either parameter.

You can list as many MSP/VG/MG names as you have msp, volumegroup, and migrategroup objects defined. A copy of the file will be migrated as follows:

- To each MSP/VG listed explicitly
- For each MG listed, to exactly one MSP/VG that is a member of the MG

---

**Note:** If `DUMP_WORKSPACE` is not set or if it is explicitly set to a location inside the backup filesystem (the filesystem that has `USE_AS_DUMP_DEST` set to ON), then you must prevent the migration of temporary files produced by the integrated-backup method. These temporary files have a project ID of 4136. To accomplish this, set the **first** `SELECT_VG/SELECT_MSP` parameter to the following value:

```
none when projid = 4136
```

---

If no `SELECT_MSP` or `SELECT_VG` parameter applies to a file, it will not be migrated.

The parameters are processed in the order that they appear in the policy. The first `SELECT_MSP` or `SELECT_VG` statement that applies to a given file is honored.

These parameters allow conditional expressions based on the value of a file tag. See "Customizing DMF" on page 186.

The `root` user on the DMF server can override the selection specified in these parameters through the use of `dmput -V` or with `libdmfusr.so` calls. If site-defined policies are in place, they may override these parameters.

There is no default.

See also:

- "Functions of `policy` Parameters" on page 365
- "Managed Filesystem Rules" on page 366

## DCM MSP `STORE_DIRECTORY` `policy` Parameters

This section discusses the following:

- "policy Object Summary for a DCM MSP" on page 376
- "Automated Space-Management Parameters for a DCM MSP STORE\_DIRECTORY" on page 376
- "File Weighting Parameters for a DCM MSP STORE\_DIRECTORY" on page 378
- "VG Selection Parameters for a DCM MSP STORE\_DIRECTORY" on page 380

See also "Functions of policy Parameters" on page 365.

### **policy Object Summary for a DCM MSP**

Following is a summary of the potential parameters for the policy object for a DCM MSP:

```
policy
    TYPE
    DUALRESIDENCE_TARGET
    FREE_DUALRESIDENT_FIRST
    FREE_SPACE_DECREMENT
    FREE_SPACE_MINIMUM
    FREE_SPACE_TARGET
    SITE_SCRIPT
    CACHE_AGE_WEIGHT
    CACHE_SPACE_WEIGHT
    SELECT_LOWER_VG
```

For details, see:

- "Automated Space-Management Parameters for a DCM MSP STORE\_DIRECTORY" on page 376
- "File Weighting Parameters for a DCM MSP STORE\_DIRECTORY" on page 378
- "VG Selection Parameters for a DCM MSP STORE\_DIRECTORY" on page 380

### **Automated Space-Management Parameters for a DCM MSP STORE\_DIRECTORY**

The following parameters control automated space management for a DCM MSP STORE\_DIRECTORY:

| Parameter               | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
|-------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| DUALRESIDENCE_TARGET    | <p>Specifies the integer percentage of DCM MSP cache capacity that DMF maintains as a reserve of dual-resident files whose online space can be freed if free space reaches or falls below <code>FREE_SPACE_MINIMUM</code>. The <code>dmdskmsp</code> process tries to ensure that this percentage of the filesystem is copied to secondary storage, is currently being copied to secondary storage, or is free after it runs <code>dmdskfree</code> to make space available. This parameter is required for a DCM MSP; there is no default. (It does not apply to managed filesystems.)</p>                                                                                                                                                                               |
| FREE_DUALRESIDENT_FIRST | <p>When set to <code>ON</code>, specifies that <code>dmdskfree</code> will first free dual-resident files before freeing files it must migrate. The default is <code>OFF</code>.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| FREE_SPACE_DECREMENT    | <p>Specifies the integer percentage of filesystem space by which <code>dmfsmon</code> or <code>dmdskmsp</code> will decrement <code>FREE_SPACE_MINIMUM</code> if it cannot find enough files to migrate so that the value is reached. The decrement is applied until a value is found that can be achieved. If space later frees up, the <code>FREE_SPACE_MINIMUM</code> is reset to its original value. Valid values are in the range 1 through the value of <code>FREE_SPACE_TARGET</code>. The default is 2.</p>                                                                                                                                                                                                                                                       |
| FREE_SPACE_MINIMUM      | <p>Specifies the minimum integer percentage of the total filesystem space that the DCM MSP tries to maintain as free. When the available free space reaches or falls below this threshold value, <code>dmdskfree</code> will begin to free dual-resident files and make non-dual-resident files dual-resident in order to meet the percentages set for <code>FREE_SPACE_MINIMUM</code>, <code>FREE_SPACE_TARGET</code>, and <code>DUALRESIDENCE_TARGET</code>.</p> <p>You should set <code>FREE_SPACE_MINIMUM</code> so that it is less than the values for <code>FREE_SPACE_TARGET</code> and <code>DUALRESIDENCE_TARGET</code>. This parameter is required; there is no default.</p> <p>For more details, see Chapter 11, "Automated Space Management" on page 509.</p> |

|                   |                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|-------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| FREE_SPACE_TARGET | Specifies the integer percentage of total filesystem space that <code>dmfsfree</code> or <code>dmdskfree</code> tries to free if free space reaches or falls below the <code>FREE_SPACE_MINIMUM</code> threshold. You should set <code>FREE_SPACE_TARGET</code> so that it is less than <code>DUALRESIDENCE_TARGET</code> . This parameter is required; there is no default.                                                                                                |
| SITE_SCRIPT       | Specifies the site-specific script to execute when <code>dmfsfree</code> , <code>dmdskfree</code> , or <code>dmfsmon</code> is run. If it returns a zero exit status, <code>dmfsfree</code> , <code>dmdskfree</code> , or <code>dmfsmon</code> continue their normal processing. If nonzero, they return immediately, using this value as their own exit status. See <code>dmfsfree(8)</code> or <code>dmdskfree(8)</code> for further details. This parameter is optional. |

See also:

- "DCM MSP STORE\_DIRECTORY Rules" on page 367
- "Functions of policy Parameters" on page 365

**File Weighting Parameters for a DCM MSP STORE\_DIRECTORY**

The `policy` parameters for file weighting are as follows:

| Parameter        | Description                                                                                                                                                                                                                                                                          |
|------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| CACHE_AGE_WEIGHT | <p>Specifies a floating-point constant and floating-point multiplier to use when calculating the weight given to a file's age, calculated as follows:</p> $constant + (multiplier * file\_age\_in\_days)$ <p>The default is a <i>constant</i> of 1 and a <i>multiplier</i> of 1.</p> |

---

**Note:** This parameter refers to the copies in the cache, not the originals in the managed filesystem.

---

The `CACHE_AGE_WEIGHT` parameter accepts an optional `when` clause, which contains a conditional expression. See "when Clause" on page 380.



Add a `when` clause to select which files should use these values. DMF checks each `AGE_WEIGHT` parameter in turn, in the order that they occur in the configuration file. If the `when` clause is present, DMF determines whether the file matches the criteria in the clause. If no `when` clause is present, a match is assumed. If the file matches the criteria, the file weight is calculated from the parameter values. If they do not match, the next instance of that parameter is examined.

You can configure a negative value to ensure that specific files are never automatically migrated. For example, you might want to set a minimum age for migration. The following parameter specifies that files that have been accessed or modified within 1 day are never automatically migrated:

```
CACHE_AGE_WEIGHT -1    0.0    when age <= 1
```

---

**Note:** DMF calculates the age weight and space weight separately. If either value is less than zero, the file is **not** automatically migrated and the file is **not** automatically freed. Otherwise, the two values are summed to form the file's weight.

---

CACHE\_SPACE\_WEIGHT

Specifies a floating-point constant and floating-point multiplier to use when calculating the weight given to a file's size, calculated as follows:

$$\text{constant} + (\text{multiplier} * \text{file\_disk\_space\_in\_bytes})$$

The default is a *constant* of 0 and a *multiplier* of 0.

For a partial-state file, *file\_disk\_space\_in\_bytes* is the amount of space occupied by the file at the time of evaluation.

The `CACHE_SPACE_WEIGHT` parameter accepts an optional `when` clause, which contains a conditional expression. See "when Clause" on page 380.

Configure negative values to ensure that files are never automatically migrated. For example, you might want to set a minimum size for migration. The following parameter specifies that small files are never automatically migrated:

```
SPACE_WEIGHT -1    0    when space <= 4k
```

See also:

- "Functions of `policy` Parameters" on page 365
- "DCM MSP `STORE_DIRECTORY` Rules" on page 367

### VG Selection Parameters for a DCM MSP `STORE_DIRECTORY`

The following parameter controls VG selection for a DCM MSP `STORE_DIRECTORY`:

| Parameter                    | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>SELECT_LOWER_VG</code> | Defines the destinations of files that must be flushed to another MSP or VG. You can specify VGs, MSPs, and/or MGs, using the same syntax as <code>SELECT_MSP/SELECT_VG</code> in "MSP/VG Selection Parameters for a Managed Filesystem" on page 374 except that it must not include DCM MSPs. If no <code>SELECT_LOWER_VG</code> applies to a file, it will remain in the cache indefinitely. A large number of such files may impair the effectiveness of the DCM MSP or (in extreme cases) may cause the migration of more user files in the managed filesystem to fail.<br><br>There is no default. |

See also:

- "Functions of `policy` Parameters" on page 365
- "DCM MSP `STORE_DIRECTORY` Rules" on page 367

### when Clause

The file weighting and MSP/VG selection parameters accept an optional `when` clause to restrict the set of files to which that parameter applies. It has the following form:

`when` *expression*

*expression* can include any of the following simple expressions:

| Expression  | Description                                                                                                                                                                                                                                                                                                                                                                    |
|-------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| age         | Specifies the number of days since last modification or last access of the file, whichever is more recent.                                                                                                                                                                                                                                                                     |
| gid         | Specifies the group ID or group name of the file.                                                                                                                                                                                                                                                                                                                              |
| sitelfn     | Invokes a site-defined policy function once for each file being considered, and is replaced by the return code of the function. This is only applicable to the AGE_WEIGHT, SPACE_WEIGHT, SELECT_MSP, and SELECT_VG parameters in a filesystem's policy stanza. For more information, see Appendix C, "Site-Defined Policy Subroutines and the sitelib.so Library" on page 735. |
| projid      | Specifies a user-determined number associated with a file by the dmprojid(8) command, in the range 0-4294967294 providing that 32-bit project IDs are enabled in the filesystem; otherwise, the range is 0-65536.                                                                                                                                                              |
| sitetag     | Specifies a site-determined number associated with a file by the dmtag(1) command, in the range 0-4294967295. For example:<br><br><pre>sitetag = 27 sitetag in (20-40, 5000, 4000000000)</pre>                                                                                                                                                                                 |
| size        | Specifies the logical size of the file, as shown by <code>ls -l</code> . By default, the unit of measure is bytes; see "Units of Measure" on page 275.                                                                                                                                                                                                                         |
| softdeleted | Specifies whether or not the file corresponding to a cached copy has been soft deleted; only applicable to the CACHE_AGE_WEIGHT, CACHE_SPACE_WEIGHT, and SELECT_LOWER_VG parameters in a DCM MSP policy stanza. Legal values are <code>false</code> and <code>true</code> .                                                                                                    |
| space       | Specifies the number of bytes that the file occupies on disk (always a multiple of the block size, which may be larger or smaller than the length of the file). There may be an optional trailing scaling character. Sparse files usually occupy less space on disk than the size of the file. For a partial-state (PAR) file, the value used is the                           |

space that the file occupies on disk at the time of evaluation. The space that a file occupies on disk can change over time due to various effects, such as speculative preallocation. For this reason, `size` may be a better and more predictable metric to use in policies. By default, the unit of measure is bytes; see "Units of Measure" on page 275.

For example, you might use the following line in a policy:

```
SELECT_VG none when space < 4096
```

Your intent would be to restrict files smaller than 4 Kbytes from migrating.

However, this line may actually allow files as small as 1 byte to be migrated, because while the amount of data in the file is 1 byte, it will take 1 block to hold that 1 byte. If your filesystem uses 4-Kbyte blocks, the space used by the file is 4096, and it does not match the policy line.

To ensure that files smaller than 4 Kbytes do not migrate, use the following line:

```
SELECT_VG none when space <= 4096
```

`uid` Specifies the user ID or user name of the file.

Combine expressions by using `and`, `or`, and `()`.

Use the following operators to specify values:

```
=  
!=  
>  
<  
>=  
<=  
in
```

The following are examples of valid expressions:

```
space < 10m           (space used is less than 10 million bytes)
uid <= 123            (file's user ID is less than or equal to 123)
gid = 55              (file's group ID is 55)
age >= 15             (file's age is greater than or equal to 15 days)
space > 1g           (space used is greater than 1 billion bytes)
uid in (chris, 10 82-110 200)
                    (file owner's user name is chris or
                    the file owner's UID is 10, in the range 82-110, or 200)
(gid = 55 or uid <= 123) and age < 5
                    (file's age is less than 5 days and its
                    group ID is 55 or its user ID is less than or equal to 123)
```

## ranges Clause

If partial-state files are enabled on your host (meaning that you have the `PARTIAL_STATE_FILES` configuration file parameter set to `ON`, according to the information in the DMF release note), you can use the `ranges` clause to select ranges of a file. The `AGE_WEIGHT` and `SPACE_WEIGHT` parameters accept an optional `ranges` clause to restrict the ranges of a file for which a parameter applies. Example 7-25, page 387, shows an example of a policy that contains `ranges` clauses.

---

**Note:** The `ranges` clause is not valid with the `CACHE_AGE_WEIGHT` or `CACHE_SPACE_WEIGHT` parameters.

---

The clause has the following form, where *byteranges* is one or more byte ranges:

```
ranges byteranges
```

Each byte range consists of a set of numbers that indicate byte positions. (You can also use `BOF` or `bof` to indicate the first byte in the file and `EOF` or `eof` to indicate the last byte in the file.) Each byte range is separated by a comma and can have one of the following forms:

- A specification of two byte positions, where *first* specifies the first byte in the range and *last* specifies the last byte in the range:

```
first : last
```

If unsigned, *first* and *last* count from the beginning of the file; if preceded by a minus sign (-), they count backwards from the end of the file.

The first byte in the file is byte 0 or BOF and the last byte is -0 or EOF. Therefore, BOF:EOF and 0:-0 both define a range covering the entire file.

For example:

- `ranges 0:4095` specifies the first 4096 bytes of the file
- `ranges -4095:EOF` specifies the last 4096 bytes of the file

- A specification of the size of the range, starting at a given point, where *first* is a byte position as above and *size* is the number of bytes in the range, starting at *first*:

*first+size*

For example, the following indicates bytes 20 through 29:

`ranges 20+10`

If *size* is preceded by a minus sign, it specifies a range of *size* bytes ending at *first*. For example, the following indicates bytes 11 through 20:

`ranges 20+-10`

- A specification of the size of the range only (without a colon or plus symbol), assumed to start at the end of file (when preceded by a minus sign) or beginning of file:

*-size*  
*size*

For example, the following specifies the last 20 bytes in the file:

`ranges -20`

The *first*, *last*, or *size* values can be of the following forms:

- A hexadecimal number: `0xn`
- A decimal number with an optional trailing scaling character. The decimal number may include a decimal point (.) and exponent. The trailing scaling character may be one of those shown in "Units of Measure" on page 275.

---

**Note:** DMF may round byte ranges and join nearby ranges if necessary. If a range is given a negative weight, rounding may cause additional bytes to be ineligible for automated space management.

---

Do not use a `ranges` clause when partial-state files are disabled in DMF. Specifying many ranges for a file is discouraged, as it can cause the time and memory used by automated space management to grow. DMF has an upper limit on the number of regions that can exist within a file; this can sometimes cause a range to be given an effective lower weight than what was specified in the configuration file. This might happen if the file is already partial-state and the range with largest weight cannot be made offline (OFL) because that would create too many regions. If the file has too many regions to make the range offline, but it could be made offline at the same time as a range with lower weight, it will be given the lower weight. If more than one range in the middle of a file is not a candidate for automatic migration, the limit on the number of regions may make it impossible to automatically free other regions of the file.

## **policy Configuration Examples**

This section discusses the following:

- "Automated Space-Management Example" on page 386
- "Automated Space-Management Using Ranges Example" on page 387
- "MSP/VG Selection Example" on page 388
- "policy Examples for Integrated Backups" on page 389

### Automated Space-Management Example

Example 7-24 shows an example of a `policy` object to configure automated space management.

#### Example 7-24 `policy` Object for Automated Space Management

```
define fs_space
    TYPE                                policy
    MIGRATION_TARGET                    50
    FREE_SPACE_TARGET                   10
    FREE_SPACE_MINIMUM                  5
    FREE_DUALSTATE_FIRST                off

    AGE_WEIGHT 0    0.00    when age < 10
    AGE_WEIGHT 1    0.01    when age < 30
    AGE_WEIGHT 10   0.05    when age < 120
    AGE_WEIGHT 50   0.1

    SPACE_WEIGHT 0 0
enddef
```

In the above example:

- The `define` parameter must have a value that matches the value previously set in the `POLICIES` parameter of the `filesystem` object.
- The automated space-management parameters specify that when only 5% (`FREE_SPACE_MINIMUM`) of the `fs_space` filesystem is free, DMF will try to migrate regular files until 10% (`FREE_SPACE_TARGET`) of the filesystem is free and 50% (`MIGRATION_TARGET`) of the filesystem is either free or has files that are dual-state. DMF will not free the space of existing dual-state files before beginning migration of regular files. (See "Automated Space-Management Parameters for a Managed Filesystem" on page 369.)

DMF checks each `AGE_WEIGHT` parameter in turn, in the order that they occur in the configuration file. DMF checks the `when` clause to see if the file matches the criteria.

- File migration likelihood increases with the length of time since last access. Files that have been accessed or modified within the last 10 days have a weight of 0, making them the least likely to be migrated; files that have not been accessed or modified in 120 days or more have a far greater weight than all other files.



- The size of the file does not affect migration because all files have `SPACE_WEIGHT` of 0.

### Automated Space-Management Using Ranges Example

Example 7-25 shows a `policy` object using ranges, which requires that partial-state files are enabled on the host (meaning that `PARTIAL_STATE_FILES` is set to `ON` and the appropriate kernel is installed, according to the information in the DMF release note).

#### Example 7-25 `policy` Object for Automated Space Management Using Ranges

```
define fs2_space
    TYPE                policy
    MIGRATION_TARGET    50
    FREE_SPACE_TARGET   10
    FREE_SPACE_MINIMUM  5
    FREE_DUALSTATE_FIRST off

    AGE_WEIGHT -1.  0.00 ranges 0:4095 when uid=624
    AGE_WEIGHT -1   0    ranges 0:4095,-4095:EOF when uid=321
    AGE_WEIGHT 1    0.01  when age < 30
    AGE_WEIGHT 10   0.05  when age < 120
    AGE_WEIGHT 50   0.1

    SPACE_WEIGHT 0 0
endef
```

The above example is similar to Example 7-24, page 386, with the following differences:

- If a file is owned by UID 624 and is 1004096 bytes long, the first 4096 bytes are given an `AGE_WEIGHT` of `-1`. The remaining 1000000 bytes are given an `AGE_WEIGHT` based on the age of the file; based on this weight, automated space management may select this file to be migrated. DMF migrates the entire file before changing its state to `OFL`, `DUL`, or `PAR`. Automated space management may also choose to put the last 1000000 bytes of the file offline based on the weight of that range; the first 4096 bytes will not be eligible for being put offline by automated space management.
- If a file is owned by UID 321, the first and last 4096 bytes of it will not be eligible for being put offline by automated space management, similar to the above situation.

- If a file is owned by UID 956, the policy in Example 7-25 would give the entire file an AGE\_WEIGHT based on its age.

### MSP/VG Selection Example

Example 7-26 defines a policy object for an MSP/VG.

**Example 7-26** policy Object for an MSP/VG

```
define fs_msp
    TYPE                policy
    SELECT_MSP none     when space < 65536
    SELECT_MSP cart1 cart2 when gid = 22
    SELECT_MSP cart3     when space >= 10m
    SELECT_MSP cart1     when space >= 50m
    SELECT_VG cart2
enddef
```

In the above example:

- The define parameter must match the value that you set previously in the POLICIES parameter of the filesystem object. See "filesystem Object Parameters" on page 351.
- The special MSP name none means that files that are smaller than 65,536 bytes will never be migrated.
- The VG/MSP names (cart1, cart2, cart3) must match the names set in the LS\_NAMES parameter (or else the MSP\_NAMES parameter) of the dm Daemon object. The SELECT\_MSP and SELECT\_VG parameters are interchangeable, so both can be used in the same stanza.
- Any file with a group ID of 22 will be sent to both cart1 and cart2
- Smaller files will be sent to cart3 and larger files will be sent to cart1

---

**Note:** The order of the SELECT\_MSP and SELECT\_VG statements is important. The first SELECT statement that applies to the file is honored. For example, if the order of the statements above were reversed, a 10-million-byte file would be migrated to cart1, because the check for greater than or equal to 65,536 bytes would be done first, and it would be true.

---

- Any other file that does not meet the above criteria is sent to cart2.

## policy Examples for Integrated Backups

Example 7-27, page 389 defines the `policy` objects for integrated backups.

### Example 7-27 `policy` Objects for Integrated Backups

```
define backup_space_policy
    TYPE                policy
    MIGRATION_TARGET    99
    FREE_SPACE_TARGET   98
    FREE_SPACE_MINIMUM  97
enddef

define backup_vg_policy
    TYPE                policy
    SELECT_VG           none when projid = 4136
    SELECT_VG           bvg1a bvg1b
enddef
```

In the above example:

- The `define` parameter must match the value that you set previously in the `POLICIES` parameter of the `filesystem` object that sets `USE_AS_DUMP_DEST`. See "filesystem Object Parameters" on page 351.
- The automated space-management parameters specify that when 97% (`FREE_SPACE_MINIMUM`) of the filesystem is free, DMF will try to migrate regular files until 99% (`FREE_SPACE_TARGET`) of the filesystem is free and 97% (`MIGRATION_TARGET`) of the filesystem is either free or has files that are dual-state. DMF will not free the space of existing dual-state files before beginning migration of regular files. (See "Automated Space-Management Parameters for a Managed Filesystem" on page 369.)

DMF checks each `AGE_WEIGHT` parameter in turn, in the order that they occur in the configuration file. DMF checks the `when` clause to see if the file matches the criteria.

- Files with project ID of 4136 (which are temporary files produced by the integrated-backup method) will never be migrated.

---

**Note:** The order of the `SELECT_VG` statements is important. The first `SELECT` statement that applies to a given file is honored.

---

- The VG names (bvg1a and bvg1b) must match the names set in the LS\_NAMES parameter (or else the MSP\_NAMES parameter) of the dmdaemon object.

## fastmountcache Object

This section contains the following:

- "fastmountcache Object Name" on page 390
- "fastmountcache Object Summary" on page 390
- "fastmountcache Object Parameters" on page 390
- "fastmountcache Object Examples" on page 391

### fastmountcache Object Name

The name of the `fastmountcache` object is chosen by the administrator and may contain uppercase or lowercase alphanumeric characters or underscores. It cannot begin with an underscore or contain any white space.

### fastmountcache Object Summary

Following is a summary of the potential parameters for the `fastmountcache` object:

```
fastmountcache
    TYPE
    CACHE_MEMBERS
```

### fastmountcache Object Parameters

The `fastmountcache` object defines the parameters for a fast-mount cache.

| Parameter | Description                                                                                         |
|-----------|-----------------------------------------------------------------------------------------------------|
| TYPE      | Specifies <code>fastmountcache</code> (required name for this type of object). There is no default. |

|               |                                                                         |
|---------------|-------------------------------------------------------------------------|
| CACHE_MEMBERS | Specifies the MGs and independent VGs to be used as a fast-mount cache. |
|---------------|-------------------------------------------------------------------------|

## fastmountcache Object Examples

This section discusses the following examples:

- "fastmountcache with an MG" on page 391
- "fastmountcache with a Mix of Members" on page 391

### fastmountcache with an MG

#### Example 7-28 fastmountcache with an MG

```
define copan_fmc
    TYPE                fastmountcache
    CACHE_MEMBERS      mg_fmc
enddef
```

In the above example:

- The name of the fast-mount cache is `copan_fmc`.
- The VGs that will be used for the fast-mount cache are part of the `mg_fmc` MG.
- The volume group objects that are part of `mg_fmc` should use a `RESERVED_VOLUMES` setting of 1 to ensure proper rotation among the volumes.
- There must be a `taskgroup` object configured elsewhere in the configuration file to free the volumes in the fast-mount cache, and it must reference the `taskgroup` object named `copan_fmc`. See "taskgroup Object" on page 304.

### fastmountcache with a Mix of Members

#### Example 7-29 fastmountcache with a Mix of Members

```
define copan_fmc
    TYPE                fastmountcache
    CACHE_MEMBERS      vg_c00 mg_fmc
enddef
```

This example is similar to Example 7-28, page 391, except for the following:

- There is a single independent VG (vg\_c00) and an MG (mg\_fmc) that will be used for the fast-mount cache.
- The vg\_c00 VG should use the default setting of RESERVED\_VOLUMES (which is 0) because it should never participate in merging and no rotation is required.

## Objects Related to an LS

Multiple objects are required to configure an LS. This section discusses the following:

- "libraryserver Object" on page 392
- "drivegroup Object" on page 395
- "volumegroup Object" on page 410
- "migrategroup Object" on page 426
- "resourcescheduler Object" on page 432
- "resourcewatcher Object" on page 433
- "allocationgroup Object" on page 434
- "Examples of Configuring an LS" on page 436
- "LS Tasks" on page 441
- "LS Database Records" on page 444

### libraryserver Object

This section discusses the following:

- "libraryserver Object Name" on page 393
- "libraryserver Object Summary" on page 393
- "libraryserver Object Parameters" on page 393

**libraryserver Object Name**

The name of the `libraryserver` object is chosen by the administrator and may contain up to 8 uppercase or lowercase alphanumeric characters or underscores. It cannot begin with an underscore or contain any white space.

**libraryserver Object Summary**

Following is a summary of the potential parameters for the `libraryserver` object:

```
libraryserver
    TYPE
    CACHE_DIR
    CACHE_SPACE
    COMMAND
    COPAN_VSNS
    DISCONNECT_TIMEOUT
    DRIVE_GROUPS
    MAX_CACHE_FILE
    MESSAGE_LEVEL
    RUN_TASK
    TASK_GROUPS
    WATCHER
```

**libraryserver Object Parameters**

The `libraryserver` object, one for each library, has the following parameters:

| Parameters | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| TYPE       | Specifies <code>libraryserver</code> (required name for this type of object). There is no default.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| CACHE_DIR  | Specifies the directory in which the VG stores chunks while merging them from sparse volumes. If you do not specify this parameter, DMF uses the value of <code>TMP_DIR</code> from the <code>base</code> object (see "base Object Parameters" on page 278). If you use Parallel DMF and specify <code>CACHE_DIR</code> , it must either be a CXFS filesystem or be in a CXFS filesystem. This directory must not be in a managed filesystem. By default, this value must not reside in the root filesystem (see the description of <code>ADMDIR_IN_ROOTFS</code> in "base Object Parameters" on |

page 278). Do not change this parameter while DMF is running.

CACHE\_SPACE

Specifies the amount of disk space that `dmatis` can use when merging chunks from sparse volumes. During merging, small chunks from sparse volumes are cached on disk before being written to a secondary storage. The default is 0, which causes all files to be merged via sockets. By default, the unit of measure is bytes; see "Units of Measure" on page 275.

The LS can merge volumes more efficiently if it can stage most of the files to disk.

---

**Note:** The zone size influences the required cache space. See `ZONE_SIZE` in "volumegroup Object" on page 410.

---

COMMAND

Specifies the binary file to execute in order to initiate the LS. This value must be `dmatis`.

COPAN\_VSNS

(*COPAN only*) Specifies if the fourth character of the VSN indicates the RAID in the COPAN virtual tape library (VTL) or COPAN MAID that contains the volume. This specification applies for all VSNs in this LS. Specifying `ON` enables this feature; specifying `OFF` disables it. The default is `OFF`. Do not change this parameter while DMF is running.

DISCONNECT\_TIMEOUT

Specifies the number of seconds after which the LS will consider a mover process to have exited if it cannot communicate with the process. Likewise, mover processes will use this value to determine if the LS has exited. The default is 180 seconds.

DRIVE\_GROUPS

Names one or more `drivegroup` objects containing drives that the LS can use for mounting and unmounting volumes. There is no default.

The order of these names is significant. Where there are multiple copies of the data of migrated files, recalls will normally be directed to the first-named DG that is applicable. If more than one VG within a DG contains copies, the order of the names on `VOLUME_GROUPS`



parameters is also relevant. Do not change this parameter while DMF is running.

---

**Note:** See "Ensure that the Cache Copy is Recalled First" on page 116.

---

|                |                                                                                                                                                                                                                                                                                     |
|----------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| MAX_CACHE_FILE | Specifies the largest chunk (in bytes) that will be merged using the merge disk cache. Larger files are transferred directly via a socket from the read child to the write child. The default is 25% of the CACHE_SPACE value. Valid values are 0 through the value of CACHE_SPACE. |
| MESSAGE_LEVEL  | Specifies the highest message level that will be written to the LS log, which includes messages from the LS's components. It must be an integer in the range 0-6; the higher the number, the more messages written to the log file. The default is 2.                               |
| RUN_TASK       | See the description of RUN_TASK in "taskgroup Object Parameters" on page 312. Also see "Automated Maintenance Tasks" on page 175.                                                                                                                                                   |
| TASK_GROUPS    | Names the taskgroup objects that contain tasks the LS should run. By default, no tasks are run.                                                                                                                                                                                     |
| WATCHER        | Names the resource watcher that the LS should run. The default is no watcher. (A corresponding resourcewatcher object is required only if the default parameters are unacceptable. See "resourcewatcher Object Parameters" on page 434.)                                            |

See also "TMF Configuration Tasks" on page 505.

## drivegroup Object

This section discusses the following:

- "drivegroup Object Name" on page 396
- "drivegroup Object Summary" on page 396
- "drivegroup Object Parameters" on page 397

### **drivegroup Object Name**

The name of the `drivegroup` object is chosen by the administrator and may contain up to 8 uppercase or lowercase alphanumeric characters or underscores. It cannot begin with an underscore or contain any white space.

### **drivegroup Object Summary**

Following is a summary of the potential parameters for the `drivegroup` object:

```
drivegroup
    TYPE
    AGGRESSIVE_HVFY
    BANDWIDTH_MULTIPLIER
    BLOCK_SIZE
    COMPRESSION_TYPE
    DRIVE_MAXIMUM
    DRIVE_SCHEDULER
    DRIVES_TO_DOWN
    FADV_SIZE_MAID
    LABEL_TYPE
    MAX_MS_RESTARTS
    MAX_PUT_CHILDREN
    MOUNT_BLOCKED_TIMEOUT
    MOUNT_SERVICE
    MOUNT_SERVICE_GROUP
    MOUNT_TIMEOUT
    MSG_DELAY
    MULTITAPE_NODES
    OV_ACCESS_MODES
    OV_INTERCHANGE_MODES
    POSITIONING
    POSITION_RETRY
    READ_ERR_MAXIMUM
    READ_ERR_MINIMUM
    READ_ERR_TIMEOUT
    READ_IDLE_DELAY
    REDIRECT_TIME_DG_DOWN
    REINSTATE_DRIVE_DELAY
    REINSTATE_VOLUME_DELAY
    REWIND_DELAY
    RUN_TASK
```

TASK\_GROUPS  
 TMF\_TMMNT\_OPTIONS  
 VERIFY\_POSITION  
 VOLUME\_GROUPS  
 WRITE\_CHECKSUM

### drivegroup Object Parameters

The `drivegroup` object, one for each pool of interchangeable drives in a single library, has the following parameters:

| Parameter            | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
|----------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| TYPE                 | Specifies <code>drivegroup</code> (required name for this type of object). There is no default.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| AGGRESSIVE_HVfy      | <p>Specifies whether or not DMF will set the <code>hvfy</code> flag on volumes in the VOL database for an expanded set of error conditions. You can set this parameter to <code>ON</code> or <code>OFF</code>. The default is <code>OFF</code> (disables).</p> <p>By default, DMF sets the <code>hvfy</code> flag for a volume in the VOL database when it determines that there have been an excessive number of errors while appending to the volume. (The <code>hvfy</code> flag prevents further writing to that volume; it must be manually cleared by using the <code>dmvoladm</code> command or the appropriate DMF Manager action.) If this parameter is enabled, DMF will also set the <code>hvfy</code> flag if there have been I/O or positioning errors in either of the following cases:</p> <ul style="list-style-type: none"> <li>• On the last two consecutive mounts, with two different drives involved</li> <li>• On three out of the last six mounts, with at least two different drives involved</li> </ul> <p>Errors that occur while recalling, merging, or migrating, are counted. DMF may also set <code>hvfy</code> on full tapes when this parameter is enabled.</p> |
| BANDWIDTH_MULTIPLIER | <i>(OpenVault only)</i> Specifies a floating point number used to adjust the amount of bandwidth that the LS assumes a drive in this DG will use. The value is used when                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |

scheduling drives, which allows the administrator to adjust for the affects of compression. The default is 1, which means no compression. The minimum is .1 and the maximum is 1000. The `node` object parameters `HBA_BANDWIDTH` and `NODE_BANDWIDTH` are related to this parameter; see "node Object" on page 294.

`BLOCK_SIZE`

Specifies the maximum block size to use when writing from the beginning of a volume. The `blocksize` field in the database is updated with this value and is later used when reading or appending to a volume. For most storage devices, DMF supports block sizes ranging from 4096 – 2097152 bytes; for COPAN MAID and JBFS, DMF supports block sizes ranging from 131072 – 2097152 bytes. DMF uses direct I/O to tapes when possible. However, direct I/O cannot be used on some architectures if the block size is larger than 524288 bytes; in this case, DMF uses buffered I/O instead. DMF always uses buffered I/O for COPAN MAID devices. For more information, see "Device Block-Size Defaults and Bandwidth" on page 276. By default, the unit of measure is bytes; see "Units of Measure" on page 275.

The default maximum size is dependent on your device configuration, show in "Device Block-Size Defaults and Bandwidth" on page 276.

`COMPRESSION_TYPE`

*(COPAN MAID or JBFS only)* Specifies the compression type and level to be used by the write child (`dmatwc`) mover process when writing from the beginning of the volume. The following values are accepted:

- `snappy` Uses the Snappy compression library.
- `zlib[:level]` Uses the `zlib` compression library with the specified compression level. See the `zlib(3)` man page for a description of the compression levels that

can be set; 1-9 are valid values. If you specify `zlib` without a value, 1 is the default level.

The compression level is set when an empty volume is first written and remains unchanged for that volume until it has been emptied and is rewritten. Compression and decompression are done by the mover process (`dmatwc` or `dmatrc`) when COPAN MAID or JBFS is used.

---

**Note:** If you specify `COMPRESSION_TYPE`, you must also specify compression for the `OV_INTERCHANGE_MODES` parameter (below); if you do not specify compression for `OV_INTERCHANGE_MODES`, the default is no compression.

If `OV_INTERCHANGE_MODES` specifies compression but `COMPRESSION_TYPE` is not specified, the default is snappy compression.

---

`DRIVE_MAXIMUM`

Specifies the maximum number of drives that the DG is allowed to use simultaneously. This may be more or less than the number of usable drives. The maximum is 100; the default is 100.

If you specify a negative number for this parameter, the DG will add it to the number of usable drives to derive the effective maximum. For example, if you specify -2 and there are 10 usable drives, then up to 8 of them can be used by the VGs that belong to this DG. If a drive is then configured down (meaning that there are 9 usable), up to 7 drives can be used by the VGs.

---

**Note:** A given VG can have a lower maximum value if you specify the `DRIVE_MAXIMUM` parameter in its `volume group stanza`. See "volume group Object" on page 410.

---

|                 |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
|-----------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| DRIVE_SCHEDULER | Names the <code>resourcescheduler</code> objects that the DG should run for the scheduling of drives. The default is a resource scheduler of default type and parameters. For the defaults, see "resourcescheduler Object Parameters" on page 432.                                                                                                                                                                                                                                                                                                                                     |
| DRIVES_TO_DOWN  | Specifies an integer value that controls the number of "bad" drives the DG is allowed to try to configure down. When more than this number are down, whether due to the DG or to external influences such as the system administrator, the DG does not attempt to disable any more drives. The default of 0 prevents the DG from disabling any drives.                                                                                                                                                                                                                                 |
| FADV_SIZE_MAID  | <i>(COPAN MAID only)</i> Specifies when to call <code>posix_fadvise()</code> with advice <code>POSIX_FADV_DONTNEED</code> for COPAN MAID volumes. When a zone is ended, DMF calls <code>posix_fadvise()</code> provided that at least <code>FADV_SIZE_MAID</code> bytes have been written since the last call to <code>posix_fadvise()</code> . The minimum is 0, which means that <code>posix_fadvise()</code> will never be called, and the maximum is 18446744073709551615. The default is 100000000. By default, the unit of measure is bytes; see "Units of Measure" on page 275. |
| LABEL_TYPE      | Specifies the label type used when writing volumes from the beginning. Possible values are: <ul style="list-style-type: none"><li>• <code>a1</code> (ANSI label)</li><li>• <code>n1</code> (no label)</li></ul> <hr/> <p><b>Note:</b> <code>n1</code> is not recommended for data security reasons even though it might be slightly faster than the other values. <code>n1</code> is not allowed with COPAN MAID or JBFS.</p> <hr/> <ul style="list-style-type: none"><li>• <code>s1</code> (standard label for IBM tapes)</li></ul> The default is <code>a1</code> .                  |

|                  |                                                                                                                                                                                                                                                                                                                                       |
|------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| MAX_MS_RESTARTS  | Specifies the maximum number of times that DMF can attempt to restart the mounting service (TMF or OpenVault) without requiring administrator intervention. The default and recommended values are 1 for TMF and 0 for OpenVault.                                                                                                     |
| MAX_PUT_CHILDREN | Specifies the maximum number of write child ( <code>dmatwc</code> ) processes that will be scheduled simultaneously for a DG. Each <code>dmatwc</code> process uses one drive. By specifying a process maximum, some drives can be reserved for recalls, provided that the total number of usable drives exceeds the process maximum. |

You can specify values as follows:

- If the DG `DRIVE_MAXIMUM` is a positive value, that value is the maximum value that you can specify for the DG `MAX_PUT_CHILDREN`.
- If you specify a negative value for the DG `MAX_PUT_CHILDREN`, the DG will add it to the value of the DG `DRIVE_MAXIMUM` to derive the effective maximum number of processes for this DG. However, this can result in a situation in which files cannot be migrated even if there are usable drives, which can lead to filesystems filling.
- If you do not specify this parameter, then each VG uses its own value of `MAX_PUT_CHILDREN`.

---

**Note:** Even if you specify the DG `MAX_PUT_CHILDREN`, a given VG can have a lower maximum value if you specify the `MAX_PUT_CHILDREN` parameter in its `volumegroup stanza`. See "volumegroup Object" on page 410.

---

For example, if there are 6 usable drives available to the DG, the DG `DRIVE_MAXIMUM` is not specified, and the DG `MAX_PUT_CHILDREN` is configured to -2, then a maximum of 4 drives will be used for migrates. But if 4

drives are then configured down, at that point no drives can be used for migration.

---

**Note:** If you are using this `drivegroup` object for integrated backups, SGI recommends a value of 1 so that the dump data will be appended to a single tape if possible.

---

`MOUNT_BLOCKED_TIMEOUT` (*OpenVault only*) Specifies the maximum number of minutes to wait for a volume to be mounted when another process is using the drive. When OpenVault is the mounting service, DMF chooses which drive to use before starting a mover process. At the time it makes this choice, the drive is unused. During the small window between when this choice is made and when the mount is started, it is possible for a non-mover process to start using the drive. In that case, the mover process will block until either the drive becomes unused or `MOUNT_BLOCKED_TIMEOUT` minutes have passed, when the process will be told to exit, and the work will be scheduled for another drive. The default is 6, the minimum is 4, and the maximum is 35791394.

`MOUNT_SERVICE` Specifies the mounting service. Possible values are `openvault` and `tmf`. You must use `openvault` for those DGs that contain drives on parallel data-mover nodes. The default is `openvault`.

---

**Note:** TMF is not supported on systems running the Red Hat Enterprise Linux operating system.

---

`MOUNT_SERVICE_GROUP` Specifies the name by which the DG's devices are known to the mounting service:

- OpenVault: use the OpenVault drive group name that is specified by the `ov_drivegroup` command.



---

**Note:** OpenVault and DMF each have a group of interchangeable devices known as a *drive group*. Despite their use of the same terminology, a DMF drive group is different from an OpenVault drive group, and need not use the same name.

---

- TMF: use the device group name that would be used with the `-g` option on the `tmmt` command.

By default, the `drivegroup` object's name is used.

`MOUNT_TIMEOUT`

Specifies the maximum number of minutes to wait for a volume to be mounted. When OpenVault is the mounting service, the smaller of `MOUNT_BLOCKED_TIMEOUT` and `MOUNT_TIMEOUT` has precedence when the mount is blocked because the drive is in use by another process; `MOUNT_TIMEOUT` applies to all other cases.

If a mount request waits for longer than this period of time, the DG attempts to stop and restart provided that the `MAX_MS_RESTARTS` parameter allows it. This is done in an attempt to force the hanging subsystem to resume normal operation or to fail solidly.

Do not make this value too restrictive, as any non-LS tape activity (including `xfsdump`) can legitimately delay a VG's volume mount, which could result in this timeout being exceeded. The maximum is 43920. The default is 0, which means infinity (that is, forever).

`MSG_DELAY`

Specifies the number of seconds that all drives in the DG can be down before DMF sends an e-mail message to the administrator and logs an error message. The default is 0, which means that as soon as DMF notices that the mounting service is up and all of the drives are configured down, it will e-mail a message. This delay also applies to email messages sent when no drives are available for migrates, which can happen if `MAX_PUT_CHILDREN` in the `drivegroup` stanza has a negative value.

MULTITAPE\_NODES

*(Parallel DMF and OpenVault only)* Restricts the recall of a file that involves multiple tapes to one of the specified mover nodes. Without this restriction, if a given file was split across more than one tape, multiple mover nodes can simultaneously recall portions of it, which may cause a performance degradation.

DMF will choose an active and enabled node from this list. DMF will use only this node to recall multitape files until the node is no longer both active and enabled. Although you can modify the MULTITAPE\_NODES list while DMF is running, it will not cause DMF to choose a new node. If you delete the MULTITAPE\_NODES list, DMF will eventually stop restricting the recall capability.

The list may include the DMF server (if it acts as a mover node) as well as any parallel data-mover nodes. Use spaces to separate the node names.

For example, if you have four mover nodes (dmfserver, mover1, mover2, and mover3), and you want to restrict the recall of multiple tapes files to any one of them, you could enter the following:

```
MULTITAPE_NODES      mover1 mover2 mover3 dmfserver
```

---

**Note:** If all drives are down or busy on the chosen node, multitape recalls will wait until at least one drive is available.

If a multitape file is partial-state with multiple disjoint offline pieces, recall is not guaranteed to occur only on the chosen node.

---

OV\_ACCESS\_MODES

*(OpenVault only)* Specifies a list of names to be provided to OpenVault for the accessmode clause when mounting a volume. These are in addition to the names that DMF always specifies: variable and rewind. If you do not specify readwrite, DMF will provide readonly or readwrite, as appropriate. For more information about the possible values, see the

|                      |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
|----------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| OV_INTERCHANGE_MODES | <p>description of the <code>access</code> option in the <code>ov_mount(8)</code> man page.</p> <p><i>(OpenVault only)</i> Specifies a list of mode values to be provided to OpenVault when writing a volume from the beginning. By default, this list is empty.</p> <p>Most drives support a value of either <code>compression</code> or <code>nocompression</code>.</p> <p>For example, to specify that you want data compressed, use:</p> <pre>OV_INTERCHANGE_MODES    compression</pre> <p>Compression and decompression are done by the mover process (<code>dmatwc</code> or <code>dmatrc</code>) when COPAN MAID or JBFS is used.</p> <hr/> <p><b>Note:</b> If you use COPAN MAID or JBFS and specify <code>compression</code>, also see the <code>COMPRESSION_TYPE</code> parameter (above).</p> <hr/> <p>Some drives support additional values. For example, the T1000C drive also supports the additional values T1000C, T1000B, and T1000A. For example, if you have a mixture of T1000C and T1000B drives, you could use the following to tell the T1000C drives to write in compressed T1000B format so that both drives can then later read the same cartridges:</p> <pre>OV_INTERCHANGE_MODES    compression T1000B</pre> <p>For more information about the possible values, see the description of the <code>firstmount</code> option in the <code>ov_mount(8)</code> man page.</p> |
| POSITIONING          | <p>Specifies how the volume should be positioned. The values can be:</p> <ul style="list-style-type: none"> <li>• <code>data</code>, which means:</li> </ul>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |

- When writing: use block ID seek capability to the zone if the block ID is known (the same as `direct`)
- When reading: try to determine the block ID of the data being read and use the block ID seek capability to position there
- `direct`, which means use block ID seek capability to the zone if the block ID is known
- `skip`, which means use volume-mark skipping to the zone

The default depends on the type of drive, and is either `direct` or `data`. If data positioning is specified for a drive whose default is `direct`, the block ID is calculated by adding an estimate of the number of blocks from the start of the zone to the data being recalled and the block ID of the start of the zone. Not all drives use this format for block ID.

`POSITION_RETRY`

Specifies the level of retry in the event of a failure during zone positioning. The values can be:

- `none`, which means there will be no retry
- `lazy`, which means the VG retries if a reasonably fast alternative means of positioning is available (default)
- `aggressive`, which means the VG can try more costly and time-consuming alternatives

If the VG is unable to position to a zone, all recalls for files with data in that zone are aborted by the VG (though not by DMF if a copy exists in another VG).

The default is `lazy`, to give the best overall recall time. If you are having trouble getting data from a volume, you might want to try `aggressive`.

`READ_ERR_MAXIMUM`

Specifies the maximum number of I/O errors that will be tolerated when recalling a file. The legal range of values is 2–100000. The default is 5000. The value of

---

`READ_ERR_MAXIMUM` should be greater than the value of `READ_ERR_MINIMUM`

---

**Note:** `READ_ERR_TIMEOUT`, `READ_ERR_MINIMUM`, and `READ_ERR_MAXIMUM` together determine how many I/O errors will be tolerated when recalling a file. If the number of consecutive I/O errors is greater than `READ_ERR_MAXIMUM`, or if the number of consecutive I/O errors is greater than `READ_ERR_MINIMUM` and the elapsed number of seconds since the first error was seen is greater than `READ_ERR_TIMEOUT`, DMF will stop trying to recall the file from the current VG and will try to recall another copy (if one exists); otherwise, the recall will fail.

---

|                                    |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>READ_ERR_MINIMUM</code>      | Specifies the number of errors (after the <code>READ_ERR_TIMEOUT</code> value has elapsed) that will cause DMF to stop trying to recall a file. The legal range of values is 1-100000. The default is 10. See the description of <code>READ_ERR_MAXIMUM</code> .                                                                                                                                                                                                                                                                                                                                                                     |
| <code>READ_ERR_TIMEOUT</code>      | Specifies the number of seconds that can elapse since the first I/O error was seen when recalling a file, after which DMF will stop trying to recall a file upon reaching the <code>READ_ERR_MINIMUM</code> value. The legal values for <code>READ_ERR_TIMEOUT</code> are 30 through 3600 seconds. The default is 600 seconds. See the description of <code>READ_ERR_MAXIMUM</code> .                                                                                                                                                                                                                                                |
| <code>READ_IDLE_DELAY</code>       | Specifies the number of seconds that an idle read child ( <code>dmtrc</code> ) can wait before being told to exit. If other DMF requests are waiting for a drive, the read child may be told to exit before <code>READ_IDLE_DELAY</code> seconds have passed. An individual <code>volume group</code> stanza may also specify <code>READ_IDLE_DELAY</code> ; the value specified in the <code>volume group</code> stanza overrides the value in the <code>drive group</code> stanza (see "volume group Object Parameters" on page 411). If <code>READ_IDLE_DELAY</code> is not specified in either stanza, the default is 5 seconds. |
| <code>REDIRECT_TIME_DG_DOWN</code> | <i>(OpenVault only)</i> Specifies the number of seconds that DMF will wait before redirecting recalls; after all drives                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |

- have been down for *REDIRECT\_TIME\_DG\_DOWN* seconds, DMF will start forwarding every recall to the VG that holds the secondary copy. (However, if a volume holding a secondary copy is in a tape that has been exported from the library, this value does not apply; in that case, DMF will wait for the drives to become available.) The default and maximum value is 2147483647. The minimum value is 420.
- REINSTATE\_DRIVE\_DELAY* Specifies the number of minutes after which a drive that was configured down by the DG will be automatically reinstated and made available for use again. A value of 0 means it should be left disabled indefinitely. The default is 1440 (one day).
- REINSTATE\_VOLUME\_DELAY* Specifies the number of minutes after which a volume that had its *hlock* flag set by DMF will be automatically reinstated and made available for use again. A value of 0 means the volume should be left disabled indefinitely. The default is 1440 (one day).
- REWIND\_DELAY* Specifies the number of seconds that an idle read child (*dmatrc*) can wait before rewinding. If other DMF requests are waiting for a drive, the read child may rewind before *REWIND\_DELAY* seconds have passed. The maximum is the value of *READ\_IDLE\_DELAY*. If *READ\_IDLE\_DELAY* is not specified, the maximum is the default value of *READ\_IDLE\_DELAY*. An individual *volume* stanza may also specify *REWIND\_DELAY*; the value specified in the *volume* stanza overrides the value in the *drive* stanza (see "volume Object Parameters" on page 411). If *REWIND\_DELAY* is not specified in either stanza, then the default is the minimum of:

$$\{2, \textit{READ\_IDLE\_DELAY}/2\}$$

If an idle read child must rewind the volume before the drive can be used to service other DMF requests, that will delay the servicing of those requests; therefore you should use caution when increasing this parameter.

---

|                   |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
|-------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| RUN_TASK          | See the description of RUN_TASK in "taskgroup Object Parameters" on page 312. Also see "Automated Maintenance Tasks" on page 175.                                                                                                                                                                                                                                                                                                                                                                                                                        |
| TASK_GROUPS       | Names the taskgroup objects that contain tasks the DG should run. By default, no tasks are run.                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
| TMF_TMMNT_OPTIONS | <i>(TMF only)</i> Specifies command options that should be added to the tmmnt command when mounting a tape. DMF uses the -Z option to tmmnt to ignore options controlling block size and label parameters. Use the BLOCK_SIZE and LABEL_TYPE DG parameters instead. There is no need for a -g option here. If it is provided, it must match the value of the MOUNT_SERVICE_GROUP parameter. To request compression, use -i. Options that are ignored are -a, -b, -c, -D, -f, -F, -l, -L, -n, -o, -O, -p, -P, -q, -R, -t, -T, -U, -v, -V, -w, -x, and -X. |
| VERIFY_POSITION   | Specifies whether the LS write child should (prior to writing) verify that the volume is correctly positioned and that the volume was properly terminated by the last use. You can set this parameter to ON or OFF. The default is ON (verify).                                                                                                                                                                                                                                                                                                          |
| VOLUME_GROUPS     | Names the volumegroup objects containing volumes that can be mounted on any of the drives within this DG. There is no default.<br><br>The order of these names is significant. Where there are multiple copies of the data of migrated files, recalls will normally be directed to the first-named VG that is applicable. A given volumegroup object can be listed in only one drivegroup object.<br><br>Do not change this parameter while DMF is running.                                                                                              |
|                   | <hr/> <b>Note:</b> See "Ensure that the Cache Copy is Recalled First" on page 116. <hr/>                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| WRITE_CHECKSUM    | Specifies if blocks should be checksummed before writing. If a block has a checksum, it is verified when                                                                                                                                                                                                                                                                                                                                                                                                                                                 |

read. You can set this parameter to ON or OFF. The default is ON.

See also Procedure 9-1 in "Configure OpenVault for a Drive Group" on page 502.

## **volumegroup Object**

This section discusses the following:

- "volumegroup Object Name" on page 410
- "volumegroup Object Summary" on page 410
- "volumegroup Object Parameters" on page 411
- "volumegroup Object Example with an AG" on page 423
- "volumegroup Object Example Overriding drivegroup Settings" on page 426

### **volumegroup Object Name**

The name of the `volumegroup` object is chosen by the administrator and may contain up to 8 uppercase or lowercase alphanumeric characters or underscores. It cannot begin with an underscore or contain any white space.

DMF supports up to 1024 MSPs, VGs and/or MGs.

### **volumegroup Object Summary**

Following is a summary of the potential parameters for the `volumegroup` object:

```
volumegroup
  TYPE
  ALLOCATION_GROUP
  ALLOCATION_MAXIMUM
  ALLOCATION_MINIMUM
  CHECKSUM_TYPE
  DRIVE_MAXIMUM
  FORWARD_RECALLS
  FULL_ZONE
  GET_WAIT_TIME
  HFREE_TIME
  IMPORT_ONLY
```



KILL\_WC\_IF\_DEMAND  
LOGICAL\_BLOCK\_PROTECTION  
MAX\_CHUNK\_SIZE  
MAX\_IDLE\_PUT\_CHILDREN  
MAX\_PUT\_CHILDREN  
MERGE\_CUTOFF  
MERGE\_THRESHOLD  
MIN\_VOLUMES  
PUT\_IDLE\_DELAY  
PUTS\_TIME  
READ\_IDLE\_DELAY  
READ\_TIME  
RESERVED\_VOLUMES  
REWIND\_DELAY  
RUN\_TASK  
TASK\_GROUPS  
TIMEOUT\_FLUSH  
VOL\_MSG\_TIME  
ZONE\_SIZE

### volume group Object Parameters

There must be a `volume group` object for each pool of volumes of the same type. It must be usable on the drives of the associated DG and capable of holding at most one copy of user files.

---

**Note:** The `run_tape_merge.sh` and `run_merge_stop.sh` tasks and their associated parameters can be specified in the `volume group` object.

---

A `volume group` object has the following parameters:

| Parameter        | Description                                                                                                                                                                                                                                                         |
|------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| TYPE             | Specifies <code>volume group</code> (required name for this type of object). There is no default.                                                                                                                                                                   |
| ALLOCATION_GROUP | Names the allocation group (AG) that serves as a pool of additional volumes for this VG. The name may contain up to 8 uppercase or lowercase alphanumeric characters or underscores; it cannot begin with an underscore, contain any white space, or be the same as |

|                                 |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
|---------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                                 | a <code>volumegroup</code> object name. See "allocationgroup Object" on page 434 and "volumegroup Object Example with an AG" on page 423.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| <code>ALLOCATION_MAXIMUM</code> | Specifies the maximum size in number of volumes to which a VG can grow by borrowing volumes from its AG. The minimum is 0, the maximum and default are 2147483647. If the VG already contains <code>ALLOCATION_MAXIMUM</code> or more volumes, no additional volumes are borrowed from the AG. If no AG is defined, this parameter is meaningless.                                                                                                                                                                                                                                                                                     |
| <code>ALLOCATION_MINIMUM</code> | Specifies the minimum size in number of volumes to which a VG can shrink by returning volumes to its AG. The minimum and default are 0 and the maximum is the value of <code>ALLOCATION_MAXIMUM</code> . If the VG already contains <code>ALLOCATION_MINIMUM</code> or fewer volumes, no additional volumes are returned to the AG. If no AG is defined, this parameter is meaningless.                                                                                                                                                                                                                                                |
| <code>KILL_WC_IF_DEMAND</code>  | Specifies whether or not an idle write child will be terminated immediately if there is demand for the drive. By default, one write child per VG is allowed to stay alive for a short period of time, even if there is demand for a drive, and even if the <code>MAX_IDLE_PUT_CHILDREN</code> value is 0. (If the <code>MAX_IDLE_PUT_CHILDREN</code> parameter is set to a nonzero value, that number of write children will be allowed to stay alive after the interim time has passed, so long as the drive is not in demand.) You can set this parameter to <code>ON</code> or <code>OFF</code> . The default is <code>OFF</code> . |
| <code>CHECKSUM_TYPE</code>      | Specifies the type of checksum algorithm to use when writing new tapes. Possible values are: <ul style="list-style-type: none"><li>• <code>crc32c</code> specifies the CRC32C checksum algorithm, which is required for the logical block protection feature (see <code>LOGICAL_BLOCK_PROTECTION</code> below). You must use the default setting for <code>WRITE_CHECKSUM</code> (<code>ON</code>) when specifying this value (see "drivegroup Object Parameters" on page 397). Any parallel data-mover nodes that use tapes in this VG must be running a version of the DMF software</li></ul>                                        |

that supports this checksum type. `crc32c` is the default for JBFS volumes.

---

**Note:** Using `crc32c` may set the actual size of the blocks written to the tape to be 4 bytes fewer than the `BLOCK_SIZE` value (see "drivegroup Object Parameters" on page 397).

---

- `legacy` specifies the original checksum algorithm used with DMF. `legacy` is the default for all other volume types.

#### DRIVE\_MAXIMUM

Specifies the maximum number of drives that this VG is allowed to use simultaneously. The maximum value for this parameter is 100; the default is the DG `DRIVE_MAXIMUM` (see "drivegroup Object Parameters" on page 397).

If you specify a negative value for the VG `DRIVE_MAXIMUM`, it will be added to the value used for the DG `DRIVE_MAXIMUM` and the sum will be the effective maximum for this VG.

However, the number of drives actually used is the least of the following:

- The VG `DRIVE_MAXIMUM` effective value
- The DG `DRIVE_MAXIMUM` effective value
- The number of usable drives

For example, suppose that the VG `DRIVE_MAXIMUM` is -1 and the DG `DRIVE_MAXIMUM` is -2. If there are 10 usable drives, then up to 7 of them will be available to this VG. If a drive is then configured down, at that point up to 6 will be available to this VG.

#### FORWARD\_RECALLS

Specifies whether or not a recall should be directed to another VG or MSP if the volume required for the recall is unavailable because it is being written to. If no other VG or MSP can satisfy the request, it will be handled by this VG. Use of this parameter may cause additional

volume mounts because the decision whether to forward a recall depends on whether the volume is being written at the time the recall request is received. You can set this parameter to ON or OFF. The default is OFF.

For more information about the use of this parameter in conjunction with tapes that have been exported from a library, see "OpenVault and Out-of-Library Tapes" on page 185. For more information about recalling from volumes being written, see GET\_WAIT\_TIME in "volumegroup Object Parameters" on page 411.

FULL\_ZONE

Limits when requests are flushed to a mounted volume that is not writing to a zone. This applies only during the short period of time when one write child per VG is allowed to say alive, even if there is demand for a drive, and even if the MAX\_IDLE\_PUT\_CHILDREN value is 0; after this time expires, FULL\_ZONE is not considered. If FULL\_ZONE is set ON, requests are flushed only when a full zone has accumulated; otherwise, requests are flushed as they arrive. (Note that requests are always flushed in the following circumstances: if the write child starts, if they are queued when a zone is completed, if TIMEOUT\_FLUSH time has passed, or if a dmdidle command has been issued. The FULL\_ZONE setting does not impact any of these actions). You can set this parameter to ON or OFF. The default is OFF.

GET\_WAIT\_TIME

Limits the amount of time (in seconds) that DMF will continue writing to a volume after receiving a recall request for that volume. In the case where there is queued writing work, the process writing to a volume will stop writing after it has finished a zone, providing a recall request for the volume has been queued for at least GET\_WAIT\_TIME seconds. If socket merges are taking place, it is possible that a few additional chunks may be written after the end of the zone before writing to the volume is stopped (depending on the size of the chunks). The legal range of values is 600 - 2147483647; the default is 2147483647.

---

To minimize extra volume mounts and the number of partial volumes created, do not make this value too small. Other requests may be queued before the recall request, therefore it may not proceed immediately after DMF stops writing to the volume. Also see `FORWARD_RECALLS` for more information about recalling from a volume that is being written.

`HFREE_TIME` Specifies the minimum number of seconds that a volume no longer containing valid data must remain unused before the VG overwrites it. The default is 172800 seconds (2 days) and the minimum is 0.

---

**Note:** If you are using this `volume` object for integrated backups, SGI recommends that you set `HFREE_TIME` to 1209600 (2 weeks). See "Consideration for Integrated Backups: Restored Database May Point to Freed Space" on page 160.

---

When an LS removes all data from a volume, it sets the `hfree` (hold free) flag bit in the volume's VOL record in the LS database to prevent that volume from being immediately reused. The next time that the LS scans the database for available volumes that can be assigned to volume groups after `HFREE_TIME` seconds have passed, the LS clears the `hfree` flag, allowing the volume to be rewritten. If `HFREE_TIME` is set to 0, the LS will never clear `hfree`, so an unused volume will not be reused until you clear its `hfree` flag manually. For a description of how to set and clear the `hfree` flag manually, see the `dmvoladm` man page.

`IMPORT_ONLY` Specifies if the VG is used for importing only. You can set this parameter to `ON` or `OFF`. The default is `OFF`. Set this parameter `ON` when the data in the VG is being migrated to another VG, perhaps as part of a media hardware upgrade. The daemon will not accept `dmput(1)`, `dmmove(8)`, or `dmarchive(1)` requests that specify a VG with this parameter enabled.

When the DMF daemon performs a complete file recall from an import-only VG and all other DMF copies also reside in import-only MSPs or VGs, it makes the file a regular file (rather than a dual-state file) and it soft-deletes the VG's copy of the file.

---

**Note:** An import-only VG should never be a member group of a `migrategroup` stanza.

---

LOGICAL\_BLOCK\_PROTECTION

Specifies whether logical block protection should be turned on when reading and writing tapes. This feature applies only to Oracle's StorageTek T10000C and later models that support data integrity validation (see the drive manufacturer's specifications for the required level of firmware). You can set this parameter to `ON` or `OFF`. The default is `OFF`.

If `ON` is specified, you must do all of the following:

- Use a supported drive
- Set `CHECKSUM_TYPE` to `crc32c` in the `volumegroup` stanza
- Use the default setting for `WRITE_CHECKSUM` (`ON`) in the `drivegroup` stanza (see "drivegroup Object Parameters" on page 397)

Otherwise, an error message is logged.

MAX\_CHUNK\_SIZE

Specifies the size of the chunk into which the VG should break up large files as it writes data to secondary storage. If a file is larger than this size, it is broken up into pieces of the specified size. Depending on other activity, more than one write child may be used to write the data to secondary storage. If `MAX_CHUNK_SIZE` is 0 (the default), the VG breaks a file into chunks only when an end-of-volume is reached. By default, the unit of measure is bytes; see "Units of Measure" on page 275. If you set this parameter in a Parallel DMF configuration where drives

in the `drivegroup` are usable from more than one node, then you should also set `MULTITAPE_NODES`; see "drivegroup Object Parameters" on page 397.

`MAX_IDLE_PUT_CHILDREN` Specifies the maximum number of idle write child (`dmatwc`) processes that will be allowed simultaneously for a VG. The maximum is the value of `MAX_PUT_CHILDREN` for the VG. The minimum and default are 0. If you specify a non-zero value, idle `dmatwc` processes will be allowed to stay alive, with a volume mounted, for a maximum of `PUT_IDLE_DELAY` seconds. During this time, if sufficient migrates arrive to fill a zone, they can be given to an idle `dmatwc` process.

---

**Note:** If the drive is needed for other work, there may be additional delay caused by the time needed to rewind and unmount the tape associated with the idle process. There may be times when the number of idle write children will exceed this value; for example, if socket merges are occurring or immediately after a `dmatwc` process completes a zone. If you configure `MAX_IDLE_PUT_CHILDREN`, you must choose its value and the value of `PUT_IDLE_DELAY` with the following in mind:

- OpenVault: DMF can take several minutes to respond when a drive is needed for some purpose other than a recall or migrate (for example, for a `dmatsnf` or `xfsdump` request)
- TMF: DMF will not notice that a drive is needed for another purpose

---

`MAX_PUT_CHILDREN` Specifies the maximum number of write child (`dmatwc`) processes that will be scheduled simultaneously for this VG.

The maximum is the DG `MAX_PUT_CHILDREN` effective value (if specified) or else the DG `DRIVE_MAXIMUM` effective value. The minimum is 1. (A negative value is invalid.)

The default is the DG `MAX_PUT_CHILDREN` value, if specified. If you do not configure the DG `MAX_PUT_CHILDREN`, the default is the same as the VG `DRIVE_MAXIMUM` value.

However, the number of process actually scheduled is the least of the following:

- The VG `MAX_PUT_CHILDREN` effective value
- The DG `MAX_PUT_CHILDREN` effective value
- The VG `DRIVE_MAXIMUM` effective value
- The number of usable drives

---

**Note:** If you are using this `volumegroup` object for integrated backups, SGI recommends a value of 1 so that the dump data will be appended to a single tape if possible.

---

Also see "Configure Appropriately for SGI 400 VTL or COPAN MAID Shelves" on page 109.

`MERGE_CUTOFF`

Specifies a limit at which the VG will stop scheduling volumes for merging. This number refers to the sum of the active and queued mover children that are generated from gets, puts, and merges (that is, the `dmatwc` and `dmatrc` processes). The default value for this option is the value used by the `volumegroup` object for `DRIVE_MAXIMUM`. This means that if sparse volumes are available, the VG will create `DRIVE_MAXIMUM` number of children, thus using resources efficiently. However, if any recall requests arrive for that VG, they will be started before new merges. Setting this number below `DRIVE_MAXIMUM` reserves some volumes for recalls at the expense of merge efficiency. Setting this number above `DRIVE_MAXIMUM` increases the priority of merges relative to recalls. The minimum value is 2.

`MERGE_THRESHOLD`

Specifies the integer percentage of active data on a volume less than which DMF will consider a volume to



---

|                              |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
|------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                              | <p>be sparse and allow merging; a value of 0 prohibits merging. This parameter overrides the <code>THRESHOLD</code> parameter (defined in a <code>taskgroup</code> stanza) for this VG, which allows each VG to have a different sparse volume threshold. If a VG is part of a fast-mount cache, you must set this parameter to 0. The default is the <code>THRESHOLD</code> parameter; see "taskgroup Object Parameters" on page 312.</p>                                                                                   |
| <code>MIN_VOLUMES</code>     | <p>Specifies the minimum number of unused volumes that can exist in the LS database for this VG without operator notification. If the number of unused volumes falls below <code>MIN_VOLUMES</code>, the operator is asked to free-up new volumes. The minimum is 0, the maximum is 2147483647, and the default is 10. If a VG has an AG configured, <code>MIN_VOLUMES</code> is applied to the sum of the number of unused volumes in the VG and in its AG subject to any <code>ALLOCATION_MAXIMUM</code> restrictions.</p> |
| <code>PUT_IDLE_DELAY</code>  | <p>Specifies the number of seconds that an idle write child (<code>dmatwc</code>) process will be allowed to stay alive. The default value is 30 seconds.</p> <hr/> <p><b>Note:</b> If you configure <code>PUT_IDLE_DELAY</code>, you should also specify <code>MAX_IDLE_PUT_CHILDREN</code> and consider the implications of these values on other work that may be needed for the drive. See the <b>Note</b> under <code>MAX_IDLE_PUT_CHILDREN</code>.</p> <hr/>                                                           |
| <code>PUTS_TIME</code>       | <p>Specifies the minimum number of seconds that a VG waits after it has requested a drive for a write child before it tells a lower priority child to go away. The default is 3600 seconds.</p>                                                                                                                                                                                                                                                                                                                              |
| <code>READ_IDLE_DELAY</code> | <p>Specifies the number of seconds that an idle read child (<code>dmatrc</code>) can wait before being told to exit. If other DMF requests are waiting for a drive, the read child may be told to exit before <code>READ_IDLE_DELAY</code> seconds have passed. The <code>drivegroup</code> stanza may also specify <code>READ_IDLE_DELAY</code>; the value specified in the <code>volume</code> stanza overrides the value in the <code>drivegroup</code> stanza. The default value of</p>                                  |

READ\_IDLE\_DELAY is the value that is specified in the drivegroup stanza (see "drivegroup Object Parameters" on page 397).

READ\_TIME

Specifies the interval (in seconds) after which the VG will evaluate whether a read child should be asked to go away (even if it is in the middle of recalling a file) so that a higher priority child can be started. If READ\_TIME is 0, the VG will not do this evaluation. The default is 0.

RESERVED\_VOLUMES

Defines the number of remaining empty volumes that will cause the VG to stop accepting migration requests:

- If merging is required for the VG, the reserved volumes will be used for merging. Reserving volumes prevents the situation where all volumes become full and there are no volumes available for merging.
- If the VG is in an MG, the requests will be sent to another VG in the MG. This enables an MG to avoid queuing requests to a full VG when there are available volumes in another VG.

When the number of empty, writable volumes drops below this threshold, the VG will fail migrations. If the migration target was not in an MG, `dmfsfree` or `dmmigrate` may try repeatedly to migrate the file and DMF logs may grow to a very large size.

Set RESERVED\_VOLUMES as follows:

| Setting | Circumstance                                                                                                                                                                                                    |
|---------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 0       | For a VG that is an independent member of a fast-mount cache (that is, this VG is listed in the <code>CACHE_MEMBERS</code> parameter, see "fastmountcache Object Parameters" on page 390). This is the default. |

- 
- 1 For every VG that is part of an MG in a fast-mount cache configuration (that is, the MG is listed in `CACHE_MEMBERS`)
- 1 or more Either of the following:
- For all VGs except the last in an MG that is not part of a fast-mount cache and that has a `ROTATION_STRATEGY` of `SEQUENTIAL`
  - For a VG on a COPAN shelf that is used as secondary storage
- 

**Note:** If you set this parameter is set to a non-zero value, you should set `EXPORT_METRICS` to `ON` (see "base Object" on page 277).

---

`REWIND_DELAY`

Specifies the number of seconds that an idle read child (`dmatrc`) can wait before rewinding. If other DMF requests are waiting for a drive, the read child may rewind before `REWIND_DELAY` seconds have passed. The maximum is the value of `READ_IDLE_DELAY`. `REWIND_DELAY` may also be specified in the `drivegroup` stanza; if `REWIND_DELAY` is specified in the `drivegroup` stanza but not in the `volume` stanza, then the `drivegroup` value is used (see "drivegroup Object Parameters" on page 397). If `REWIND_DELAY` is not specified in either stanza, then the default is the minimum of:

$$\{2, \text{READ\_IDLE\_DELAY}/2\}$$

If an idle read child must rewind the volume before the drive can be used to service other DMF requests, that will delay the servicing of those requests; therefore you should use caution when increasing this parameter.

`RUN_TASK`

See the description of `RUN_TASK` in "taskgroup Object Parameters" on page 312. Also see "Automated Maintenance Tasks" on page 175.

|               |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
|---------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| TASK_GROUPS   | Names the <code>taskgroup</code> objects that contain tasks the VG should run. By default, no tasks are run. The only defined tasks that can be run in a VG <code>taskgroup</code> are <code>run_tape_merge.sh</code> and <code>run_merge_stop.sh</code> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| TIMEOUT_FLUSH | Specifies the number of minutes after which the VG will flush files to secondary storage, even if the flush does not produce a full volume zone. The minimum is 0 (that is, do not flush based on time), the maximum is 35791394, and the default is 120 minutes.<br><br>See also "Appropriately Force Small Files to Migrate" on page 107.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
| VOL_MSG_TIME  | Specifies the minimum interval (in seconds) between operator notifications for low-volume and no-volume conditions for this VG. DMF will send at most one message for each occurrence of a low-volume condition and one message for each occurrence of a no-volume condition. Volumes that are actively being used are not considered available, and so a VG may fall below the low-volume or no-volume threshold, and then as the volumes are no longer being used, it may rise above the threshold. This can trigger frequent notifications when the VG is close to the threshold. You can use this parameter to reduce the number of messages sent. Additional notifications may be sent when the VG has no writable volumes at all or when the number of empty + partial volumes falls below the threshold. The default value is 86400 seconds (24 hours), the minimum value is 0, and the maximum value is 2147483647. Also see the <code>MIN_VOLUMES</code> parameter in "drivegroup Object" on page 395 |

**ZONE\_SIZE**

Specifies approximately how much data the write child should put in a zone. The write child adds files and chunks to a zone until the data written equals or exceeds this value, at which time it writes a volume mark and updates the database.

The VG also uses zone size to determine when to start write children and the number of write children to start. The minimum is 1000000 bytes and the maximum is 1000000000000000, and the default is 50000000 bytes (or 50m). By default, the unit of measure is bytes; see "Units of Measure" on page 275. For more information about zone size, also see "Media Concepts" on page 534

---

**Note:** It is critical that the zone size is appropriate for the media speed and average data compression rate at your site. A value that is too small can cause poor write performance because a volume mark is written at the end of each zone; a value that is too large can reduce parallelism when migrating files. See "Improve Drive Performance with an Appropriate VG Zone Size" on page 105.

The zone size influences the required cache space. The value for the `CACHE_SPACE` parameter should be at least twice the value used for `ZONE_SIZE`. Increasing the `ZONE_SIZE` value without also increasing `CACHE_SPACE` could cause volume merging to become inefficient. Merges could have problems if the `ZONE_SIZE` value is larger than the `CACHE_SPACE` value. For more information about `CACHE_SPACE`, see "libraryserver Object Parameters" on page 393.

See also "Appropriately Force Small Files to Migrate" on page 107

---

**volume group Object Example with an AG**

You can include an optional AG to provide a logical pool of additional volumes that are available to multiple VGs. These volumes will automatically be transferred to a

given VG as they are needed. When free, they can be immediately returned to the AG, making them eligible for use by another VG. This movement of volumes in and out of the AG is subject to the restrictions imposed by `HFREE_TIME`, `ALLOCATION_MAXIMUM` and `ALLOCATION_MINIMUM`.

To identify the AG for given VG, include the `ALLOCATION_GROUP` parameter within its `volumegroup` object. Normally, you will use one AG to serve multiple VGs by including the same `ALLOCATION_GROUP` parameter value in the definition of multiple `volumegroup` objects.

When you add a group of volumes to the VOL database, you can explicitly assign them to a specific AG by using the `dmvoladm (8)` command. If a VG has free volumes at the time when you add an AG to its stanza, those free volumes will automatically move into the AG (subject to the restrictions imposed by the configuration parameters `ALLOCATION_MAXIMUM` and `ALLOCATION_MINIMUM`).

---

**Note:** Any volume that is assigned to an AG must be usable by any of the VGs that will use the AG. That is, you must ensure that volumes assigned to the AG are mountable on drives in the same DG as any VG that references the AG.

---

An `ALLOCATION_GROUP` name cannot be the same as a `volumegroup` object name.

A VG must define the `ALLOCATION_GROUP` option in order to use an AG

**Example 7-30** `volumegroup` example with an AG

Do the following:

1. *(Optional)* Assign the volumes to the AG when you add them to the VOL database by using the `dmvoladm(8)` command:

```
# dmvoladm -l LS -c "create VSNs volgrp AG"
```

where:

| <b>Option</b>     | <b>Description</b>                                                         |
|-------------------|----------------------------------------------------------------------------|
| <code>LS</code>   | Specifies the name of the LS that owns the VOL records                     |
| <code>VSNs</code> | Specifies one VSN or a range of VSNs separated by the hyphen (-) character |
| <code>AG</code>   | Specifies the AG to which VSNs will be assigned                            |

---

**Note:** The `volgrp` field keyword specifies either a VG name or an AG name.

---

For example, the following line would assign volumes with the VSNs X04000 through X04010 to the AG `ag1`:

```
# dmvoladm -l ls1 -c "create X04000-X04010 volgrp ag1"
```

For more information, see the `dmvoladm(8)` man page.

2. Include the AG in the DMF configuration file according to the information in "volumeobject Object" on page 410.
  - a. Add the `ALLOCATION_GROUP` parameter to the `volumeobject` stanza for each VG that should use the pool of volumes. For example, the following extract shows that `ag1` will supply volumes to both `vg1` and `vg2`:

```
define  vg1
        TYPE                volumeobject
        ALLOCATION_GROUP     ag1
enddef

define  vg2
        TYPE                volumeobject
        ALLOCATION_GROUP     ag1
enddef
```

---

**Note:** An AG only requires an `allocationgroup` stanza if you wish to change its `VOL_MSG_TIME` setting.

---

- b. Define the `ALLOCATION_MAXIMUM` and `ALLOCATION_MINIMUM` parameters as needed in the `volumeobject` stanza to restrict the size of the VG.
3. (Optional) To change the minimum interval between operator notifications for low-volume and no-volume conditions for the AG to 48 hours (172800 seconds), you could add the optional `allocationgroup` stanza:

```
define  ag1
        TYPE                allocationgroup
        VOL_MSG_TIME       172800
enddef
```

For a more complete example, see "Example: LS with a Resource Watcher, Two DGs, and an AG" on page 436.

### **volumegroup Object Example Overriding drivegroup Settings**

The following excerpts illustrate how setting values in the `volumegroup` stanza override the `drivegroup` settings. Suppose you have the following:

```
define dg1
    TYPE                drivegroup
    VOLUME_GROUPS       vg1 vg2
    MOUNT_SERVICE_GROUP dg_c00
enddef

define vg1
    TYPE                volumegroup
    READ_IDLE_DELAY     0
enddef

define vg2
    TYPE                volumegroup
enddef
```

The default for `REWIND_DELAY` depends upon the setting for `READ_IDLE_DELAY`:

- For `vg1`, `READ_IDLE_DELAY` is set to 0. Therefore, the default value used for `REWIND_DELAY` is calculated by using the minimum of 2 and  $READ\_IDLE\_DELAY/2$  (in this case  $0/2$ ), making the default 0.
- For `vg2`, `READ_IDLE_DELAY` is not explicitly set. Therefore, the default value used for `REWIND_DELAY` is determined by using the default value of `READ_IDLE_DELAY` (5) in calculating the minimum of 2 and  $READ\_IDLE\_DELAY/2$  (in this case  $5/2$ ), making the default 2.

### **migrategroup Object**

This section discusses the following:

- "migrategroup Object Name" on page 427



- "migrategroup Object Summary" on page 427
- "migrategroup Object Parameters" on page 427
- "migrategroup Object Example with Multiple MGs" on page 431
- "Single migrategroup Object Example Using the ROUND\_ROBIN\_BY\_BYTES Strategy" on page 431
- "migrategroup Object Example Using the ROUND\_ROBIN\_BY\_FILES Strategy" on page 431

### migrategroup Object Name

The name of the migrategroup object is chosen by the administrator and may contain up to 8 uppercase or lowercase alphanumeric characters or underscores. It cannot begin with an underscore or contain any white space.

DMF supports up to 1024 MSPs, VGs and/or MGs.

### migrategroup Object Summary

Following is a summary of the potential parameters for the migrategroup object:

```
migrategroup
    TYPE
    GROUP_MEMBERS
    MULTIPLIER
    ROTATION_STRATEGY
```

### migrategroup Object Parameters



**Warning:** Never add, delete, or change the order of migrategroup stanzas while DMF is running; making changes of this type can result in data corruption or data loss.

---

There can be a migrategroup object for each set of MSPs/VGs that you want to treat as a single migration target.

A migrategroup object has the following parameters:

| <b>Parameter</b> | <b>Description</b>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
|------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| TYPE             | Specifies <code>migrategroup</code> (required name for this type of object). There is no default.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
| GROUP_MEMBERS    | <p>Specifies the list of MSPs/VGs that are members of this MG. Each migration request will result in exactly one copy being made to a member MSP/VG. The order of the group members is significant if you use a <code>ROTATION_STRATEGY</code> of <code>SEQUENTIAL</code>.</p> <p>The members must have their own <code>volumegroup</code> or <code>msp</code> stanzas in the configuration file. See:</p> <ul style="list-style-type: none"> <li>• "volumegroup Object" on page 410</li> <li>• "msp Object for a Cloud MSP" on page 448</li> <li>• "msp Object for an FTP MSP" on page 455</li> <li>• "msp Object for a Disk MSP" on page 466</li> <li>• "msp Object for a DCM MSP" on page 459</li> </ul> <p>Do not change this parameter while DMF is running.</p> <p>Do not include an import-only MSP/VG.</p> |
| MULTIPLIER       | <p>Specifies the amount of data to be sent to a group member relative to the other members listed for <code>GROUP_MEMBERS</code> when using <code>ROUND_ROBIN_BY_BYTES</code> or <code>ROUND_ROBIN_BY_FILES</code> for <code>ROTATION_STRATEGY</code>. The <code>MULTIPLIER</code> parameter can contain multiple floating-point values:</p> <ul style="list-style-type: none"> <li>• If the number of <code>MULTIPLIER</code> values equals the number of <code>GROUP_MEMBERS</code> entries, the values will be used in order for each specified member.</li> <li>• If there are fewer <code>MULTIPLIER</code> values than <code>GROUP_MEMBERS</code> entries, the last value will be repeated for the remaining members.</li> </ul>                                                                             |

- If there are more values in `MULTIPLIER` than there are entries in `GROUP_MEMBERS`, the extras are ignored (and `dmcheck` will issue a warning).
- If there is no `MULTIPLIER` parameter, then by default a value of 1 will be used for each MSP/VG in `GROUP_MEMBERS`. This results in an equal distribution of data among all non-full group members.

Do not change this parameter while DMF is running.

#### `ROTATION_STRATEGY`

Specifies the method by which a group member is selected for a migration request. Valid methods are:

- `ROUND_ROBIN_BY_BYTES` specifies that a certain number of bytes (defined by `MULTIPLIER`) are sent to each non-full MSP/VG member specified in `GROUP_MEMBERS`.
- `ROUND_ROBIN_BY_FILES` specifies that a certain number of files (defined by `MULTIPLIER`) are sent to each non-full MSP/VG member specified in `GROUP_MEMBERS`.
- `SEQUENTIAL` selects the first member in the list that is not already marked as full. This strategy is the default.

If `ROTATION_STRATEGY` is set to `SEQUENTIAL`, all `GROUP_MEMBERS` except the last must be able to report when they are full:

- For a disk MSP, you should specify `FULL_THRESHOLD_BYTES` to a non-zero value.
- For a VG, you should specify `RESERVED_VOLUMES`. See the recommendations in "Configure Appropriately for SGI 400 VTL or COPAN MAID Shelves" on page 109.
- Because a cloud MSP, disk cache manager (DCM) MSP, or FTP MSP never reports that it is full, if used

it must be the last member in the `GROUP_MEMBER` list.

For more information, see:

- "Configure Appropriately for SGI 400 VTL or COPAN MAID Shelves" on page 109
- "volume group Object" on page 410
- "msp Object for a Disk MSP" on page 466

Note the following for `ROUND_ROBIN_BY_BYTES` and `ROUND_ROBIN_BY_FILES`:

- The goal of these parameters is to optimize VG bandwidth.
- The amounts specified are rounded up to a whole file or byte boundary.
- When an MSP/VG becomes full, its multiplier is removed from the round-robin calculation and the files are spread among the remaining non-full MSPs/VGs. A disk MSP will only report that it is full when `FULL_BYTE_THRESHOLD` is configured; a VG will only report that it is full when `RESERVED_VOLUMES` is configured. (Cloud MSPs, FTP MSPs, and DCM MSPs never report that they are full. )
- The statistics for these strategies are stored in the `SPOOL_DIR` directory on a per-MG basis and are persistent in nature.

Do not change this parameter while DMF is running.

---

**Note:** VGs only report that they are full when `RESERVED_VOLUMES` is specified; disk MSPs only report that they are full when `FULL_THRESHOLD_BYTES` is specified as a non-zero value. Cloud MSPs, DCM MSPs, and FTP MSPs never report that they are full; therefore, if one of these MSPs is to be included as a `GROUP_MEMBER` in a `migrategroup` stanza using `SEQUENTIAL` for `ROTATION_STRATEGY`, it must be the last member.

---

**migrategroup Object Example with Multiple MGs****Example 7-31** migrategroup Object with Multiple MGs

```

define  mg1
        TYPE                migrategroup
        ROTATION_STRATEGY   ROUND_ROBIN_BY_BYTES
        GROUP_MEMBERS       vg1 vg2
endif

define  mg2
        TYPE                migrategroup
        ROTATION_STRATEGY   ROUND_ROBIN_BY_BYTES
        GROUP_MEMBERS       vg3 vg4
endif

```

Example 7-31 defines two MGs, mg1 and mg2.

There is no MULTIPLIER value, so the default value of 1 will be used.

**Single migrategroup Object Example Using the ROUND\_ROBIN\_BY\_BYTES Strategy****Example 7-32** Single migrategroup Using the ROUND\_ROBIN\_BY\_BYTES Strategy

```

define  mg3
        TYPE                migrategroup
        ROTATION_STRATEGY   ROUND_ROBIN_BY_BYTES
        GROUP_MEMBERS       vg1 vg2 vg3 vg4
        MULTIPLIER          1 1.5 2 1
endif

```

In Example 7-32, vg3 is sent twice as much data as vg1 or vg4, and vg2 is sent 1.5 times as much. If vg3 should become full, dmfdemon will still send 1.5 times more data to vg2 than to vg1 and vg4.

**migrategroup Object Example Using the ROUND\_ROBIN\_BY\_FILES Strategy****Example 7-33** migrategroup Using the SEQUENTIAL Strategy

```

define  mg5
        TYPE                migrategroup
        ROTATION_STRATEGY   SEQUENTIAL
        GROUP_MEMBERS       copan1 copan2 copan3 copan4 ltol

```

```
endif
```

In the above example, each MSP will be filled before advancing to the next (that is, `copan1` will be filled before advancing to `copan2`). After `copan4` is filled, any subsequent data overflows to the `lto1` library.

### resourcescheduler Object

This section discusses the following:

- "resourcescheduler Object Name" on page 432
- "resourcescheduler Object Summary" on page 432
- "resourcescheduler Object Parameters" on page 432

#### resourcescheduler Object Name

The name of the `resourcescheduler` object is chosen by the administrator and may contain up to 8 uppercase or lowercase alphanumeric characters or underscores. It cannot begin with an underscore or contain any white space.

#### resourcescheduler Object Summary

Following is a summary of the potential parameters for the `resourcescheduler` object:

```
resourcescheduler
    TYPE
    ALGORITHM
    PENALTY
    WEIGHT
```

#### resourcescheduler Object Parameters

The entries for a `resourcescheduler` object, one for each DG in a single library, has the following parameters:

| Parameter | Description                                                                                            |
|-----------|--------------------------------------------------------------------------------------------------------|
| TYPE      | Specifies <code>resourcescheduler</code> (required name for this type of object). There is no default. |

|           |                                                                                                                                                                                                                     |
|-----------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| ALGORITHM | Specifies the resource scheduling algorithm to be used, one of: <ul style="list-style-type: none"> <li>• <code>fifo</code> (“first-in, first out”)</li> <li>• <code>weighted_roundrobin</code> (default)</li> </ul> |
|-----------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

If you specify `weighted_roundrobin`, the following apply:

| Parameter | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
|-----------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| PENALTY   | Modifies the priority of requests from a VG that is not the next one preferred by the round-robin algorithm. It is a multiplier in the range 0.0–1.0. Low values reduce the priority of the requests from a VG, high values increase the priority of an urgent request from the VG. The default is 0.7 (an urgent request has a little more priority than the preferred request).                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| WEIGHT    | Assigns a weight to one or more VGs. The ratio of these weights to each other (within the one DG) determines the number of opportunities the VG has to obtain drives when they are needed. The weights are integers in the range 1–99 and they need not be unique. For efficiency reasons, small numbers are preferred, especially if large numbers of VGs are defined. If a given VG appears on multiple <code>WEIGHT</code> lines, the sum of the weights is used as the effective weight for that VG. Any VG that does not appear on a <code>WEIGHT</code> line is assigned the default of 5. If there are no <code>WEIGHT</code> lines, all VGs will use this default, resulting in a strict round-robin behavior. <p><code>WEIGHT</code> has the following format:</p> <pre><code>WEIGHT weight vg1 vg2 ...</code></pre> |

## resourcewatcher Object

This section discusses the following:

- "resourcewatcher Object Name" on page 434
- "resourcewatcher Object Summary" on page 434
- "resourcewatcher Object Parameters" on page 434

### resourcewatcher Object Name

The name of the `resourcewatcher` object is chosen by the administrator and may contain up to 8 uppercase or lowercase alphanumeric characters or underscores. It cannot begin with an underscore or contain any white space.

### resourcewatcher Object Summary

Following is a summary of the potential parameters for the `resourcewatcher` object:

```
resourcewatcher
    TYPE
    HTML_REFRESH
```

### resourcewatcher Object Parameters

The `resourcewatcher` object is needed only if you wish to change its parameter defaults; a reference to a resource watcher by the `libraryserver` object is sufficient to activate it.

The `resourcewatcher` object has the following parameters:

| Parameter    | Description                                                                                          |
|--------------|------------------------------------------------------------------------------------------------------|
| TYPE         | Specifies <code>resourcewatcher</code> (required name for this type of object). There is no default. |
| HTML_REFRESH | Specifies the refresh rate (in seconds) of the generated HTML pages. The default is 60.              |

### allocationgroup Object

The `allocationgroup` object is optional. You should specify it if you want to change the default value of its parameter. This section discusses the following:

- "allocationgroup Object Name" on page 435
- "allocationgroup Object Summary" on page 435
- "allocationgroup Object Parameters" on page 435



**allocationgroup Object Name**

The name of the `allocationgroup` object is chosen by the administrator and may contain up to 8 uppercase or lowercase alphanumeric characters or underscores. It cannot begin with an underscore or contain any white space. It must match the value of the `ALLOCATION_GROUP` parameter in the `volume` stanza; see "volume Object Parameters" on page 411.

**allocationgroup Object Summary**

Following is a summary of the potential parameters for the `allocationgroup` object:

```
allocationgroup
    TYPE
    VOL_MSG_TIME
```

**allocationgroup Object Parameters**

The `allocationgroup` object is needed only if you wish to change its parameter defaults. A reference to an `ALLOCATION_GROUP` parameter by a `volume` object is sufficient to activate an AG.

The `allocationgroup` object has the following parameters:

| <b>Parameter</b>          | <b>Description</b>                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
|---------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>TYPE</code>         | Specifies <code>allocationgroup</code> (required name for this type of object). There is no default.                                                                                                                                                                                                                                                                                                                                                                            |
| <code>VOL_MSG_TIME</code> | Specifies the minimum interval (in seconds) between operator notifications for low-volume and no-volume conditions for this AG. DMF will send at most one message for each occurrence of a low-volume condition and one message for each occurrence of a no-volume condition. An AG's low-volume threshold depends on the number of unused volumes in the VGs that use it. You can use this parameter to further reduce the number of messages sent. The default value is 86400 |

seconds (24 hours), the minimum value is 0, and the maximum value is 2147483647.

## Examples of Configuring an LS

This section contains the following:

- "Example: LS with a Resource Watcher, Two DGs, and an AG" on page 436
- "Example: LS for Fast-Mount Cache" on page 439

### Example: LS with a Resource Watcher, Two DGs, and an AG

Example 7-34 defines an LS containing a default resource watcher, two DGs, and one AG that serves multiple VGs.

---

**Note:** Example 7-34 does not use all of the possible options for configuring a `libraryserver` object.

---

#### Example 7-34 `libraryserver` Object with a Resource Watcher, Two DGs, and an AG

```
define ls1
    TYPE                libraryserver
    COMMAND             dmatls
    DRIVE_GROUPS        dg1 dg2
    CACHE_SPACE         500m
    TASK_GROUPS         ls_tasks
    WATCHER             rw
enddef

define dg1
    TYPE                drivegroup
    VOLUME_GROUPS       vg_1 vg_2
    MOUNT_SERVICE       openvault
    MOUNT_SERVICE_GROUP ultrium3grp
    OV_INTERCHANGE_MODES compression
    DRIVE_SCHEDULER     rs
    DRIVES_TO_DOWN      2
    REINSTATE_DRIVE_DELAY 60
enddef
```

```

define dg2
    TYPE                drivegroup
    VOLUME_GROUPS       vg_ul4
    MOUNT_SERVICE       openvault
    MOUNT_SERVICE_GROUP ultrium4grp
    OV_INTERCHANGE_MODES compression
    DRIVES_TO_DOWN     2
    REINSTATE_DRIVE_DELAY 60
endef

define rs
    TYPE                resourcescheduler
    WEIGHT              10    vg_1
    WEIGHT              5    vg_2
endef

define vg_1
    TYPE                volumegroup
    ALLOCATION_GROUP     ag_ult3
endef

define vg_2
    TYPE                volumegroup
    ALLOCATION_GROUP     ag_ult3
    DRIVE_MAXIMUM       2
endef

define vg_ul4
    TYPE                volumegroup
endef

```

In the above example:

- The `define` value must match the value set previously in the `LS_NAMES` or `MSP_NAMES` parameter of the `dm Daemon` object.
- `COMMAND` is set to `dmatls`, as required.
- There are two DGs, `dg1` and `dg2`:
  - `dg1` contains two VGs (`vg_1` `vg_2`) sharing an AG. A resource scheduler is defined to give primary `vg_1` twice the priority of secondary `vg_2` when

competing for drives. The `volumegroup` objects are slightly different, reflecting that `vg_2` is usually write-only.

The `vg_2` object specifies that it can use at most two tape drives, so that other drives in the `dg1` DG will be immediately available for use by `vg_1` when it needs them.

- `dg2` contains a single VG, `vg_ul4`.

For each VG listed for a `VOLUME_GROUPS` parameter of a `drivegroup` object, there must be a corresponding `volumegroup` object.

- The LS can use 500 million bytes of disk cache space when merging chunks from sparse volumes.
- The `ls_tasks` object (defined elsewhere) will specify how periodic maintenance tasks are completed. For more information, see "LS Tasks" on page 441.
- The `rw` resource watcher allows observation of LS operation through a web browser. Assuming that `SPOOL_DIR` was set in the base object to be `/dmf/spool`, the URL is `file://dmf/spool/ls/_rw/ls.html`. Text files are generated in the same directory as the HTML files. (You should define a `resourcewatcher` object only if you want to change its default parameters. See "resourcewatcher Object Parameters" on page 434.)
- OpenVault is the mounting service. (Because OpenVault is the default mounting service, this line could be omitted.)
- For `dg1`, OpenVault will use the group name `ultrium3grp`; for `dg1`, OpenVault will use the group name `ultrium4grp`.
- Both drives will be used in compression mode.
- `dg1` overrides the default drive scheduler behavior by referring to an object named `rs`. The `rs` object is a `resourcescheduler` object; it specifies that when there are more requests for drives than there are drives in the DG, `vg_1` (with a weight of 10) is to be given access twice as often as `vg_2` (with a weight of 5).

---

**Note:** The ratio of the numbers is important, but the exact values are not; the values 40 and 20 would have the same affect.

---

- Each DG can have at most two drives down temporarily for up to 60 minutes; this allows for recovery from I/O errors if the drives are faulty and will result in an

operation that is more reliable. If a drive goes down, the administrator is e-mailed so that maintenance can be performed.

- There is an AG for Ultrium 3 tapes called `ag_ult3` that is used by VGs `vg_1` and `vg_2` (there is no separate configuration stanza for an AG). No AG is defined for Ultrium 4 tapes in VG `vg_ult4`. The volumes have been assigned to `ag_ult3` by using the `dmvoladm(8)` command, as described in "volumegroup Object Example with an AG" on page 423.

In this case, the volumes will automatically be transferred to either `vg_1` or `vg_2` as they are needed and can be immediately returned from the VG to the AG (subject to the restrictions imposed by the configuration parameters `ALLOCATION_MAXIMUM` and `ALLOCATION_MINIMUM`, which in this case are not defined and therefore use their default values of no allocation maximum and an allocation minimum of 0).

#### Example: LS for Fast-Mount Cache

Example 7-35 shows various extracts from the configuration file that highlight some of the configuration objects that are specifically associated with the fast-mount cache feature, using two shelves of a COPAN MAID cabinet as the fast-mount cache in conjunction with secondary storage on a physical tape library.

#### Example 7-35 `libraryserver` and Associated Objects for Fast-Mount Cache

```
define daemon
    TYPE                dmdaemon
    MIGRATION_LEVEL     auto
    LS_NAMES             copan_ls tape_ls
    TASK_GROUPS         daemon_tasks dump_tasks fmc_task
    MOVE_FS             /dmf/move
enddef

define copan_ls
    TYPE                libraryserver
    DRIVE_GROUPS        dg_c00 dg_c01
    COMMAND             dmatls
enddef

define vg_policy
    TYPE                policy
```

## 7: DMF Configuration File

---

```
        SELECT_VG          mg_fmc mg0 mg1
enddef

define copan_fmc
    TYPE                  fastmountcache
    CACHE_MEMBERS         mg_fmc
enddef

define mg_fmc
    TYPE                  migrategroup
    GROUP_MEMBERS         vg_c00 vg_c01
    ROTATION_STRATEGY    ROUND_ROBIN_BY_BYTES
enddef

define dg_c00
    TYPE                  drivegroup
    VOLUME_GROUPS         vg_c00
    MOUNT_SERVICE         openvault
    MOUNT_SERVICE_GROUP  dg_c00
enddef

define vg_c00
    TYPE                  volumegroup
    MERGE_THRESHOLD      0
    RESERVED_VOLUMES    1
enddef

define fmc_task
    TYPE                  taskgroup
    RUN_TASK              $ADMINDIR/run_fmc_free.sh at 23:00
    FMC_NAME              copan_fmc
    FREE_VOLUME_MINIMUM  10
    FREE_VOLUME_TARGET   20
enddef
```

In the above example:

- There are two LSs:
  - One for the fast-mount cache (copan\_ls), which must be listed first

- One for the secondary-storage data copy (`tape_ls`)
- The `dmdaemon` object has a task for the fast-mount cache operations (`fmc_task`).
- There are two DGs (`dg_c00` and `dg_c01`) associated with the LS for the fast-mount cache.
- The MG for the fast-mount cache (`mg_fmc`) is included in the VG selection policy as are two secondary-storage targets (`mg0` and `mg1`).
- There is an object of type `fastmountcache` (named `copan_fmc`) that has the `mg_fmc` MG as the only member.
- The `mg_fmc` MG contains two VGs (`vg_c00` and `vg_c01`).
- The `dg_c00` DG manages pool of drives in the `vg_c00` volume.
- Volumes within the `vg_c00` VG will never be merged because the `MERGE_THRESHOLD` is set to 0, as required for volumes in a fast-mount cache.
- The `RESERVED_VOLUMES` parameter is set to 1 in `vg_c00` to ensure proper distribution of data, because `vg_c00` is part of the `mg_fmc` MG listed for `CACHE_MEMBERS`.
- Volumes in the fast-mount cache VGs (`vg_c00` and `vg_c01`) will be freed as required by the `run_fmc_free.sh` task at 11:00 PM each day. When fewer than 10% of the volumes in the fast-mount cache are free, DMF will free the volumes with the oldest write dates until 20% of the volumes are free. For more information, see "taskgroup Object Example for Fast-Mount Cache Tasks" on page 339.

---

**Note:** For brevity, this example does not show the definitions for `vg_c01`, `dg_c01`, `mg0`, `mg1`, and `tape_ls`.

---

## LS Tasks

This section discusses the following:

- "Overview of LS Tasks" on page 442
- "LS taskgroup Object with One VG" on page 443
- "LS taskgroup Object with Multiple VGs" on page 444

## Overview of LS Tasks

You can configure parameters for how the LS daemon performs the following maintenance tasks:

- Merging sparse volumes with the `run_tape_merge.sh` task (for physical tapes, COPAN VTL virtual tapes, COPAN MAID volumes, and JBFS volumes), and the `THRESHOLD`, `VOLUME_LIMIT`, and `DATA_LIMIT` parameters

---

**Note:** For a VG used as a fast-mount cache, do not configure merge tasks. See "Use Fast-Mount Cache Appropriately" on page 112.

---

- Stopping volume merges at a specified time with the `run_merge_stop.sh` task

Table 7-1 on page 305 provides a summary of automated maintenance tasks. For each of these tasks, you can configure when the task is run. For merging sparse volumes, you must provide more information such as what determines that a volume is sparse and how many volumes can be merged at one time.

---

**Note:** The `run_remove_journals.sh` and `run_remove_logs.sh` tasks are configured as part of the `taskgroup` object for daemon tasks, but these tasks also clear the journals and logs for MSPs/LSs. These tasks are described in "taskgroup Object" on page 304.

The `run_daily_drive_report.sh`, `run_daily_tsreport.sh`, and `run_daily_report.sh` tasks should be configured as part of the `taskgroup` object for `dmdaemon` tasks. This is because there could be multiple LSs for which `run_daily_drive_report.sh` and `run_daily_tsreport.sh` create reports, and `run_daily_report.sh` reports on other things besides LS information (such as information about the managed filesystems).

---



---

## LS taskgroup Object with One VG

---

**Note:** When modifying sample RUN\_TASK parameters, you can comment out any tasks you do not want to run, but you should not change the pathnames or task names, such as \$ADMINDIR/run\_tape\_merge.sh.

---

### Example 7-36 taskgroup Object for LS with One VG

```
define libraryserver_tasks
    TYPE                taskgroup
    RUN_TASK             $ADMINDIR/run_tape_merge.sh on \
                        monday wednesday friday at 2:00
    THRESHOLD           50
    # VOLUME_LIMIT      20
    # DATA_LIMIT       5g
    RUN_TASK             $ADMINDIR/run_merge_stop.sh at 5:00
```

In the above example:

- The define value must match the value set previously for the TASK\_GROUPS parameter of the libraryserver object. In this case, libraryserver\_tasks.
- The run\_tape\_merge.sh task merges sparse volumes, using the following criteria to determine that a volume is sparse:
  - Its active data is less than 50% (THRESHOLD)
  - There is no limit to the number of volumes that can be selected for merging at one time, because the VOLUME\_LIMIT parameter is commented out. (If the comment character is removed, the limit will be 20 volumes.)

---

**Note:** This example uses the run\_merge\_stop.sh task used to control volume merging rather than the VOLUME\_LIMIT and DATA\_LIMIT parameters.

---

- There is no maximum limit on the amount of data that can be selected for merging at one time because the DATA\_LIMIT parameter is commented out. (If the comment character is removed, at most 5 GB can be selected for merging at one time.)
- The run\_merge\_stop.sh task will shut down volume merging at 5:00 AM every day. Merge requests that were assigned to mover processes will be allowed to complete.

For more information about `RUN_TASK` parameter, see "taskgroup Object Parameters" on page 312.

### LS taskgroup Object with Multiple VGs

For an LS, you can configure volume merging as either of the following:

- As part of the `libraryserver` object's `TASK_GROUPS` parameter. This permits volumes from any of the VGs in the LS to be marked as sparse. However, this can lead to drive scheduling and cache usage conflicts.
- As part of a `RUN_TASK` parameter in the `volume` object. This avoids the scheduling and conflict problems, but you must ensure that there is no overlap in the times that the various merge tasks run. This might become cumbersome when there are large numbers of VGs configured; in this case, you can use `run_merge_mgr.sh` rather than `run_tape_merge.sh`.

The `run_merge_mgr.sh` task establishes the needs of the VGs for more volumes, using their `MIN_VOLUMES` parameters as a guide to expected requirements. The task processes the most urgent requests first, minimizing interference with the production workload. To use this task, do the following:

1. Define a `taskgroup` object, which is referred to by the `drivegroup` object (not the `volume` or `libraryserver` object).
2. Specify a `RUN_TASK` parameter for `run_merge_mgr.sh` in the `taskgroup` object and (optionally) another for `run_merge_stop.sh`. You can also specify `MESSAGE_LEVEL`, `THRESHOLD`, `VOLUME_LIMIT`, and `DATA_LIMIT` parameters.
3. Ensure that the `libraryserver` object that refers to this DG has a `resourcewatcher` object defined via the `WATCHER` parameter.
4. For each `volume` object, confirm that the value of its `MIN_VOLUMES` parameter is realistic.

### LS Database Records

After you have added the LS information to the configuration file, use the `dmvoladm(8)` command with the `-m` option to create any missing directories with the proper labels and to create volume (VOL) and catalog (CAT) records in the LS database.

You can follow the steps in Procedure 7-1 for each LS that you have defined.



---

**Caution:** Each LS must have a unique set of VSNs.

---

**Procedure 7-1** Creating LS Database Records

The following procedure is shown as an example that assumes you have an LS called `ls1`. This LS contains a VG named `vg_pri`.

1. Enter the following command and it will respond as shown:

```
% dmvoladm -m ls1
dmvoladm: at rdm_open - created database libsrv_db
adm: 1>
```

The response is an informational message indicating that `dmvoladm` could not open an existing LS database, so it is creating a new and empty one. You should get this message the first time you use `dmvoladm` for an LS, but never again. The next line (`adm:1>`) is the prompt for `dmvoladm` directives.

2. Assume that you will use 200 volumes with VSNs `VA0001` through `VA0200`. After the prompt, enter the following directive:

```
adm:1> create VA0001-VA0200 vg vg_pri
```

---

**Note:** You are specifying the VG `vg_pri` for the volumes being added. It is also valid to specify an AG name instead of a VG name.

---

After entering this directive, you will receive 200 messages, one for each entry created, beginning with the following:

```
VSN VA0001 created.
VSN VA0002 created.
```

3. List all of the VSNs in the newly created library:

```
adm:2> list all
```

4. Complete setting up the LS:

```
adm:3> quit
```

## m<sub>SP</sub> Objects

This section discusses the following:

- "m<sub>SP</sub> Object Name" on page 446
- "NAME\_FORMAT Details" on page 446
- "m<sub>SP</sub> Object for a Cloud MSP" on page 448
- "m<sub>SP</sub> Object for an FTP MSP" on page 455
- "m<sub>SP</sub> Object for a DCM MSP" on page 459
- "m<sub>SP</sub> Object for a Disk MSP" on page 466

### m<sub>SP</sub> Object Name

The name of an m<sub>SP</sub> object (for a cloud, FTP, disk, or DCM MSP) is chosen by the administrator and may contain and up to 8 uppercase or lowercase alphanumeric characters or underscores. It cannot begin with an underscore or contain any white space.

### NAME\_FORMAT Details

The NAME\_FORMAT parameter consists of substitution strings to create a template for the names that are used in secondary storage. It applies to the following:

- Cloud MSP for S3 systems
- FTP MSP
- disk MSP
- DCM MSP

The default NAME\_FORMAT for all of the supported MSPs is %u/%b (*username/bfid*). However, this default may not work well in all circumstances, particularly for a large number of files in a given directory. You can use the substitution strings listed in Table 7-3 to create a template that is more appropriate for your site.

The NAME\_FORMAT value must include one of the following:

- %b (which will guarantee a unique filename)

- %2, %3, %4 in some combination

The default size allotted to the `NAME_FORMAT` value in the daemon database record is 34 bytes. This is large enough to accommodate the default for `NAME_FORMAT` if the user name is 8 or fewer characters (the `%b` value is always 24 characters). If you choose a set of strings that will evaluate to a field that is larger than 34 bytes, you may want to consider increasing the size of this record; see "Daemon Database Record Length" on page 173.

The `NAME_FORMAT` value is only used when files are being stored. After a file has been stored, the name is saved in the daemon database. This saved name is used to retrieve the file. This ensures that migrated files remain accessible even if they are renamed, if their owner changes, or if the `NAME_FORMAT` value changes. If you change the value, it affects only subsequent store operations.

Note the following considerations for specific MSPs:

- For the S3 cloud MSP, you can use the `%p` string to randomize the order of keys, which may improve performance for a bucket with a high ingest rate. For example, a `NAME_FORMAT` value of `%p%p/%b` will create keys that are randomly distributed according to their first two characters. For more information, see: <http://aws.amazon.com/articles/Amazon-S3/1904>
- For a disk MSP, DCM MSP, or FTP MSP, you can use the `%p` or the date- and time-related substitution strings to spread files over a large number of directories, to potentially minimize subsequent access times.
- For an FTP MSP that is implemented on a system other than one based on UNIX or Linux, the default may not work.

**Table 7-3** `NAME_FORMAT` Strings

| String Type  | String | Evaluates To                                                                                            |
|--------------|--------|---------------------------------------------------------------------------------------------------------|
| BFID strings | %1     | First set of 32 bits of the BFID in lowercase hexadecimal, which are always 8 pad characters (00000000) |
|              | %2     | Second set of 32 bits of the BFID in lowercase hexadecimal                                              |

| String Type       | String | Evaluates To                                                                                                                                             |
|-------------------|--------|----------------------------------------------------------------------------------------------------------------------------------------------------------|
|                   | %3     | Third set of 32 bits of the BFID in lowercase hexadecimal                                                                                                |
|                   | %4     | Fourth set of 32 bits of the BFID in lowercase hexadecimal                                                                                               |
|                   | %b     | BFID in lowercase hexadecimal (least-significant 24 characters) without the 8 pad characters found in the 8 most-significant characters of the full BFID |
| Ownership strings | %u     | User name of the file owner                                                                                                                              |
|                   | %U     | User ID of the file owner                                                                                                                                |
|                   | %g     | Group name of the file                                                                                                                                   |
|                   | %G     | Group ID of the file                                                                                                                                     |
| Date strings      | %d     | Current day of month (2 digits)                                                                                                                          |
|                   | %H     | Current hour (2 digits)                                                                                                                                  |
|                   | %m     | Current month (2 digits)                                                                                                                                 |
|                   | %M     | Current minute (2 digits)                                                                                                                                |
|                   | %S     | Current second (2 digits)                                                                                                                                |
|                   | %Y     | Last 2 digits of the current year (such as 03 for 2003)                                                                                                  |
| Percent string    | %%     | Literal % character                                                                                                                                      |
| Partition string  | %p     | A digit (0 through 9) derived from the BFID, producing an essentially random number; up to 9 %p strings are permitted                                    |

### **m<sub>SP</sub> Object for a Cloud MSP**

This section discusses the following:

- "m<sub>SP</sub> Object Summary for a Cloud MSP" on page 449
- "m<sub>SP</sub> Object Parameters for a Cloud MSP" on page 449
- "m<sub>SP</sub> Object Example for an S3 Cloud MSP" on page 453
- "m<sub>SP</sub> Object Example for a Scalify Cloud MSP" on page 454

**m<sub>sp</sub> Object Summary for a Cloud MSP**

Following is a summary of the potential parameters for the `msp` object for a cloud MSP:

```
msp
    TYPE
    CHILD_MAXIMUM
    CLOUD_BACKEND
    CLOUD_BASE_PATH
    CLOUD_BUCKET
    CLOUD_HOST
    CLOUD_PASSWORD
    CLOUD_REDUNDANCY
    CLOUD_USER
    COMMAND
    GUARANTEED_DELETES
    GUARANTEED_GETS
    MESSAGE_LEVEL
    NAME_FORMAT
    TASK_GROUPS
    WRITE_CHECKSUM
```

**m<sub>sp</sub> Object Parameters for a Cloud MSP**

To enable a cloud MSP, define an `msp` object for it in the DMF configuration file and include the name of that object on the `MSP_NAMES` or `LS_NAMES` parameter in the `dmdaemon` object.

The MSP checks the DMF configuration file just before it starts child processes. If the DMF configuration file changed, it is reread.

A cloud `msp` object has the following parameters:

| <b>Parameter</b>           | <b>Description</b>                                                                                                                     |
|----------------------------|----------------------------------------------------------------------------------------------------------------------------------------|
| <code>TYPE</code>          | Specifies <code>m<sub>sp</sub></code> (required name for this type of object). There is no default.                                    |
| <code>CHILD_MAXIMUM</code> | Specifies the maximum number of child processes that the MSP is allowed to fork. The legal range of values is 0–100; the default is 4. |

|                              |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
|------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                              | <p>If <code>CHILD_MAXIMUM</code> is nonzero, its value must be greater than the sum of <code>GUARANTEED_DELETES</code> and <code>GUARANTEED_GETS</code>.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| <code>CLOUD_BACKEND</code>   | <p>Specifies the backend used by this cloud instance, which determines how other cloud-specific parameters are interpreted. There is no default value. Legal values are:</p> <p><code>s3</code> Specifies Amazon Simple Storage Service (S3)</p> <p><code>scality</code> Specifies Scality RING</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                |
| <code>CLOUD_BASE_PATH</code> | <p>(S3 only) Specifies a string that is prefixed to the key (separated from the key by a slash <code>/</code> character) in all requests to S3. The string may not begin or end with a slash (<code>/</code>). By default, there is no prefix.</p> <p>A prefix may be useful if another application is sharing the same S3 bucket and you want to differentiate the keys that belong to data migrated by DMF. For example, if this parameter is set to <code>DMF</code>, the S3 key name would begin with <code>DMF/NAME_FORMAT</code>.</p>                                                                                                                                                                                                        |
| <code>CLOUD_BUCKET</code>    | <p>(S3 only) Specifies the name of the existing S3 bucket to use when storing files. There is no default for S3 systems.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| <code>CLOUD_HOST</code>      | <p>Specifies one or more domain names or IP addresses used to connect to the cloud, using the following format:</p> <p><code>hostname1[:port][,hostname2[:port]]</code></p> <p>You can specify multiple comma-separated addresses. Connections will be distributed in round-robin fashion, in an order that is randomized from the order specified. The cloud MSP will attempt to send requests to all of the addresses, ignoring any that fail to respond.</p> <p>You must provide at least one <i>host</i> value:</p> <ul style="list-style-type: none"><li>• S3: <i>host</i> specifies the address of the S3 service.</li><li>• Scality: <i>host</i> specifies the machines that are running the Scality <code>sproxyd</code> daemons</li></ul> |



|                    | The default for <i>port</i> varies by the cloud service:                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |          |             |         |                                                      |          |                                  |               |             |       |                                                                       |                    |                                                                    |
|--------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------|-------------|---------|------------------------------------------------------|----------|----------------------------------|---------------|-------------|-------|-----------------------------------------------------------------------|--------------------|--------------------------------------------------------------------|
|                    | <ul style="list-style-type: none"> <li>• S3: 80</li> <li>• Scality: 81</li> </ul>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |          |             |         |                                                      |          |                                  |               |             |       |                                                                       |                    |                                                                    |
| CLOUD_PASSWORD     | <p>Specifies the file containing password information to use on the cloud:</p> <ul style="list-style-type: none"> <li>• S3: specifies the location of the file that contains the Secret Access Key (required for S3)</li> <li>• Scality: specifies the file containing the password to use on the cloud host (required only if HTTP Basic Authentication is enabled on the cloud host; see the Scality documentation for details)</li> </ul> <p>If this file exists, it must be owned by <code>root</code> and only be accessible by <code>root</code>.</p>                                                                                                                                                                                                                                                                                                      |          |             |         |                                                      |          |                                  |               |             |       |                                                                       |                    |                                                                    |
| CLOUD_REDUNDANCY   | <p>Specifies the level of data redundancy that is requested from the cloud service for new files.</p> <p>Valid values for S3 are as follows:</p> <table> <thead> <tr> <th>S3 Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>reduced</td> <td>Specifies S3 <i>Reduced Redundancy Storage</i> (RRS)</td> </tr> <tr> <td>standard</td> <td>Specifies standard S3 redundancy</td> </tr> </tbody> </table> <p>The default for S3 is <code>standard</code>.</p> <p>Valid values for Scality are as follows:</p> <table> <thead> <tr> <th>Scality Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>1copy</td> <td>Specifies that only a single copy of the data is kept (no redundancy)</td> </tr> <tr> <td>2copies to 6copies</td> <td>Specifies the number of copies (from two to six) that will be kept</td> </tr> </tbody> </table> | S3 Value | Description | reduced | Specifies S3 <i>Reduced Redundancy Storage</i> (RRS) | standard | Specifies standard S3 redundancy | Scality Value | Description | 1copy | Specifies that only a single copy of the data is kept (no redundancy) | 2copies to 6copies | Specifies the number of copies (from two to six) that will be kept |
| S3 Value           | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |          |             |         |                                                      |          |                                  |               |             |       |                                                                       |                    |                                                                    |
| reduced            | Specifies S3 <i>Reduced Redundancy Storage</i> (RRS)                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |          |             |         |                                                      |          |                                  |               |             |       |                                                                       |                    |                                                                    |
| standard           | Specifies standard S3 redundancy                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |          |             |         |                                                      |          |                                  |               |             |       |                                                                       |                    |                                                                    |
| Scality Value      | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |          |             |         |                                                      |          |                                  |               |             |       |                                                                       |                    |                                                                    |
| 1copy              | Specifies that only a single copy of the data is kept (no redundancy)                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |          |             |         |                                                      |          |                                  |               |             |       |                                                                       |                    |                                                                    |
| 2copies to 6copies | Specifies the number of copies (from two to six) that will be kept                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |          |             |         |                                                      |          |                                  |               |             |       |                                                                       |                    |                                                                    |

ARC Specifies *Scality Advanced Resilience Configuration* (ARC)

The default for Scality is 3copies.

---

**Note:** SGI strongly recommends that you migrate at least two copies to secondary-storage targets in order to prevent file data loss in the event that a migrated copy is damaged. A given cloud can be a single point of failure, therefore redundant copies within one cloud do not sufficiently protect against data loss. SGI therefore highly recommends that you migrate data to a second location (to another cloud instance, tape, or disk).

---

|                    |                                                                                                                                                                                                                                                                                                                               |
|--------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| CLOUD_USER         | <p>Specifies the username information on the cloud host:</p> <ul style="list-style-type: none"> <li>• S3: specifies the Access Key ID (required)</li> <li>• Scality: specifies the cloud user (required only if HTTP Basic Authentication is enabled on the cloud host; see the Scality documentation for details)</li> </ul> |
| COMMAND            | <p>Specifies the binary file to execute in order to initiate this MSP. For the cloud MSP, this value must be dmcloudmsp. There is no default.</p>                                                                                                                                                                             |
| GUARANTEED_DELETES | <p>Specifies the number of child processes that are guaranteed to be available for processing delete requests. If CHILD_MAXIMUM is nonzero, its value must be greater than the sum of GUARANTEED_DELETES and GUARANTEED_GETS. The default is 1.</p>                                                                           |
| GUARANTEED_GETS    | <p>Specifies the number of child processes that are guaranteed to be available for processing dmget(1) requests. If CHILD_MAXIMUM is nonzero, its value must be greater than the sum of GUARANTEED_DELETES and GUARANTEED_GETS. The default is 1.</p>                                                                         |
| MESSAGE_LEVEL      | <p>Specifies the highest message level that will be written to the MSP log. It must be an integer in the range 0–6; the higher the number, the more messages written to the log file. The default is 2. For more information on</p>                                                                                           |

|                |                                                                                                                                                                                                                                 |
|----------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                | message levels, see Chapter 10, "Message Log Files" on page 507.                                                                                                                                                                |
| NAME_FORMAT    | (S3 only) Specifies substitution strings that provide a template for keys on the S3 cloud storage. You can customize the strings to create a template that is appropriate for your site; see "NAME_FORMAT Details" on page 446. |
| TASK_GROUPS    | Names the <code>taskgroup</code> objects that contain tasks the MSP should run. By default, no tasks are run.                                                                                                                   |
| WRITE_CHECKSUM | Specifies if the cloud MSP's copy of the file should be checksummed before writing. If the file has been checksummed, it is verified when read. You can set this parameter to ON or OFF. The default is ON.                     |

### mSP Object Example for an S3 Cloud MSP

#### Example 7-37 mSP Object for an S3 Cloud MSP

```
define cloudA
    TYPE                msp
    COMMAND             dmcloudmsp
    CLOUD_BACKEND       s3
    CLOUD_HOST          s3.amazonaws.com
    CLOUD_USER          WITST4TQBFJOTLDB2IAB
    CLOUD_PASSWORD     HOME_DIR/password
    CLOUD_BUCKET        dmf-bucket
    NAME_FORMAT         %p%p/%b
enddef
```

In the above example:

- The `define` value must match the `MSP_NAMES` or `LS_NAMES` parameter of the `dmdaemon` object.
- The command to initiate the cloud MSP must be `dmcloudmsp`.
- This cloud MSP instance uses S3.
- The name of the cloud host on which files will be stored is `s3.amazonaws.com` and the default port will be used.

- The Access Key ID for the cloud user during session initialization is WITST4TQBFJOTLDB2IAB.
- The Secret Access Key is stored in the file *HOME\_DIR*/password.
- The S3 bucket is named *dmf-bucket*.
- The key names will be randomly ordered by the first two characters (which will be anywhere from 00 through 99). This avoids sequential keys when writing files, which may potentially minimize subsequent access times and improve performance for a bucket with a high ingest rate.
- Because *CLOUD\_REDUNDANCY* is not specified, the default standard redundancy will be used.

#### **m<sub>sp</sub> Object Example for a Scality Cloud MSP**

##### **Example 7-38** m<sub>sp</sub> Object for a Scality Cloud MSP

```
define cloudB
    TYPE                msp
    COMMAND              dmcloudmsp
    CLOUD_BACKEND        scality
    CLOUD_HOST           scalityserver
    CLOUD_REDUNDANCY    3copies
enddef
```

In the above example:

- The *define* value must match the *MSP\_NAMES* or *LS\_NAMES* parameter of the *dmdaemon* object
- The command to initiate the cloud MSP must be *dmcloudmsp*
- This cloud MSP instance uses Scality
- The name of the cloud host on which files will be stored is *scalityserver*
- Three copies will be made by the cloud service for redundancy

## **m<sub>SP</sub> Object for an FTP MSP**

This section discusses the following:

- "m<sub>SP</sub> Object Summary for an FTP MSP" on page 455
- "m<sub>SP</sub> Object Parameters for an FTP MSP" on page 455
- " m<sub>SP</sub> Object Example for an FTP MSP" on page 458

## **m<sub>SP</sub> Object Summary for an FTP MSP**

Following is a summary of the potential parameters for the m<sub>SP</sub> object for an FTP MSP:

```
mSP
    TYPE
    CHILD_MAXIMUM
    COMMAND
    FTP_ACCOUNT
    FTP_COMMAND
    FTP_DIRECTORY
    FTP_HOST
    FTP_PASSWORD
    FTP_PORT
    FTP_USER
    GUARANTEED_DELETES
    GUARANTEED_GETS
    IMPORT_DELETE
    IMPORT_ONLY
    MESSAGE_LEVEL
    MVS_UNIT
    NAME_FORMAT
    TASK_GROUPS
    WRITE_CHECKSUM
```

## **m<sub>SP</sub> Object Parameters for an FTP MSP**

To enable a File Transfer Protocol (FTP) MSP, define an m<sub>SP</sub> object for it in the DMF configuration file and include the name of that object on the MSP\_NAMES or LS\_NAMES parameter in the dmdaemon object.

DMF has the capability to use an FTP MSP to convert a non-DMF fileserver to DMF with a minimal amount of down time for the switch over, and at a site-determined pace. Contact your customer service representative for information about technical assistance with fileserver conversion.

The MSP checks the DMF configuration file just before it starts child processes. If the DMF configuration file changed, it is reread.

An FTP `msp` object has the following parameters:

| <b>Parameter</b> | <b>Description</b>                                                                                                                                                                                                                                                                                                   |
|------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| TYPE             | Specifies <code>m<sub>sp</sub></code> (required name for this type of object). There is no default.                                                                                                                                                                                                                  |
| CHILD_MAXIMUM    | Specifies the maximum number of child processes that the MSP is allowed to fork. The legal range of values is 0-100; the default is 4.<br><br>If CHILD_MAXIMUM is nonzero, its value must be greater than the sum of GUARANTEED_DELETES and GUARANTEED_GETS.                                                         |
| COMMAND          | Specifies the binary file to execute in order to initiate this MSP. For the FTP MSP, this value must be <code>dmftpmsp</code> . There is no default.                                                                                                                                                                 |
| FTP_ACCOUNT      | Specifies the account ID to use on the remote FTP server. Most FTP servers do not need account information. By default, no account information is supplied. When account information is required, its nature and format will be dictated by the remote host and will vary from operating system to operating system. |
| FTP_COMMAND      | Specifies an additional command to send to the remote system. There may be more than one instance of this parameter. By default, no other commands are sent.                                                                                                                                                         |
| FTP_DIRECTORY    | Specifies the directory into which files will be placed on the remote FTP server. There is no default.                                                                                                                                                                                                               |
| FTP_HOST         | Specifies the domain name or IP address of the remote node on which files are to be stored. If you use a domain name with multiple IP addresses, the FTP MSP tries all of the addresses in order. If the remote system                                                                                               |

|                    |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
|--------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                    | cannot be reached, the MSP waits 5 minutes and retries again until it succeeds. There is no default.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| FTP_PASSWORD       | Specifies the file containing the password to use when migrating files to the remote system. This file must be owned by <code>root</code> and be only accessible by <code>root</code> . (The MSP will not operate if the <code>FTP_PASSWORD</code> file is readable by anyone other than <code>root</code> .) There is no default.                                                                                                                                                                                                                                                                        |
| FTP_PORT           | Specifies the port number of the FTP server on the remote system. The default is the value configured for <code>ftp</code> in the <code>services</code> file.                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| FTP_USER           | Specifies the user name to use when migrating files to the remote system. There is no default.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
| GUARANTEED_DELETES | Specifies the number of child processes that are guaranteed to be available for processing delete requests. If <code>CHILD_MAXIMUM</code> is nonzero, its value must be greater than the sum of <code>GUARANTEED_DELETES</code> and <code>GUARANTEED_GETS</code> . The default is 1.                                                                                                                                                                                                                                                                                                                      |
| GUARANTEED_GETS    | Specifies the number of child processes that are guaranteed to be available for processing <code>dmget(1)</code> requests. If <code>CHILD_MAXIMUM</code> is nonzero, its value must be greater than the sum of <code>GUARANTEED_DELETES</code> and <code>GUARANTEED_GETS</code> . The default is 1.                                                                                                                                                                                                                                                                                                       |
| IMPORT_DELETE      | Specifies if the MSP should honor hard-delete requests from the daemon. (This parameter applies only if <code>IMPORT_ONLY</code> is set to <code>ON</code> .) You can set this parameter to <code>ON</code> or <code>OFF</code> . The default is <code>OFF</code> . Set <code>IMPORT_DELETE</code> to <code>ON</code> if you wish files to be deleted on the destination system when hard deletes are processed.                                                                                                                                                                                          |
| IMPORT_ONLY        | Specifies if the MSP is used for importing only. You can set this parameter to <code>ON</code> or <code>OFF</code> . The default is <code>OFF</code> . Set this parameter <code>ON</code> when the data is stored as a bit-for-bit copy of the file and must be available to DMF as part of a conversion. The daemon will not accept <code>dmput(1)</code> , <code>dmmove(8)</code> , or <code>dmarchive(1)</code> requests that specify an MSP with this parameter enabled. By default, the MSP will ignore hard-delete requests when this parameter is enabled. When the DMF daemon performs a complete |

file recall from an import-only MSP and all other DMF copies also reside in import-only MSPs or VGs, it makes the file a regular file rather than a dual-state file, and it soft-deletes the MSP's copy of the file.

---

**Note:** An import-only MSP should never be a member of a `migrategroup` stanza.

---

|                |                                                                                                                                                                                                                                                                                               |
|----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| MESSAGE_LEVEL  | Specifies the highest message level that will be written to the MSP log. It must be an integer in the range 0–6; the higher the number, the more messages written to the log file. The default is 2. For more information on message levels, see Chapter 10, "Message Log Files" on page 507. |
| MVS_UNIT       | Defines the storage device type on an IBM MVS™ system. You must specify a this parameter when the destination is an MVS system. Valid values are:<br><br>3330<br>3350<br>3380<br>3390                                                                                                         |
| NAME_FORMAT    | Specifies the strings that form a template for names stored in <code>FTP_DIRECTORY</code> . You can customize the strings to create a template that is appropriate for your site; see "NAME_FORMAT Details" on page 446.                                                                      |
| TASK_GROUPS    | Names the <code>taskgroup</code> objects that contain tasks the MSP should run. By default, no tasks are run.                                                                                                                                                                                 |
| WRITE_CHECKSUM | Specifies if the FTP MSP's copy of the file should be checksummed before writing. If the file has been checksummed, it is verified when read. You can set this parameter to <code>ON</code> or <code>OFF</code> . The default is <code>ON</code> .                                            |

**misp Object Example for an FTP MSP**

**Example 7-39** `misp` Object for an FTP MSP

```
define ftp
    TYPE                misp
```



```

COMMAND                dmftpsp
FTP_HOST                fileserver
FTP_USER                dmf
FTP_ACCOUNT              dmf.disk
FTP_PASSWORD            /dmf/ftp/password
FTP_DIRECTORY           ftpmsp
FTP_COMMAND             umask 022
endif

```

In the above example:

- The string `%u/%b` will be used as a template to create names for files stored on remote hosts in `FTP_DIRECTORY` (which is the default when `NAME_FORMAT` is not specified)
- The `define` value must match the `MSP_NAMES` or `LS_NAMES` parameter of the `dmdaemon` object
- The command to initiate the FTP MSP must be `dmftpsp`
- The user name for the remote FTP server during session initialization is `dmf`
- The name of the remote host on which files will be stored is `fileserver`
- The remote host requires the FTP account information `dmf.disk`
- The password for the user on the remote host is stored in the file `/dmf/ftp/password`
- Files will be placed into the `ftpmsp` directory on the remote host
- The `umask` for files created will be set to `022`, which removes write permission for `group` and `other`

### **m<sub>sp</sub> Object for a DCM MSP**

This section discusses the following:

- "m<sub>sp</sub> Object Summary for a DCM MSP" on page 460
- "m<sub>sp</sub> Object Parameters for a DCM MSP" on page 460
- "m<sub>sp</sub> Object Example for a DCM MSP" on page 465

### m<sub>sp</sub> Object Summary for a DCM MSP

Following is a summary of the potential parameters for the m<sub>sp</sub> object for a DCM MSP:

```
msp
    TYPE
    BUFFERED_IO_SIZE
    CHILD_MAXIMUM
    COMMAND
    DIRECT_IO_SIZE
    DSK_BUFSIZE
    DUMP_FLUSH_DCM_FIRST
    FADV_SIZE_MSP
    GUARANTEED_DELETES
    GUARANTEED_GETS
    MESSAGE_LEVEL
    MIGRATION_LEVEL
    MIN_DIRECT_SIZE
    NAME_FORMAT
    POLICIES
    PRIORITY_PERIOD
    STORE_DIRECTORY
    TASK_GROUPS
    WRITE_CHECKSUM
```

### m<sub>sp</sub> Object Parameters for a DCM MSP

A DCM MSP is a disk MSP that is configured for *n*-tier capability. To enable a DCM MSP, define an m<sub>sp</sub> object for it in the DMF configuration file and include a name for that object on the MSP\_NAMES or LS\_NAMES parameter in the dm<sub>daemon</sub> object.

---

**Note:** The parameters differ for a disk MSP that is not a DCM MSP. See "m<sub>sp</sub> Object for a Disk MSP" on page 466.

---

A DCM m<sub>sp</sub> object has the following parameters:

| Parameter | Description                                                                             |
|-----------|-----------------------------------------------------------------------------------------|
| TYPE      | Specifies m <sub>sp</sub> (required name for this type of object). There is no default. |

---

|                                                                                                     |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|-----------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| BUFFERED_IO_SIZE                                                                                    | Specifies the size of I/O requests for buffered I/O when migrating files downward in the hierarchy from <i>STORE_DIRECTORY</i> of this DCM MSP. The legal range of values is 4096–16777216. The default is 262144. By default, the unit of measure is bytes; see "Units of Measure" on page 275.                                                                                                                                                                                                                                                                            |
| CHILD_MAXIMUM                                                                                       | Specifies the maximum number of child processes that the DCM MSP is allowed to fork. The legal range of values is 0–100. The default is 4.                                                                                                                                                                                                                                                                                                                                                                                                                                  |
| <hr/> <b>Note:</b> SGI recommends that you use a larger value than the default for a DCM MSP. <hr/> |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| COMMAND                                                                                             | Specifies the binary file to execute in order to initiate this MSP. For the DCM MSP, this value must be <code>dmdskmsp</code> .                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| DIRECT_IO_SIZE                                                                                      | Specifies the size of I/O requests for direct I/O when migrating files downward in the hierarchy from <i>STORE_DIRECTORY</i> for this DCM MSP. The legal range of values is 65536–18446744073709551615. The default depends on the filesystem, but will not exceed the value of <code>DIRECT_IO_MAXIMUM_SIZE</code> defined in the base object (see "base Object" on page 277). By default, the unit of measure is bytes; see "Units of Measure" on page 275.<br><br>For more information about direct I/O, see <code>O_DIRECT</code> in the <code>open(2)</code> man page. |
| DSK_BUF_SIZE                                                                                        | Specifies the transfer size in bytes used when reading from and writing to files within the DCM MSP <i>STORE_DIRECTORY</i> . The value must be in the range 4096–16000000 (16 million). The default is 131072 when writing and 1000000 when reading. By default, the unit of measure is bytes; see "Units of Measure" on page 275.                                                                                                                                                                                                                                          |
| DUMP_FLUSH_DCM_FIRST                                                                                | <i>(integrated-backup context only)</i> Specifies whether or not the <code>dmmigrate</code> command is run on the filesystem specified by the <code>STORE_DIRECTORY</code> parameter for this                                                                                                                                                                                                                                                                                                                                                                               |

|                                 |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|---------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                                 | <p>DCM MSP before dumping the filesystem, overriding the value set for the <code>taskgroup</code> object. Running <code>dmmigrate</code> first ensures that all non-dual-resident files in the DCM MSP caches are migrated to a lower tier. You can set this parameter to <code>ON</code> or <code>OFF</code>. The default is <code>ON</code>. For integrated backups, the value set in the <code>taskgroup</code> object overrides the value set here.</p>                                                                                                                 |
| <code>FADV_SIZE_MSP</code>      | <p>Specifies the size of files in the MSP's <code>STORE_DIRECTORY</code> for which <code>posix_fadvise()</code> will be called with advice <code>POSIX_FADV_DONTNEED</code>. If the file is larger than <code>FADV_SIZE_MSP</code> bytes, the call is made following migration to the MSP or following recall of the entire file. The minimum is 0, which means that <code>posix_fadvise()</code> will always be called, and the maximum is 9223372036854775807. The default is 10000000. By default, the unit of measure is bytes; see "Units of Measure" on page 275.</p> |
| <code>GUARANTEED_DELETES</code> | <p>Specifies the number of child processes that are guaranteed to be available for processing delete requests. The default is 1.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                        |
| <code>GUARANTEED_GETS</code>    | <p>Specifies the number of child processes that are guaranteed to be available for processing <code>dmget(1)</code> requests. The default is 1.</p>                                                                                                                                                                                                                                                                                                                                                                                                                         |
| <code>MESSAGE_LEVEL</code>      | <p>Specifies the highest message level that will be written to the MSP log. It must be an integer in the range 0–6; the higher the number, the more messages written to the log file. The default is 2. For more information on message levels, see Chapter 10, "Message Log Files" on page 507.</p>                                                                                                                                                                                                                                                                        |
| <code>MIGRATION_LEVEL</code>    | <p>Specifies the level of migration service for the DCM MSP. Valid values are:</p> <ul style="list-style-type: none"><li>• <code>auto</code> (automated space management)</li><li>• <code>none</code> (no flushing to a lower VG)</li><li>• <code>user</code> (only requests from <code>dmmigrate</code> or a manually invoked <code>dmdskfree</code>)</li></ul> <p>The default is <code>auto</code>.</p>                                                                                                                                                                   |

---

|                 |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| MIN_DIRECT_SIZE | <p>Determines whether direct or buffered I/O is used when migrating files downward in the hierarchy from the <i>STORE_DIRECTORY</i> of this DCM MSP. If the number of bytes to be read is smaller than the value specified, buffered I/O is used, otherwise direct I/O is used. The legal range of values is 0 (direct I/O is always used) through 18446744073709551615 (direct I/O is never used). The default is 0. By default, the unit of measure is bytes; see "Units of Measure" on page 275.</p> <hr/> <p><b>Note:</b> For real-time filesystems, this parameter is ignored.</p> <hr/> <p>For more information about direct I/O, see <code>O_DIRECT</code> in the <code>open(2)</code> man page.</p> |
| NAME_FORMAT     | <p>Specifies the substitution strings that form a template for names stored in <i>STORE_DIRECTORY</i>. You can customize the strings to create a template that is appropriate for your site; see "NAME_FORMAT Details" on page 446.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| POLICIES        | <p>Specifies the names of the configuration objects defining policies for this filesystem. The configuration stanza must contain at least one <code>POLICIES</code> parameter and the configuration stanza for that parameter must contain a <code>SELECT_LOWER_VG</code> parameter.</p>                                                                                                                                                                                                                                                                                                                                                                                                                    |
| PRIORITY_PERIOD | <p>Specifies the number of minutes after which a migrating file gets special treatment.</p> <p>Normally, if there is insufficient room in the <i>STORE_DIRECTORY</i> for a file, the DCM MSP will attempt to make room, while continuing to store files that will fit. If a file has not been stored into the <i>STORE_DIRECTORY</i> within <i>PRIORITY_PERIOD</i>, however, the DCM MSP will stop trying to store other files until either sufficient room has been made or it has determined that room cannot be made. The legal range of values is 1-2000000; the default is 120 minutes (2 hours).</p>                                                                                                  |

|                 |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|-----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| STORE_DIRECTORY | Specifies the directory used to hold files for this DCM MSP. This directory must not be in a managed filesystem. The directory must be the mount point of a dedicated XFS or CXFS filesystem mounted with DMAPI enabled. You must mount a DCM MSP STORE_DIRECTORY with both <code>dirsync</code> and <code>dmi</code> . In addition, when using Parallel DMF, the directory must be a CXFS filesystem. See "Configure Filesystems and Directories Appropriately for DMF" on page 94. |
| TASK_GROUPS     | Names the <code>taskgroup</code> objects that contain tasks the DCM MSP should run. By default, no tasks are run.                                                                                                                                                                                                                                                                                                                                                                    |
| WRITE_CHECKSUM  | Specifies if the DCM MSP's copy of the file should be checksummed before writing. If the file has been checksummed, it is verified when read. You can set this parameter to <code>ON</code> or <code>OFF</code> . The default is <code>ON</code> .                                                                                                                                                                                                                                   |

A DCM MSP also requires a task group that runs the `run_dcm_admin.sh` task during off-peak hours to perform routine maintenance for the DCM MSP.

When using a DCM MSP, `dmdskmsp` will not fail if the `STORE_DIRECTORY` is full. Instead, it will queue the requests and wait to fulfill them until after `dmdskfree` has freed the required space.

**mSP Object Example for a DCM MSP**

Following is a sample of the configuration stanzas with some explanatory notes below. Many of parameters have defaults and can be omitted if the defaults are appropriate.

**Example 7-40 Configuration Stanzas Associated with a DCM MSP**

```

define daemon
    TYPE                dmdaemon
    LS_NAMES             dcm_msp ls                ### See note 1
    ...                 ### See note 2
enddef

define msp_policy
    TYPE                policy
    SELECT_MSP          dcm_msp copy2 when space > 4096 ### See note 3
    ...                 ### See note 2
enddef

define dcm_msp
    TYPE                msp
    COMMAND             dmmskmsp
    STORE_DIRECTORY     /dmf/dcm_msp_store        ### See note 4
    CHILD_MAXIMUM       10                       ### See note 5
    POLICIES            dcm_policy
    TASK_GROUPS         dcm_tasks
enddef

define dcm_policy
    TYPE                policy                    ### See note 6
    FREE_SPACE_MINIMUM  10
    FREE_SPACE_TARGET   70
    DUALRESIDENCE_TARGET 90
    FREE_SPACE_DECREMENT 1
    FREE_DUALRESIDENT_FIRST on
    CACHE_AGE_WEIGHT    1 .1
    CACHE_SPACE_WEIGHT  1 .1
    SELECT_LOWER_VG     none when uid = 0
    SELECT_LOWER_VG     vg1 when space > 1G
    SELECT_LOWER_VG     vg2
enddef

```

```
define dcm_tasks
  TYPE                taskgroup
  RUN_TASK            $ADMINDIR/run_dcm_admin.sh at 22:00:10
enddef
```

Notes referred to in the preceding example:

1. The DCM MSP must be specified before the LSs that contain its lower VGs. (Otherwise, all recalls will attempt to come directly from the lower VGs.)
2. Other parameters essential to the use of this stanza but not relevant to the DCM MSP have been omitted.
3. The DCM MSP and its lower VGs should be considered to act as a single high-speed VG logically maintaining only one copy of a migrated file. You should always have a second copy of all migrated files, which is the purpose of `copy2` in this example. It would probably be a tape VG, but could be any type of MSP other than a DCM MSP.

The copy that resides in the DCM MSP *STORE\_DIRECTORY* is not to be considered a permanent copy of the file in terms of the safety of the file's data. It can be deleted at any time, though never before a copy of it exists in one of the *SELECT\_LOWER\_VG* VGs.

4. The mount point of a **dedicated** DMAPi-mounted filesystem.
5. Any other parameters applicable to a disk MSP may also be used, with the exception of `IMPORT_ONLY` and `IMPORT_DELETE`.
6. Several parameters in DCM MSP policies have functions that are analogous to those in disk MSP policies; see "Rules for `policy` Parameters" on page 366 and "Managed Filesystem `policy` Parameters" on page 368.

## mSP Object for a Disk MSP

This section discusses the following:

- "mSP Object Summary for a Disk MSP" on page 467
- "mSP Object Parameters for a Disk MSP" on page 467
- "mSP Object Example for a Disk MSP" on page 470



**m<sub>sp</sub> Object Summary for a Disk MSP**

Following is a summary of the potential parameters for the `msp` object for a disk MSP:

```
msp
    TYPE
    CHILD_MAXIMUM
    COMMAND
    DSK_BUFSIZE
    FADV_SIZE_MSP
    FULL_THRESHOLD_BYTES
    GUARANTEED_DELETES
    GUARANTEED_GETS
    IMPORT_DELETE
    IMPORT_ONLY
    MESSAGE_LEVEL
    NAME_FORMAT
    STORE_DIRECTORY
    TASK_GROUPS
    WRITE_CHECKSUM
```

**m<sub>sp</sub> Object Parameters for a Disk MSP**


---

**Note:** The parameters differ for a DCM MSP, which is a disk MSP configured for *n*-tier capability. See "m<sub>sp</sub> Object for a DCM MSP" on page 459.

---

To enable a disk MSP, define an `msp` object for it in the DMF configuration file and include a name for that object on the `MSP_NAMES` or `LS_NAMES` parameter in the `dmdaemon` object.

You can use a disk MSP to convert a non-DMF fileserver to DMF with a minimal amount of down time for the switch over, and at a site-determined pace. Contact your customer service representative for information about technical assistance with fileserver conversion.

A disk `msp` object has the following parameters:

| Parameter         | Description                                                                                         |
|-------------------|-----------------------------------------------------------------------------------------------------|
| <code>TYPE</code> | Specifies <code>m<sub>sp</sub></code> (required name for this type of object). There is no default. |

|                      |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|----------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| CHILD_MAXIMUM        | Specifies the maximum number of child processes that the MSP is allowed to fork. The legal range of values is 0–100. The default is 4.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| COMMAND              | Specifies the binary file to execute in order to initiate this MSP. For the disk MSP, this value must be <code>dmdskmsp</code> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| DSK_BUFSIZE          | Specifies the transfer size in bytes used when reading from and writing to files within the disk MSP's <i>STORE_DIRECTORY</i> . The value must be in the range 4096–16000000 (or 16m). The default is 131072 when writing and 1000000 when reading. By default, the unit of measure is bytes; see "Units of Measure" on page 275.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
| FADV_SIZE_MSP        | Specifies the size of files in the MSP's <i>STORE_DIRECTORY</i> for which <code>posix_fadvise()</code> will be called with advice <code>POSIX_FADV_DONTNEED</code> . If the file is larger than <i>FADV_SIZE_MSP</i> bytes, the call is made following migration to the MSP or following recall of the entire file. The minimum is 0, which means that <code>posix_fadvise()</code> will always be called, and the maximum is 9223372036854775807. The default is 10000000. By default, the unit of measure is bytes; see "Units of Measure" on page 275.                                                                                                                                                                                                                                                                            |
| FULL_THRESHOLD_BYTES | Specifies the number of bytes at which point the disk MSP will tell the DMF daemon that it is full. If 0, the disk MSP will never report that it is full. If non-zero, the MSP will report when it is full and will continue to report full until the number of bytes specified by <i>FULL_THRESHOLD_BYTES</i> become free. (You can free bytes by using <code>dmmove(8)</code> or hard-deleting BFIDs.) The <i>SEQUENTIAL</i> choice for <i>ROTATION_STRATEGY</i> relies on the disk MSP reporting that it is full (see "migrategroup Object" on page 426); if the MSP is part of an MG, setting <i>FULL_THRESHOLD_BYTES</i> to a non-zero value prevents the MG from sending migrations to the MSP before enough disk space has been freed to make the migrations productive. If you specify a non-zero value, you should also set |

---

|                    |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
|--------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                    | EXPORT_METRICS to ON (see "base Object" on page 277). The default is 0.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
| GUARANTEED_DELETES | Specifies the number of child processes that are guaranteed to be available for processing delete requests. The default is 1.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| GUARANTEED_GETS    | Specifies the number of child processes that are guaranteed to be available for processing <code>dmget(1)</code> requests. The default is 1.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| IMPORT_DELETE      | Specifies if the MSP should honor hard-delete requests from the daemon. (This parameter only applies if <code>IMPORT_ONLY</code> is set to ON.) You can set this parameter to ON or OFF. The default is OFF. Set <code>IMPORT_DELETE</code> to ON if you want files to be deleted in <code>STORE_DIRECTORY</code> when hard deletes are processed.                                                                                                                                                                                                                                                                                                                                                                                                                         |
| IMPORT_ONLY        | Specifies if the MSP is used for importing only. You can set this parameter to ON or OFF. The default is OFF. Set this parameter ON when the data is stored as a bit-for-bit copy of the file and must be available to DMF as part of a conversion. The daemon will not accept <code>dmput(1)</code> , <code>dmmove(8)</code> , or <code>dmarchive(1)</code> requests that specify an MSP with this parameter enabled. The MSP will, by default, ignore hard-delete requests when this parameter is enabled. When the DMF daemon performs a complete file recall from an import-only MSP and all other DMF copies also reside in import-only MSPs or VGs, it makes the file a regular file (rather than a dual-state file) and it soft-deletes the MSP's copy of the file. |
|                    | <hr/> <b>Note:</b> An import-only MSP should never be a member of a <code>migrategroup</code> stanza. <hr/>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
| MESSAGE_LEVEL      | Specifies the highest message level that will be written to the MSP log. It must be an integer in the range 0–6; the higher the number, the more messages written to the log file. The default is 2. For more information on message levels, see Chapter 10, "Message Log Files" on page 507.                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |

|                 |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
|-----------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| NAME_FORMAT     | Specifies the substitution strings that form a template for names stored in <i>STORE_DIRECTORY</i> . You can customize the strings to create a template that is appropriate for your site; see "NAME_FORMAT Details" on page 446.                                                                                                                                                                                                                                                                                                                                            |
| STORE_DIRECTORY | Specifies the directory that holds files for this disk MSP. This directory may be in a local filesystem or in a remote filesystem that has been imported by NFS, CXFS, or similar. This directory must not be in a managed filesystem. By default, this value must not reside in the root filesystem (see the description of <i>ADMDIR_IN_ROOTFS</i> in "base Object Parameters" on page 278). You must mount a disk MSP <i>STORE_DIRECTORY</i> with <i>dirsync</i> (but without <i>dmi</i> ); see "Configure Filesystems and Directories Appropriately for DMF" on page 94. |
| TASK_GROUPS     | Names the <i>taskgroup</i> objects that contain tasks the MSP should run. By default, no tasks are run.                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| WRITE_CHECKSUM  | Specifies if the disk MSP's copy of the file should be checksummed before writing. If the file has been checksummed, it is verified when read. You can set this parameter to <i>ON</i> or <i>OFF</i> . The default is <i>ON</i> .                                                                                                                                                                                                                                                                                                                                            |

### **m**sp Object Example for a Disk MSP

#### **Example 7-41** *m*sp Object for a Disk MSP

```
define dsk
    TYPE                msp
    COMMAND              dmdskmsp
    CHILD_MAXIMUM       8
    GUARANTEED_DELETES  3
    GUARANTEED_GETS     3
    STORE_DIRECTORY     /dmf/dsk_store
enddef
```

In the above example:

- The *define* value must match the *MSP\_NAMES* or *LS\_NAMES* parameter of the *dm<sub>d</sub>daemon* object.

- The command to initiate the disk MSP must be `dmdskmsp`.
- This MSP can fork up to 8 child processes.
- 3 child processes are guaranteed to be available for processing delete and get requests.
- Files will be stored in `/dmf/dsk_store`.

## Summary of the Configuration-File Parameters

Table 7-4 alphabetically lists the DMF configuration file parameters discussed in this chapter.

**Table 7-4** Configuration Parameters

| Parameter            | Section Discussed In                                                                            |
|----------------------|-------------------------------------------------------------------------------------------------|
| ADMDIR_IN_ROOTFS     | "base Object Parameters" on page 278                                                            |
| ADMIN_EMAIL          | "base Object Parameters" on page 278                                                            |
| AGE_WEIGHT           | "File Weighting Parameters for a Managed Filesystem" on page 371                                |
| AGGRESSIVE_HVFX      | "drivegroup Object Parameters" on page 397                                                      |
| ALERT_RETENTION      | "taskgroup Object Parameters" on page 312                                                       |
| ALGORITHM            | "resourcescheduler Object Parameters" on page 432                                               |
| ALLOCATION_GROUP     | "volumegroup Object Parameters" on page 411                                                     |
| ALLOCATION_MAXIMUM   | "volumegroup Object Parameters" on page 411                                                     |
| ALLOCATION_MINIMUM   | "volumegroup Object Parameters" on page 411                                                     |
| BANDWIDTH_MULTIPLIER | "drivegroup Object Parameters" on page 397                                                      |
| BLOCK_SIZE           | "drivegroup Object Parameters" on page 397                                                      |
| BUFFERED_IO_SIZE     | "filesystem Object Parameters" on page 351<br>"msp Object Parameters for a DCM MSP" on page 460 |
| CACHE_AGE_WEIGHT     | "File Weighting Parameters for a DCM MSP STORE_DIRECTORY" on page 378                           |
| CACHE_DIR            | "libraryserver Object Parameters" on page 393                                                   |
| CACHE_MEMBERS        | "fastmountcache Object" on page 390                                                             |
| CACHE_SPACE          | "libraryserver Object Parameters" on page 393                                                   |
| CACHE_SPACE_WEIGHT   | "File Weighting Parameters for a DCM MSP STORE_DIRECTORY" on page 378                           |
| CHECKSUM_TYPE        | "volumegroup Object Parameters" on page 411                                                     |

| Parameter                  | Section Discussed In                                                                                                                                                                                                                                                  |
|----------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| CHILD_MAXIMUM              | "msp Object Parameters for a Cloud MSP" on page 449<br>"msp Object Parameters for a DCM MSP" on page 460<br>"msp Object Parameters for a Disk MSP" on page 467<br>"msp Object Parameters for an FTP MSP" on page 455                                                  |
| CLOUD_BACKEND              | "msp Object Parameters for a Cloud MSP" on page 449                                                                                                                                                                                                                   |
| CLOUD_BASE_PATH            | "msp Object Parameters for a Cloud MSP" on page 449                                                                                                                                                                                                                   |
| CLOUD_BUCKET               | "msp Object Parameters for a Cloud MSP" on page 449                                                                                                                                                                                                                   |
| CLOUD_HOST                 | "msp Object Parameters for a Cloud MSP" on page 449                                                                                                                                                                                                                   |
| CLOUD_PASSWORD             | "msp Object Parameters for a Cloud MSP" on page 449                                                                                                                                                                                                                   |
| CLOUD_REDUNDANCY           | "msp Object Parameters for a Cloud MSP" on page 449                                                                                                                                                                                                                   |
| CLOUD_USER                 | "msp Object Parameters for a Cloud MSP" on page 449                                                                                                                                                                                                                   |
| COMMAND                    | "libraryserver Object Parameters" on page 393<br>"msp Object Parameters for a Cloud MSP" on page 449<br>"msp Object Parameters for a DCM MSP" on page 460<br>"msp Object Parameters for a Disk MSP" on page 467<br>"msp Object Parameters for an FTP MSP" on page 455 |
| COMPRESSION_TYPE           | "drivegroup Object Parameters" on page 397                                                                                                                                                                                                                            |
| COPAN_VSNS                 | "libraryserver Object Parameters" on page 393                                                                                                                                                                                                                         |
| DATA_LIMIT                 | "taskgroup Object Parameters" on page 312                                                                                                                                                                                                                             |
| DATABASE_COPIES            | "taskgroup Object Parameters" on page 312                                                                                                                                                                                                                             |
| DB_SERVER_BIN              | "base Object Parameters" on page 278                                                                                                                                                                                                                                  |
| DB_SERVER_HOST             | "base Object Parameters" on page 278                                                                                                                                                                                                                                  |
| DB_SERVER_PORT             | "base Object Parameters" on page 278                                                                                                                                                                                                                                  |
| DIRECT_IO_MAXIMUM_SIZE     | "base Object Parameters" on page 278                                                                                                                                                                                                                                  |
| DIRECT_IO_SIZE             | "filesystem Object Parameters" on page 351<br>"msp Object Parameters for a DCM MSP" on page 460                                                                                                                                                                       |
| DISCONNECT_TIMEOUT         | "libraryserver Object Parameters" on page 393                                                                                                                                                                                                                         |
| DMMIGRATE_MINIMUM_AGE      | "taskgroup Object Parameters" on page 312                                                                                                                                                                                                                             |
| DMMIGRATE_MIN_OFFLINE_AGE  | "taskgroup Object Parameters" on page 312                                                                                                                                                                                                                             |
| DMMIGRATE_MIN_OFFLINE_SIZE | "taskgroup Object Parameters" on page 312                                                                                                                                                                                                                             |

| Parameter              | Section Discussed In                                                                                                                      |
|------------------------|-------------------------------------------------------------------------------------------------------------------------------------------|
| DMMIGRATE_QUEUE_MAX    | "taskgroup Object Parameters" on page 312                                                                                                 |
| DMMIGRATE_TRICKLE      | "taskgroup Object Parameters" on page 312                                                                                                 |
| DMMIGRATE_UNACK        | "taskgroup Object Parameters" on page 312                                                                                                 |
| DMMIGRATE_VERBOSE      | "taskgroup Object Parameters" on page 312                                                                                                 |
| DMMIGRATE_WAIT         | "taskgroup Object Parameters" on page 312                                                                                                 |
| DRIVE_GROUPS           | "libraryserver Object Parameters" on page 393                                                                                             |
| DRIVE_MAXIMUM          | "drivegroup Object Parameters" on page 397<br>"volumegroup Object Parameters" on page 411                                                 |
| DRIVE_SCHEDULER        | "drivegroup Object Parameters" on page 397<br>"volumegroup Object Parameters" on page 411                                                 |
| DRIVES_TO_DOWN         | "drivegroup Object Parameters" on page 397                                                                                                |
| DRIVETAB               | "taskgroup Object Parameters" on page 312                                                                                                 |
| DSK_BUFSIZE            | "msp Object Parameters for a DCM MSP" on page 460<br>"msp Object Parameters for a Disk MSP" on page 467                                   |
| DUALRESIDENCE_TARGET   | "Automated Space-Management Parameters for a DCM MSP<br>STORE_DIRECTORY" on page 376<br>"msp Object Parameters for a DCM MSP" on page 460 |
| DUMP_COMPRESS          | "dumpgroup Object Parameters" on page 343<br>"filesystem Object Parameters" on page 351<br>"taskgroup Object Parameters" on page 312      |
| DUMP_CONCURRENCY       | "taskgroup Object Parameters" on page 312                                                                                                 |
| DUMP_DESTINATION       | "taskgroup Object Parameters" on page 312                                                                                                 |
| DUMP_DEVICE            | "taskgroup Object Parameters" on page 312                                                                                                 |
| DUMP_DR_EMAIL          | "taskgroup Object Parameters" on page 312                                                                                                 |
| DUMP_DR_EMAIL_MAX_SIZE | "taskgroup Object Parameters" on page 312                                                                                                 |
| DUMP_DR_MINIMAL        | "taskgroup Object Parameters" on page 312                                                                                                 |
| DUMP_DR_MIRRORS        | "taskgroup Object Parameters" on page 312                                                                                                 |
| DUMP_FILE_SYSTEMS      | "dumpgroup Object Parameters" on page 343<br>"taskgroup Object Parameters" on page 312                                                    |



| Parameter               | Section Discussed In                                                                                                                 |
|-------------------------|--------------------------------------------------------------------------------------------------------------------------------------|
| DUMP_FLUSH_DCM_FIRST    | "msp Object Parameters for a DCM MSP" on page 460<br>"taskgroup Object Parameters" on page 312                                       |
| DUMP_GROUPS             | "taskgroup Object Parameters" on page 312                                                                                            |
| DUMP_INVENTORY_COPY     | "taskgroup Object Parameters" on page 312                                                                                            |
| DUMP_MAX_FILESPACE      | "dumpgroup Object Parameters" on page 343<br>"filesystem Object Parameters" on page 351<br>"taskgroup Object Parameters" on page 312 |
| DUMP_MIGRATE_FIRST      | "dumpgroup Object Parameters" on page 343<br>"filesystem Object Parameters" on page 351<br>"taskgroup Object Parameters" on page 312 |
| DUMP_MIRRORS            | "taskgroup Object Parameters" on page 312                                                                                            |
| DUMP_MISC_LOCATIONS     | "taskgroup Object Parameters" on page 312                                                                                            |
| DUMP_POST_BACKUP_SCRIPT | "taskgroup Object Parameters" on page 312                                                                                            |
| DUMP_POST_DR_SCRIPT     | "taskgroup Object Parameters" on page 312                                                                                            |
| DUMP_PRE_BACKUP_SCRIPT  | "taskgroup Object Parameters" on page 312                                                                                            |
| DUMP_RETENTION          | "taskgroup Object Parameters" on page 312                                                                                            |
| DUMP_STREAMS            | "dumpgroup Object Parameters" on page 343<br>"filesystem Object Parameters" on page 351<br>"taskgroup Object Parameters" on page 312 |
| DUMP_TAPES              | "taskgroup Object Parameters" on page 312                                                                                            |
| DUMP_VSNS_USED          | "taskgroup Object Parameters" on page 312                                                                                            |
| DUMP_WORKSPACE          | "taskgroup Object Parameters" on page 312                                                                                            |
| DUMP_XFSDUMP_PARAMS     | "dumpgroup Object Parameters" on page 343<br>"filesystem Object Parameters" on page 351<br>"taskgroup Object Parameters" on page 312 |
| EXPORT_METRICS          | "base Object Parameters" on page 278                                                                                                 |
| EXPORT_QUEUE            | "dmdaemon Object Parameters" on page 290                                                                                             |
| FADV_SIZE_MAID          | "drivegroup Object Parameters" on page 397                                                                                           |
| FADV_SIZE_MSP           | "msp Object Parameters for a DCM MSP" on page 460<br>"msp Object Parameters for a Disk MSP" on page 467                              |

| Parameter               | Section Discussed In                                                                                                                                              |
|-------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| FILE_RETENTION_DAYS     | "taskgroup Object Parameters" on page 312                                                                                                                         |
| FMC_MOVEFS              | "taskgroup Object Parameters" on page 312                                                                                                                         |
| FMC_NAME                | "taskgroup Object Parameters" on page 312                                                                                                                         |
| FORWARD_RECALLS         | "volumegroup Object Parameters" on page 411                                                                                                                       |
| FREE_DUALRESIDENT_FIRST | "Automated Space-Management Parameters for a DCM MSP STORE_DIRECTORY" on page 376                                                                                 |
| FREE_DUALSTATE_FIRST    | "Automated Space-Management Parameters for a Managed Filesystem" on page 369                                                                                      |
| FREE_SPACE_DECREMENT    | "Automated Space-Management Parameters for a DCM MSP STORE_DIRECTORY" on page 376<br>"Automated Space-Management Parameters for a Managed Filesystem" on page 369 |
| FREE_SPACE_MINIMUM      | "Automated Space-Management Parameters for a DCM MSP STORE_DIRECTORY" on page 376<br>"Automated Space-Management Parameters for a Managed Filesystem" on page 369 |
| FREE_SPACE_TARGET       | "Automated Space-Management Parameters for a DCM MSP STORE_DIRECTORY" on page 376<br>"Automated Space-Management Parameters for a Managed Filesystem" on page 369 |
| FREE_VOLUME_MINIMUM     | "taskgroup Object Parameters" on page 312                                                                                                                         |
| FREE_VOLUME_TARGET      | "taskgroup Object Parameters" on page 312                                                                                                                         |
| FTP_ACCOUNT             | "msp Object Parameters for an FTP MSP" on page 455                                                                                                                |
| FTP_COMMAND             | "msp Object Parameters for an FTP MSP" on page 455                                                                                                                |
| FTP_DIRECTORY           | "msp Object Parameters for an FTP MSP" on page 455                                                                                                                |
| FTP_HOST                | "msp Object Parameters for an FTP MSP" on page 455                                                                                                                |
| FTP_PASSWORD            | "msp Object Parameters for an FTP MSP" on page 455                                                                                                                |
| FTP_PORT                | "msp Object Parameters for an FTP MSP" on page 455                                                                                                                |
| FTP_USER                | "msp Object Parameters for an FTP MSP" on page 455                                                                                                                |
| FULL_THRESHOLD_BYTES    | "msp Object Parameters for a Disk MSP" on page 467                                                                                                                |

| Parameter          | Section Discussed In                                                                                                                                                                                                 |
|--------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| FULL_ZONE          | "volumegroup Object Parameters" on page 411                                                                                                                                                                          |
| GET_WAIT_TIME      | "volumegroup Object Parameters" on page 411                                                                                                                                                                          |
| GROUP_MEMBERS      | "migrategroup Object Parameters" on page 427                                                                                                                                                                         |
| GUARANTEED_DELETES | "msp Object Parameters for a Cloud MSP" on page 449<br>"msp Object Parameters for a DCM MSP" on page 460<br>"msp Object Parameters for a Disk MSP" on page 467<br>"msp Object Parameters for an FTP MSP" on page 455 |
| GUARANTEED_GETS    | "msp Object Parameters for a Cloud MSP" on page 449<br>"msp Object Parameters for a DCM MSP" on page 460<br>"msp Object Parameters for a Disk MSP" on page 467<br>"msp Object Parameters for an FTP MSP" on page 455 |
| HBA_BANDWIDTH      | "base Object Parameters" on page 278<br>"node Object Parameters" on page 294                                                                                                                                         |
| HFREE_TIME         | "volumegroup Object Parameters" on page 411                                                                                                                                                                          |
| HOME_DIR           | "base Object Parameters" on page 278                                                                                                                                                                                 |
| HTML_REFRESH       | "resourcewatcher Object Parameters" on page 434                                                                                                                                                                      |
| IMMUTABLE_BFIDS    | "filesystem Object Parameters" on page 351                                                                                                                                                                           |
| IMPORT_DELETE      | "msp Object Parameters for a Disk MSP" on page 467<br>"msp Object Parameters for an FTP MSP" on page 455                                                                                                             |
| IMPORT_ONLY        | "msp Object Parameters for a Disk MSP" on page 467<br>"msp Object Parameters for an FTP MSP" on page 455<br>"volumegroup Object Parameters" on page 411                                                              |
| INTERFACE          | "node Object Parameters" on page 294                                                                                                                                                                                 |
| JOURNAL_DIR        | "base Object Parameters" on page 278                                                                                                                                                                                 |
| JOURNAL_RETENTION  | "taskgroup Object Parameters" on page 312                                                                                                                                                                            |
| JOURNAL_SIZE       | "base Object Parameters" on page 278                                                                                                                                                                                 |
| KILL_WC_IF_DEMAND  | "volumegroup Object Parameters" on page 411                                                                                                                                                                          |
| LABEL_TYPE         | "drivegroup Object Parameters" on page 397                                                                                                                                                                           |
| LICENSE_FILE       | "base Object Parameters" on page 278                                                                                                                                                                                 |
| LOG_RETENTION      | "taskgroup Object Parameters" on page 312                                                                                                                                                                            |

| Parameter                | Section Discussed In                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|--------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| LOGICAL_BLOCK_PROTECTION | "volumegroup Object Parameters" on page 411                                                                                                                                                                                                                                                                                                                                                                                                                |
| LS_NAMES                 | "dmdaemon Object Parameters" on page 290                                                                                                                                                                                                                                                                                                                                                                                                                   |
| MAX_ALERTDB_SIZE         | "taskgroup Object Parameters" on page 312                                                                                                                                                                                                                                                                                                                                                                                                                  |
| MAX_CACHE_FILE           | "libraryserver Object Parameters" on page 393                                                                                                                                                                                                                                                                                                                                                                                                              |
| MAX_CHUNK_SIZE           | "volumegroup Object Parameters" on page 411                                                                                                                                                                                                                                                                                                                                                                                                                |
| MAX_IDLE_PUT_CHILDREN    | "volumegroup Object Parameters" on page 411                                                                                                                                                                                                                                                                                                                                                                                                                |
| MAX_MANAGED_REGIONS      | "filesystem Object Parameters" on page 351                                                                                                                                                                                                                                                                                                                                                                                                                 |
| MAX_MS_RESTARTS          | "drivegroup Object Parameters" on page 397                                                                                                                                                                                                                                                                                                                                                                                                                 |
| MAX_PERFDB_SIZE          | "taskgroup Object Parameters" on page 312                                                                                                                                                                                                                                                                                                                                                                                                                  |
| MAX_PUT_CHILDREN         | "drivegroup Object Parameters" on page 397<br>"volumegroup Object Parameters" on page 411                                                                                                                                                                                                                                                                                                                                                                  |
| MERGE_CUTOFF             | "volumegroup Object Parameters" on page 411                                                                                                                                                                                                                                                                                                                                                                                                                |
| MERGE_INTERFACE          | "node Object Parameters" on page 294"node Object" on page 294                                                                                                                                                                                                                                                                                                                                                                                              |
| MERGE_THRESHOLD          | "volumegroup Object Parameters" on page 411                                                                                                                                                                                                                                                                                                                                                                                                                |
| MESSAGE_LEVEL            | "dmdaemon Object Parameters" on page 290<br>"filesystem Object Parameters" on page 351<br>"libraryserver Object Parameters" on page 393<br>"msp Object Parameters for a Cloud MSP" on page 449<br>"msp Object Parameters for a DCM MSP" on page 460<br>"msp Object Parameters for a Disk MSP" on page 467<br>"msp Object Parameters for an FTP MSP" on page 455<br>"services Object Parameters" on page 300<br>Chapter 10, "Message Log Files" on page 507 |
| METRICS_RETENTION        | "base Object Parameters" on page 278                                                                                                                                                                                                                                                                                                                                                                                                                       |
| MIGRATION_LEVEL          | "dmdaemon Object Parameters" on page 290<br>"filesystem Object Parameters" on page 351<br>"msp Object Parameters for a DCM MSP" on page 460                                                                                                                                                                                                                                                                                                                |
| MIGRATION_TARGET         | "Automated Space-Management Parameters for a Managed Filesystem" on page 369                                                                                                                                                                                                                                                                                                                                                                               |
| MIN_ARCHIVE_SIZE         | "filesystem Object Parameters" on page 351                                                                                                                                                                                                                                                                                                                                                                                                                 |

| Parameter             | Section Discussed In                                                                                                                                                                                                 |
|-----------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| MIN_DIRECT_SIZE       | "msp Object Parameters for a DCM MSP" on page 460<br>"filesystem Object Parameters" on page 351                                                                                                                      |
| MIN_VOLUMES           | "volume group Object Parameters" on page 411                                                                                                                                                                         |
| MOUNT_BLOCKED_TIMEOUT | "drivegroup Object Parameters" on page 397                                                                                                                                                                           |
| MOUNT_SERVICE         | "device Object Parameters" on page 348<br>"drivegroup Object Parameters" on page 397                                                                                                                                 |
| MOUNT_SERVICE_GROUP   | "device Object Parameters" on page 348<br>"drivegroup Object Parameters" on page 397                                                                                                                                 |
| MOUNT_TIMEOUT         | "drivegroup Object Parameters" on page 397                                                                                                                                                                           |
| MOVE_FS               | "dmdaemon Object Parameters" on page 290                                                                                                                                                                             |
| MSG_DELAY             | "drivegroup Object Parameters" on page 397                                                                                                                                                                           |
| MSP_NAMES             | "dmdaemon Object Parameters" on page 290                                                                                                                                                                             |
| MULTIPLIER            | "migrate group Object Parameters" on page 427                                                                                                                                                                        |
| MULTITAPE_NODES       | "drivegroup Object Parameters" on page 397                                                                                                                                                                           |
| MVS_UNIT              | "msp Object Parameters for an FTP MSP" on page 455                                                                                                                                                                   |
| NAME_FORMAT           | "msp Object Parameters for a Cloud MSP" on page 449<br>"msp Object Parameters for a DCM MSP" on page 460<br>"msp Object Parameters for a Disk MSP" on page 467<br>"msp Object Parameters for an FTP MSP" on page 455 |
| NODE_ANNOUNCE_RATE    | "services Object Parameters" on page 300                                                                                                                                                                             |
| NODE_BANDWIDTH        | "base Object Parameters" on page 278<br>"node Object Parameters" on page 294                                                                                                                                         |
| NODE_TIMEOUT          | "services Object Parameters" on page 300                                                                                                                                                                             |
| OV_ACCESS_MODES       | "device Object Parameters" on page 348<br>"drivegroup Object Parameters" on page 397                                                                                                                                 |
| OV_INTERCHANGE_MODES  | "device Object Parameters" on page 348<br>"drivegroup Object Parameters" on page 397                                                                                                                                 |
| OV_KEY_FILE           | "base Object Parameters" on page 278                                                                                                                                                                                 |
| OV_SERVER             | "base Object Parameters" on page 278                                                                                                                                                                                 |
| PARTIAL_STATE_FILES   | "dmdaemon Object Parameters" on page 290                                                                                                                                                                             |

---

| Parameter                | Section Discussed In                                                                            |
|--------------------------|-------------------------------------------------------------------------------------------------|
| PENALTY                  | "resourcescheduler Object Parameters" on page 432                                               |
| PERF_RETENTION           | "taskgroup Object Parameters" on page 312                                                       |
| PERFTRACE_METRICS        | "base Object Parameters" on page 278                                                            |
| POLICIES                 | "filesystem Object Parameters" on page 351<br>"msp Object Parameters for a DCM MSP" on page 460 |
| POSITIONING              | "drivegroup Object Parameters" on page 397                                                      |
| POSITION_RETRY           | "drivegroup Object Parameters" on page 397                                                      |
| POSIX_FADVISE_SIZE       | "filesystem Object Parameters" on page 351                                                      |
| PRIORITY_PERIOD          | "msp Object Parameters for a DCM MSP" on page 460                                               |
| PUT_IDLE_DELAY           | "volumegroup Object Parameters" on page 411                                                     |
| PUTS_TIME                | "volumegroup Object Parameters" on page 411                                                     |
| READ_ERR_MAXIMUM         | "drivegroup Object Parameters" on page 397                                                      |
| READ_ERR_MINIMUM         | "drivegroup Object Parameters" on page 397                                                      |
| READ_ERR_TIMEOUT         | "drivegroup Object Parameters" on page 397                                                      |
| READ_IDLE_DELAY          | "drivegroup Object Parameters" on page 397<br>"volumegroup Object Parameters" on page 411       |
| READ_TIME                | "volumegroup Object Parameters" on page 411                                                     |
| RECALL_NOTIFICATION_RATE | "dm Daemon Object Parameters" on page 290                                                       |
| REDIRECT_TIME_DG_DOWN    | "drivegroup Object Parameters" on page 397                                                      |
| REINSTATE_DRIVE_DELAY    | "drivegroup Object Parameters" on page 397                                                      |
| REINSTATE_VOLUME_DELAY   | "drivegroup Object Parameters" on page 397                                                      |
| RELEASETHREADS           | "filesystem Object Parameters" on page 351                                                      |
| REMALENT_PARAMS          | "taskgroup Object Parameters" on page 312                                                       |
| REMPERF_PARAMS           | "taskgroup Object Parameters" on page 312                                                       |
| RESERVED_VOLUMES         | "volumegroup Object Parameters" on page 411                                                     |
| REWIND_DELAY             | "drivegroup Object Parameters" on page 397<br>"volumegroup Object Parameters" on page 411       |
| ROTATION_STRATEGY        | "migrategroup Object Parameters" on page 427                                                    |

| Parameter        | Section Discussed In                                                                                                                                                                                                                 |
|------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| RUN_TASK         | "Automated Maintenance Tasks" on page 175<br>"drivegroup Object Parameters" on page 397<br>"libraryserver Object Parameters" on page 393<br>"taskgroup Object Parameters" on page 312<br>"volumegroup Object Parameters" on page 411 |
| SCAN_FILESYSTEMS | "taskgroup Object Parameters" on page 312                                                                                                                                                                                            |
| SCAN_FOR_DMSTAT  | "taskgroup Object Parameters" on page 312                                                                                                                                                                                            |
| SCAN_OUTPUT      | "taskgroup Object Parameters" on page 312                                                                                                                                                                                            |
| SCAN_PARALLEL    | "taskgroup Object Parameters" on page 312                                                                                                                                                                                            |
| SCAN_PARAMS      | "taskgroup Object Parameters" on page 312                                                                                                                                                                                            |
| SELECT_LOWER_VG  | "VG Selection Parameters for a DCM MSP STORE_DIRECTORY" on page 380                                                                                                                                                                  |
| SELECT_MSP       | "MSP/VG Selection Parameters for a Managed Filesystem" on page 374                                                                                                                                                                   |
| SELECT_VG        | "MSP/VG Selection Parameters for a Managed Filesystem" on page 374                                                                                                                                                                   |
| SERVER_NAME      | "base Object Parameters" on page 278                                                                                                                                                                                                 |
| SERVICES         | "node Object Parameters" on page 294                                                                                                                                                                                                 |
| SERVICES_PORT    | "services Object Parameters" on page 300                                                                                                                                                                                             |
| SITE_SCRIPT      | "Automated Space-Management Parameters for a DCM MSP STORE_DIRECTORY" on page 376<br>"Automated Space-Management Parameters for a Managed Filesystem" on page 369<br>"msp Object Parameters for a DCM MSP" on page 460               |
| SPACE_WEIGHT     | "File Weighting Parameters for a Managed Filesystem" on page 371                                                                                                                                                                     |
| SPOOL_DIR        | "base Object Parameters" on page 278                                                                                                                                                                                                 |
| STORE_DIRECTORY  | "msp Object Parameters for a DCM MSP" on page 460<br>"msp Object Parameters for a Disk MSP" on page 467                                                                                                                              |

---

| Parameter         | Section Discussed In                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
|-------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| TASK_GROUPS       | "dmdaemon Object Parameters" on page 290<br>"drivegroup Object Parameters" on page 397<br>"filesystem Object Parameters" on page 351<br>"libraryserver Object Parameters" on page 393<br>"msp Object Parameters for a Cloud MSP" on page 449<br>"msp Object Parameters for a DCM MSP" on page 460<br>"msp Object Parameters for a Disk MSP" on page 467<br>"msp Object Parameters for an FTP MSP" on page 455<br>"services Object Parameters" on page 300<br>"taskgroup Object Parameters" on page 312<br>"volumegroup Object Parameters" on page 411 |
| THRESHOLD         | "taskgroup Object Parameters" on page 312                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| TIMEOUT_FLUSH     | "volumegroup Object Parameters" on page 411                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
| TMF_TMMNT_OPTIONS | "device Object Parameters" on page 348<br>"drivegroup Object Parameters" on page 397                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
| TMP_DIR           | "base Object Parameters" on page 278                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
| TSREPORT_OPTIONS  | "taskgroup Object Parameters" on page 312                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |



| Parameter          | Section Discussed In                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
|--------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| TYPE               | "allocationgroup Object Parameters" on page 435<br>"base Object Parameters" on page 278<br>"device Object Parameters" on page 348<br>"dmdaemon Object Parameters" on page 290<br>"drivegroup Object Parameters" on page 397<br>"dumpgroup Object Parameters" on page 343<br>"fastmountcache Object" on page 390<br>"filesystem Object Parameters" on page 351<br>"libraryserver Object Parameters" on page 393<br>"migrategroup Object Parameters" on page 427<br>"msp Object Parameters for a Cloud MSP" on page 449<br>"msp Object Parameters for a DCM MSP" on page 460<br>"msp Object Parameters for a Disk MSP" on page 467<br>"msp Object Parameters for an FTP MSP" on page 455<br>"node Object Parameters" on page 294<br>"policy Object" on page 364<br>"resourcescheduler Object Parameters" on page 432<br>"resourcewatcher Object Parameters" on page 434<br>"services Object Parameters" on page 300<br>"taskgroup Object Parameters" on page 312<br>"volumeobject Object Parameters" on page 411 |
| UPDATE_CTIME       | "filesystem Object Parameters" on page 351                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| USE_AS_DUMP_DEST   | "filesystem Object Parameters" on page 351                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| USE_UNIFIED_BUFFER | "filesystem Object Parameters" on page 351                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| VALID_ROOT_HOSTS   | "base Object Parameters" on page 278                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
| VERIFY_POSITION    | "drivegroup Object Parameters" on page 397                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| VOL_MSG_TIME       | "allocationgroup Object Parameters" on page 435<br>"volumeobject Object Parameters" on page 411                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
| VOLUME_GROUPS      | "drivegroup Object Parameters" on page 397                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| VOLUME_LIMIT       | "taskgroup Object Parameters" on page 312                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| WATCHER            | "libraryserver Object Parameters" on page 393                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
| WEIGHT             | "resourcescheduler Object Parameters" on page 432                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |

---

| Parameter      | Section Discussed In                                                                                                                                                                                                                                               |
|----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| WRITE_CHECKSUM | "drivegroup Object Parameters" on page 397<br>"msp Object Parameters for a Cloud MSP" on page 449<br>"msp Object Parameters for a DCM MSP" on page 460<br>"msp Object Parameters for a Disk MSP" on page 467<br>"msp Object Parameters for an FTP MSP" on page 455 |
| ZONE_SIZE      | "volumegroup Object Parameters" on page 411                                                                                                                                                                                                                        |

---

## Parallel DMF Configuration

This chapter discusses the following:

- "Parallel DMF Configuration Procedure" on page 485
- "Determining the State of Parallel Data-Mover Nodes" on page 488
- "Disabling Parallel Data-Mover Nodes" on page 489
- "Reenabling Parallel Data-Mover Nodes" on page 489

### Parallel DMF Configuration Procedure

If you are running DMF with the Parallel Data-Mover Option (Parallel DMF), do the following:

#### **Procedure 8-1** Configuring Parallel DMF

1. Configure the DMF configuration file (`/etc/dmf/dmf.conf`) on the DMF server according to the instructions in "Object Definitions" on page 272. Ensure that a `node` object is defined in `dmf.conf` for the parallel data-mover node that is being added.
2. Copy `/etc/dmf/dmf.conf` on the DMF server to `/etc/dmf/dmf.conf` on the DMF parallel data-mover node.

---

**Note:** Do not edit the `dmf.conf` file on the parallel data-mover node.

---

3. Install the software for the parallel data mover on the parallel data-mover node. See the *SGI InfiniteStorage Software Platform* release note for more information.
4. Configure CXFS according to the instructions in the *CXFS 7 Administrator Guide for SGI InfiniteStorage*.
5. Include the DMF parallel data-mover node as a CXFS client, such as by creating an `autoconf` rule. For more information, see the section about the `autoconf` command in the `cxfs_admin` chapter of the CXFS administrator guide or the `cxfs_admin(8)` man page.

For example, for two parallel data-mover nodes named `pdml` and `pdm2` in a CXFS cluster named `mycluster`:

```
# cxf_admin -c "create autoconf rule_name=pdmlrule policy=allowed \  
hostname=pdml enable_node=true" -i mycluster  
# cxf_admin -c "create autoconf rule_name=pdm2rule policy=allowed \  
hostname=pdm2 enable_node=true" -i mycluster
```

After you have finished creating or modifying all of the desired `autoconf` rules, you must unlock all `cxf_admin` sessions in order for nodes to be automatically configured. (The automatic configuration process must have access to the `cxf_admin` lock.)

If a node you refer to in an `autoconf` rule has previously been part of the CXFS cluster, or if the node fails to join the CXFS membership, you must reboot the node.

6. Configure the CXFS filesystems defined by the following DMF configuration parameters so that they are mounted only on the primary DMF server, the passive DMF server (if applicable), and each parallel data-mover node:

```
HOME_DIR  
CACHE_DIR  
MOVE_FS  
TMP_DIR  
SPOOL_DIR  
STORE_DIRECTORY for a DCM MSP
```

For more information about these parameters, see "base Object" on page 277.

For example, if the filesystem to be mounted on the directory specified by `CACHE_DIR` is on the `/dev/cxvm/fscache` device, you could specify the following `cxf_admin` commands to restrict it to the CXFS potential metadata server nodes on which the DMF server can run (say `server1` and `server2`) and the parallel data-mover nodes (say `pdml` and `pdm2`):

```
# cxf_admin -c "create filesystem name=fscache mount_new_nodes=false \  
nodes=server1,server2,pdml,pdm2" -i mycluster
```

For more information, see the section about the `mount` command in the `cxf_admin` chapter of the CXFS administrator guide.

7. If you use a directory other than those listed in step 6 for the `OV_KEY_FILE` configuration parameter, ensure that the OpenVault security key file is visible to the DMF server and all parallel data-mover nodes. See "base Object" on page 277.
8. Configure the managed filesystems as CXFS filesystems that are mounted on the DMF server and all of the parallel data-mover nodes. They may also be mounted on CXFS client-only nodes.
9. On the DMF server, use `ov_admin` to allow the parallel data-mover node to be a DCP-enabled OpenVault client machine. Do the following:
  - a. From the main menu in `ov_admin`, enter 22 to select `Manage OpenVault Client Machines`.
  - b. Enter 1 to select `Activate an OpenVault Client Machine` and follow the prompts. Be sure to answer `yes` when asked if the machine will run DCPs.

For more information about `ov_admin`, see the *OpenVault Administrator Guide for SGI InfiniteStorage*.

10. On the parallel data-mover node, use `ov_admin` to configure DCPs for those drives that it should operate.
11. If not already done, activate a privileged instance and an unprivileged instance of the `dmf` application for each parallel data-mover node. See "Configure OpenVault for DMF Use" on page 494.
12. Verify the DMF configuration; if there are errors, fix them and repeat the verification until there are no errors. You can do this by using DMF Manager or the `dmcheck(8)` script on the DMF server. For more information, see Chapter 6, "DMF Manager" on page 191.
13. Start the DMF mover service on the parallel data-mover node:

```
mover# service dmf_mover start
```

After initial configuration, changes to `dmf.conf` will normally be propagated to parallel data-mover nodes automatically while the DMF services are running. Certain changes, such as changing the `SERVER_NAME` or `SERVICES_PORT` of the DMF server, will require that you manually copy `dmf.conf` to the parallel data-mover nodes and then restart the DMF services on those nodes.

## Determining the State of Parallel Data-Mover Nodes

To determine the status of a parallel data-mover node, enter the following command as root:

```
# dmnode_admin -l
```

For example, showing the state for parallel data-mover nodes jar and zin:

```
# dmnode_admin -l
Node Name  State      Enabled  Active Since      Dropouts
jar        Inactive   Yes      -                  0
zin        Active     Yes      2008-Nov-26,12:45:48 0
```

The node state can be one of the following:

**Active**                    The node is connected to dmnode\_service on the DMF server and is eligible to run data-mover processes.

**Inactive**                 The node is not connected to dmnode\_service.

**Disabled**                The node is connected to dmnode\_service but has been disabled using dmnode\_admin. See "Disabling Parallel Data-Mover Nodes" on page 489.

**FileSysWait**             The node is connected to dmnode\_service but has not been made active by dmnode\_admin because a filesystem is mounted on the server but not on the node. The filesystem could be a managed filesystem or one of the filesystems identified by the following parameters in the DMF configuration file:

```
CACHE_DIR
HOME_DIR (if it contains the file specified by
```

```
OV_KEY_FILE)
```

```
MOVE_FS
SPOOL_DIR
STORE_DIRECTORY for a DCM MSP
TMP_DIR
```

**License Wait**            The node is connected to dmnode\_service but has not been made active by dmnode\_admin due to the

lack of a sufficient number of DMF parallel data mover licenses on the server.

The `Dropouts` field specifies the number of times that the node has transitioned from `Active` to `Inactive`. A non-zero count may indicate a problem with the mover node or network. This count is reset when `dmnode_service` is restarted.

---

**Note:** If `dmnode_service` is not running, the `dmnode_admin` command will not function. To restart `dmnode_service`, enter the following:

```
# service dmf start
```

---

## Disabling Parallel Data-Mover Nodes

To disable parallel data-mover nodes in order to perform maintenance on the system or to diagnose a problem, enter the following:

```
# dmnode_admin -d nodename ...
```

The node will remain disabled across DMF restarts.

The disabled node is no longer eligible to start new data-mover processes.

Existing data-mover processes on the disabled node will be told to exit after the library server notices this change, which may take up to 2 minutes. The existing data-mover processes may exit in the middle of recalling or migrating a file; this work will be reassigned to other data-mover processes. Stopping data-mover processes with the following command has the same result on existing processes:

```
# service dmf_mover stop
```

## Reenabling Parallel Data-Mover Nodes

To reenabling parallel data-mover nodes, making them eligible to run data-mover processes, enter the following as `root`:

```
# dmnode_admin -e nodename ...
```

The node will remain enabled across DMF restarts.

To determine the current state of a node, see "Determining the State of Parallel Data-Mover Nodes" on page 488.

---

**Note:** DMF and DMF Manager must be running for the `dmnode_admin` command to function.

---



## Mounting Service Configuration Tasks

This chapter discusses the following:

- "OpenVault Configuration Tasks" on page 491
- "TMF Configuration Tasks" on page 505

### OpenVault Configuration Tasks

This section discusses the following:

- "Configure the OpenVault Server" on page 492
- "Configure OpenVault for DMF Use" on page 494
- "Configure OpenVault for Each Parallel Data-Mover Node" on page 498
- "Configure OpenVault on the DMF Server If on a Different Host" on page 502
- "Configure OpenVault for a Drive Group" on page 502

---

**Note:** For additional information about COPAN MAID or COPAN VTL and OpenVault, see:

- *COPAN MAID for DMF Quick Start Guide*
  - *SGI 400 VTL for DMF Quick Start Guide*
-

## Configure the OpenVault Server

Following is an example of the steps you will take to initially configure the OpenVault server, using an example host named `dmfserver` as the OpenVault server (typically, the same host will be the DMF server and the OpenVault server). The characters `###` in the right margin highlight comments related to the steps, which follow the example:

```
dmfserver# ov_admin ### Step 1
```

```
    OpenVault Configuration
```

```
The general strategy for setting up OpenVault is to
```

- 1) configure the OpenVault server
- 2) configure LCP/DCPs on the server machine
- 3) configure server for local Applications
- 4) if needed, configure server for remote LCPs, DCPs, and Applications
- 5) if needed, install and configure LCP/DCPs on remote machines
- 6) from the server, for each library setup/import media

```
Where possible, defaults for each prompt are indicated by [value].  
Help text may be obtained by entering '?' at most prompts.
```

```
Some menus will present only the available options depending  
upon the software, hardware, or options that are installed.  
If you do not see the choice you are looking for, double check  
your installation to make sure the items are installed.
```

```
Press enter to continue...
```

```
There may be multiple OpenVault servers and networks in your area.  
Enter the name where the OpenVault server is listening (or will be  
listening after it has been configured). This may be the server's  
system hostname, or the hostname of another interface on the server  
if an alternative network is being used.
```

```
Name where the OpenVault server is (or will be) listening? [dmfserver] ### Step 2
```

```
The OpenVault server is not yet configured; would you like to do so now? [Yes] ### Step 3
```

```
What port number should the OpenVault server use? [695] ### Step 4
```

```
What security key would you like the admin commands to use? [none]
Waiting for OpenVault to initialize ...
The OpenVault server was successfully started.
```

**### Step 5****Comments:**

1. Log in to the system where the OpenVault server will run and invoke the OpenVault administration tool `ov_admin(8)`. SGI recommends that the OpenVault server run on the same node as the DMF server.
2. Enter the name associated with the IP address where the OpenVault server will listen. If OpenVault will be running on the same server as DMF, the OpenVault server should listen on the same interface used for DMF communications. Enter:
  - The server's virtual hostname if using high availability (HA)
  - The hostname used for the server's `INTERFACE` parameter (see "node Object" on page 294) if using the Parallel Data-Mover option with an alternative network.
  - The system hostname if using basic DMF or the Parallel Data-Mover Option with the default interface

---

**Note:** You must set the `OV_SERVER` parameter in the base object (see "base Object" on page 277).

---

3. Enter `Yes` to configure the OpenVault server.
4. Select a port number for the OpenVault server. Normally, you can use the default. You must use the same port number when configuring OpenVault on any parallel data-mover nodes.
5. Optionally provide a security key to prevent unauthorized clients from using the OpenVault administration commands if your environment is not secure (this will result in larger log files.)

## Configure OpenVault for DMF Use

You must give DMF permission to connect to OpenVault from various hosts and make use of drives and volumes by activating instances of the `dmf` application. The following example uses a host named `dmfserver` as the OpenVault server:

1. Add an unprivileged instance and then an privileged instance of the `dmf` application:

```
dmfserver# ov_admin ### Step a
```

```
Name where the OpenVault server is listening? [dmfserver] ### Step b
```

```
OpenVault Configuration Menu for server "dmfserver"
```

```
Configuration on Machines Running LCPs and DCPs
```

- 1 - Manage LCPs for locally attached Libraries
- 2 - Manage DCPs for locally attached Drives

```
Configuration on Admin-Enabled Machines
```

- 11 - Manage Cartridge Groups
- 12 - Manage Drive Groups
- 13 - Import Media

```
Configuration on the OpenVault Server Machine
```

- 21 - Manage Applications
- 22 - Manage OpenVault Client Machines

```
q - Exit.
```

```
Which operation would you like to do: 21 ### Step c
```

```
Manage Applications Menu
```

```
1 - Create a new Application
```

```
2 - Delete an Application
```

```
3 - Show all existing Applications
```

```
4 - Activate another Application Instance for an existing Application
```

```
5 - Deactivate an Application Instance
```

6 - Show all activated Application Instances

r - Return to Main Menu.

q - Exit.

Which operation would you like to do: 4

### Step d

Select the Application for which you want to activate a new Instance

1 - dmf

2 - ov\_umsh

r - Return to Previous Menu.

q - Exit.

Which operation would you like to do: 1

### Step e

Enter the name of the Host where an instance of Application "dmf" will run [dmfserver] \* ### Step f

Enter the Application's instance name or "\*" [] \* ### Step g

Should this Instance of the Application "dmf" be "privileged"? [No] ### Step h

What security key will the Application use [none] ### Step i

Unprivileged Instance "\*" of Application "dmf"  
was successfully activated on "dmfserver".

Press enter to continue... ### Step j

Manage Applications Menu

1 - Create a new Application

2 - Delete an Application

3 - Show all existing Applications

4 - Activate another Application Instance for an existing Application

5 - Deactivate an Application Instance

6 - Show all activated Application Instances

## 9: Mounting Service Configuration Tasks

---

r - Return to Main Menu.  
q - Exit.

Which operation would you like to do: **4**

**### Step k**

Select the Application for which you want to activate a new Instance

1 - dmf  
2 - ov\_umsh

r - Return to Previous Menu.  
q - Exit.

Which operation would you like to do: **1**

**### Step l**

Enter the name of the Host where an instance of Application "dmf" will run [dmfserver] \* **### Step m**

Enter the Application's instance name or "\*" [] \* **### Step n**

Should this Instance of the Application "dmf" be "privileged"? [No] **yes** **### Step o**

What security key will the Application use [none] **### Step p**

Privileged Instance "\*" of Application "dmf"  
was successfully activated on "dmfserver".

Press enter to continue...

Manage Applications Menu

1 - Create a new Application  
2 - Delete an Application  
3 - Show all existing Applications  
  
4 - Activate another Application Instance for an existing Application  
5 - Deactivate an Application Instance  
6 - Show all activated Application Instances

r - Return to Main Menu.  
q - Exit.

Which operation would you like to do: q  
dmfserver#

### Step q

**Comments:**

- a. Log in to the OpenVault server and invoke the OpenVault administration tool `ov_admin(8)`.
- b. Enter the name associated with the IP address on which the OpenVault server is listening.
- c. Enter 21 to manage applications.
- d. Enter 4 to activate another application instance.
- e. Enter 1 to select the application `dmf`.
- f. Enter the wildcard `*` character to allow the `dmf` application to be used from any host. (Alternatively, you can repeat these steps to create a privileged and an unprivileged application instance for each system that DMF runs on; that is, each DMF server and each parallel data-mover node).
- g. Enter the wildcard `*` for the application instance name.
- h. Use the default (No) to create the unprivileged instance.
- i. Optionally provide a security key.
- j. Press `Enter` to continue.
- k. Enter 4 to activate another application instance.
- l. Enter 1 to select the application `dmf`.
- m. Enter the wildcard `*` character to allow the `dmf` application to be used from any host. (See step f.)
- n. Enter the wildcard `*` for the application instance name.
- o. Enter `yes` to make the application privileged.
- p. Optionally provide a security key.

q. Enter q to exit.

2. Configure the base object for use with OpenVault. For example:

```
define base
    TYPE          base
    HOME_DIR      /dmf/home
.
.
.
    OV_KEY_FILE   /dmf/home/ov_keys
```

For more information, see "base Object" on page 277.

3. Use the `dmov_keyfile(8)` command to create the file defined by the `OV_KEY_FILE` parameter. This command will prompt you for the unprivileged and privileged keys that you defined.

### Configure OpenVault for Each Parallel Data-Mover Node

Following is an example of the steps you will take to configure the Parallel Data-Mover Option. You will repeat these steps for each parallel data-mover node:

1. On the OpenVault server (for example, named `dmfserver`), activate the parallel data-mover node (such as `mover1`) as a client:

```
dmfserver# ov_admin                                     ### Step 1a
Name where the OpenVault server is (or will be) listening? [dmfserver]  ### Step 1b

OpenVault Configuration Menu for server "dmfserver"

Configuration on Machines Running LCPs and DCPs
  1 - Manage LCPs for locally attached Libraries
  2 - Manage DCPs for locally attached Drives

Configuration on Admin-Enabled Machines
  11 - Manage Cartridge Groups
  12 - Manage Drive Groups
  13 - Import Media

Configuration on the OpenVault Server Machine
```



- 21 - Manage Applications
- 22 - Manage OpenVault Client Machines

q - Exit.

Which operation would you like to do: **22**

**### Step 1c**

Manage OpenVault Client Machines Menu

- 1 - Activate an OpenVault Client Machine
- 2 - Deactivate an OpenVault Client Machine
- 3 - Show all OpenVault Client Machines

r - Return to Main Menu.

q - Exit.

Which operation would you like to do: **1**

**### Step 1d**

Which Client Machine do you want to activate? [**]** **mover1**

**### Step 1e**

What security key would you like the Client Machine mover1 to use? [none]

**### Step 1f**

Will DCPs and/or LCPs also be configured to run on "mover1"? [Yes]

**### Step 1g**

The Client Machine "mover1" was successfully activated.

Press enter to continue...

Manage OpenVault Client Machines Menu

- 1 - Activate an OpenVault Client Machine
- 2 - Deactivate an OpenVault Client Machine
- 3 - Show all OpenVault Client Machines

r - Return to Main Menu.

q - Exit.

Which operation would you like to do: **q**

**### Step 1h**

**Comments:**

- a. Log in to the OpenVault server and invoke the OpenVault administration tool `ov_admin(8)`.
  - b. Enter the name associated with the IP address on which the OpenVault server is listening.
  - c. Enter 22 to manage an OpenVault client.
  - d. Enter 1 to activate a client.
  - e. Enter the system name of the parallel data-mover node, such as `mover1`.
  - f. Optionally provide a security key to protect against clients masquerading as allowed clients.
  - g. Press `Enter` to allow DCPs and LCPs to run on the parallel data-mover node.
  - h. Enter `q` to exit.
2. On the parallel data-mover node (for example, `mover1`), specify the name on which OpenVault is listening, the port number, and optional security key:

```
mover1# ov_admin
```

**### Step 2a**

```
OpenVault Configuration
```

The general strategy for setting up OpenVault is to

- 1) configure the OpenVault server
- 2) configure LCP/DCPs on the server machine
- 3) configure server for local Applications
- 4) if needed, configure server for remote LCPs, DCPs, and Applications
- 5) if needed, install and configure LCP/DCPs on remote machines
- 6) from the server, for each library setup/import media

Where possible, defaults for each prompt are indicated by `[value]`.  
Help text may be obtained by entering `'?'` at most prompts.

Some menus will present only the available options depending upon the software, hardware, or options that are installed. If you do not see the choice you are looking for, double check your installation to make sure the items are installed.

Press enter to continue...

There may be multiple OpenVault servers and networks in your area. Enter the name where the OpenVault server is listening (or will be listening after it has been configured). This may be the server's system hostname, or the hostname of another interface on the server if an alternative network is being used.

Name where the OpenVault server is (or will be) listening? [dmfserver] **### Step 2b**

What port number is the OpenVault server on dmfserver using? [695] **### Step 2c**

What security key would you like the admin commands to use? [none] **### Step 2d**

OpenVault Configuration Menu for server "dmfserver"

Configuration on Machines Running LCPs and DCPs  
1 - Manage LCPs for locally attached Libraries  
2 - Manage DCPs for locally attached Drives

Configuration on Admin-Enabled Machines  
11 - Manage Cartridge Groups  
12 - Manage Drive Groups  
13 - Import Media

q - Exit.

Which operation would you like to do: q **### Step 2e**

#### Comments:

- a. Log in to the parallel data-mover node and invoke the OpenVault administration tool `ov_admin(8)`.
- b. Enter the same name here as you did when initially configuring the OpenVault server. (This will also be the same value you entered in 1b).
- c. Enter the same port here as you did when initially configuring the OpenVault server (step 4 of "Configure the OpenVault Server" on page 492).
- d. If you specified a security key in 1f, enter the same value here.

- e. Enter `q` to exit.

## Configure OpenVault on the DMF Server If on a Different Host

---

**Note:** If the same host is both the OpenVault server and the DMF server, this procedure is not needed.

---

If the OpenVault server is on a different host from the DMF server, you must repeat the steps in "Configure OpenVault for Each Parallel Data-Mover Node" on page 498 on the DMF server host in order to configure it for OpenVault.

## Configure OpenVault for a Drive Group

Procedure 9-1 describes the steps you must take to configure OpenVault for a drive group.

### Procedure 9-1 Configuring OpenVault for a Drive Group

---

**Note:** The procedure that follows assumes that before you complete the steps described, the OpenVault server is configured and all drives and libraries are configured and OpenVault is running. For more information about configuring OpenVault, see the `ov_admin(8)` man page and *OpenVault Administrator Guide for SGI InfiniteStorage*.

---

1. Add DMF as a valid application to appropriate cartridge groups.

The `ov_admin` script allows you to specify the cartridge groups when the DMF application is created or, after creation of the DMF application, you can choose the menu option that allows you to manage cartridge groups. For more information, see the `ov_admin(8)` man page.

2. Add the DMF application as a valid user to appropriate OpenVault drive groups. The OpenVault drive groups that DMF uses must contain only fungible drives. That is, the drives in the OpenVault drive group must have identical characteristics and accessibility, so that any volume that can be mounted and written on one of the drives can also be mounted and read on any of the other drives within the group. Failure to provide identical mounting and accessibility characteristics to all drives in an OpenVault drive group used by an LS might result in mount failures.

Choose the appropriate item from the `ov_admin` menu. If for some reason you cannot use the `ov_admin` script, you can enter the command manually, as follows:

```
ov_drivegroup -a -G drive_group -A dmf
```

3. Configure the following parameters as needed in the LS's `drivegroup` object for use with OpenVault:

```
MOUNT_SERVICE
MOUNT_SERVICE_GROUP
OV_INTERCHANGE_MODES
```

For example:

```
define dg_c00
    TYPE                drivegroup
    VOLUME_GROUPS       vg_c00
    MOUNT_SERVICE       openvault
    MOUNT_SERVICE_GROUP dg_c00
    OV_INTERCHANGE_MODES compression
enddef
```

For more information, see:

- "device Object" on page 347
  - "drivegroup Object Parameters" on page 397
4. Make the appropriate cartridges accessible to the allocation groups, VGs, or filesystem backup scripts by assigning the cartridges to the DMF application in OpenVault. Do the following:

- To find out which drives are in each drive group:

```
# ov_dumptable -n -d'|' -c DriveGroupName,DriveName,LibraryName DRIVE
ultrium3grp|drive1|lib1
ultrium3grp|drive2|lib1
ultrium4grp|drive3|lib1
ultrium4grp|drive4|lib1
```

- To find out which cartridge types each drive can mount:

```
# ov_dumptable -n -d'|' -c DriveName,CartridgeTypeName DCPCAPABILITY | sort -u
drive1|Ultrium1-100
drive1|Ultrium2-200
```

```
drive1|Ultrium3-400
drive2|Ultrium1-100
drive2|Ultrium2-200
drive2|Ultrium3-400
drive3|Ultrium2-200
drive3|Ultrium3-400
drive3|Ultrium4-800
drive4|Ultrium2-200
drive4|Ultrium3-400
drive4|Ultrium4-800
```

In this example, any Ultrium4-800 cartridges can only be used in the `ultrium4grp` drive group.

- To find out the possible cartridge groups:

```
# ov_cartgroup -s -A dmf
```

- Do one of the following to make both DMF and OpenVault aware of the cartridges to be mounted:



**Caution:** All cartridges that DMF mounts via OpenVault must have the correct cartridge type. Failure to correctly specify the cartridge type can result in errors when reading and writing data. Contact your SGI service representative if you have questions about cartridge type specification.

---

- If you already have tapes defined in your LS database or in a `DUMP_TAPES` file but OpenVault is not aware of them, and every cartridge in the given LS, VG, or task group is of the same cartridge type, you can tell OpenVault about these tapes by entering one of the following:

```
dmov_makecarts [-g cartgroup] [-t carttype] taskgroupnames
dmov_makecarts [-g cartgroup] [-t carttype] lsnames
dmov_makecarts [-g cartgroup] [-t carttype] [-v vg1,vg2,...] lsname
```

You can replace any of the references to a VG previously mentioned with an AG. If the `-v` parameter is omitted, all VGs and allocation groups in the specified LS will be processed. Tapes will be added to the file controlling the `run_full_dump.sh` and `run_partial_dump.sh` scripts by specifying the name of the task group that refers to them.

- If you have volumes that neither DMF nor OpenVault is aware of, you can import them by cartridge type into OpenVault and add them to DMF by VG, AG, or task group by entering one of the following:

```
dmov_loadtapes [-g cartgroup] [-l library] [-s tapesize] [-t carttype] vgname
dmov_loadtapes [-g cartgroup] [-l library] [-s tapesize] [-t carttype] agname
dmov_loadtapes [-g cartgroup] [-l library] [-s tapesize] [-t carttype] taskgroupname
```

This command will invoke a `vi(1)` session. In the `vi` session, delete any cartridges that you do **not** want added to the LS database. All cartridges that are left in the `vi` session file must be of the same cartridge type, the type you specified with the `-t` option. Volumes will be added to the file controlling the `run_full_dump.sh` and `run_partial_dump.sh` scripts by specifying the name of the task group which refers to them.

- If neither of the above cases apply, you can manually configure the cartridges. The following commands can be useful in this effort:

- Use `ov_stat` to list cartridges in a library. For example:

```
ov_stat -s -L library
```

- Use `ov_lscarts` to list information on cartridges known to OpenVault. For example:

```
ov_lscarts -f '.*'
```

- Use `ov_import` and `dmvoladm` to add the unmanaged cartridges to OpenVault and DMF, and use `vi` to edit the task group in the file specified by the `DUMP_TAPES` parameter in the `taskgroup` stanza in the `dmf.conf` file.

## TMF Configuration Tasks

Use one of the following `dmvoladm(8)` commands to add tapes to the LS database:

```
dmvoladm -l lsname -c 'create vsn001-vsn010 vg vgname [ts tapesize]'
dmvoladm -l lsname -c 'create vsn001-vsn010 vg vgname [ts tapesize]'
```

An AG is specified by the `vg` option, just like a VG. Specifying the tape size will allow commands such as `dmcapacity(8)` and its display in DMF Manager to accurately estimate the remaining capacity of the volume.

There is no special procedure to inform TMF of a tape's existence. TMF assumes that every tape it deals with is in the library or can be provided by an operator, as needed.



## Message Log Files

The `dmfdaemon`, `dmlockmgr`, `dmfsmon`, media-specific process (MSP), and library server (LS) message log files use the same general naming convention and message format. The filenames for message logs are created using the extension `yyyymmdd`, which represents the year, month, and day of file creation.

Each line in a message log file begins with the time the message was issued, an optional message level, the process ID number, and the name of the program that issued the message.

The optional message level is described below. The remainder of the line contains informative or diagnostic information. The following sections provide details about each of these logs:

- "Automated Space Management Log File" on page 513 for information about `dmfsmon` and `autolog.yyyymmdd`
- "Daemon Logs and Journals" on page 525 for information about `dmfdaemon` and `dmdlog.yyyymmdd`
- "dmlockmgr Communication and Log Files" on page 527 for information about `dmlockmgr` and `dmlocklog.yyyymmdd`
- "LS Logs" on page 539 and "FTP MSP Activity Log" on page 575 for information about `dmatls`, `dmdskmsp`, `dmftpmisp`, and `misplog.yyyymmdd`
- Chapter 15, "DMF Maintenance" on page 585, for information about log maintenance

Messages in the `dmdlog`, `dmlocklog`, `moverlog`, and `misplog` files contain a 2-character field immediately following the time field in each message that is issued. This feature helps to categorize the messages and can be used to extract error messages automatically from these logs. Because the only indication of DMF operational failure may be messages written to the DMF logs, recurring problems can go undetected if you do not check the logs daily.

Possible message types for `autolog`, `dmdlog`, `moverlog`, `misplog`, and `dmlocklog` are defined in Table 10-1. The table also lists the corresponding message levels in the configuration file.

**Table 10-1** Message Types and Levels

| Field | Message Type  | Message Level |
|-------|---------------|---------------|
| -E    | Error         | 0             |
| -O    | Ordinary      | 0             |
| -I    | Informative   | 1             |
| -V    | Verbose       | 2             |
| -1    | Debug level 1 | 3             |
| -2    | Debug level 2 | 4             |
| -3    | Debug level 3 | 5             |
| -4    | Debug level 4 | 6             |

## Automated Space Management

This chapter discusses the following:

- "The `dmfsmon` Daemon and `dmfsfree` Command" on page 509
- "Generating the Candidate List" on page 510
- "Selection of Migration Candidates" on page 511
- "Space Management and the DCM MSP" on page 513
- "Automated Space Management Log File" on page 513

### The `dmfsmon` Daemon and `dmfsfree` Command

The `dmfsmon(8)` daemon monitors the free-space levels in filesystems configured with automated space management enabled (`auto`). When the free space in one of the filesystems falls below the free-space minimum, `dmfsmon` invokes `dmfsfree(8)`. The `dmfsfree` command attempts to bring the free space and migrated space of a filesystem into compliance with configured values. You can also invoke `dmfsfree` directly.

When the free space in one of the filesystems falls below its minimum, `dmfsfree` performs the following steps:

- Scans the filesystem for files that can be migrated and freed or ranges of files that can be freed. Each of these candidates is assigned a weight. This information is used to create a list, called a *candidate list*, that contains an entry for each file or range and is ordered by weight (largest to smallest).
- Selects enough candidates to bring the free space back up to the desired level. Files or ranges of files are selected in order from largest weight to smallest.
- Selects enough regular files from the candidate list to achieve the *migration target*, the integer percentage of total filesystem space that `dmfsmon` tries to maintain as a reserve of space that is free or occupied by dual-state files (whose online space can be freed quickly) if free space reaches or falls below the *free-space minimum threshold*. Files are selected from the candidate list in order from largest weight to smallest weight.

The `dmfsmon` daemon should be running whenever DMF is active. You control automated space management by setting the filesystem and policy configuration parameters in the DMF configuration file. The configuration parameters specify targets for migration and free space as well as one or more policies for weighting. Only filesystems configured as `MIGRATION_LEVEL auto` in the configuration file are included in the space-management process. "policy Object" on page 364, describes how to configure automated space management.

You can change the migration level of a filesystem by editing the configuration file.

## Generating the Candidate List

The first step in the migration process occurs when `dmfsmon` determines it is time to invoke `dmfsfree`, which scans the filesystem and generates the candidate list. During candidate list generation, the inode of each online file in the specified filesystem is audited and a weight is computed for it.

A filesystem is associated with a weighting policy in the DMF configuration file. The applicable weighting policy determines a file's total weight, or, if a `ranges` clause is specified in the configuration file, the range's total weight. Total file or range weight is the sum of the `AGE_WEIGHT` and `SPACE_WEIGHT` parameters. Defaults are provided for these parameters, and you can configure either to make a change. You do not need to configure a weighting policy if the defaults are acceptable, but you should be aware that the default selects files based on age and not on size. If you want to configure a policy based on size that ignores file age, you should set `AGE_WEIGHT` to `0 0`.

The default weighting policy bases the weight of the file on the time that has passed since the file was last accessed or modified. Usually, the more recent a file's access, the more likely it is to be accessed again.

The candidate list is ordered by total file or range weight (largest to smallest). You can prevent a file from being automatically migrated by making sure that no ranges within the file have a positive weight value. You can configure the weighting parameters to have a negative value to ensure that certain files or ranges are never automatically freed.

---

**Note:** If you use negative weights to exclude files or ranges from migration, you must ensure that a filesystem does not fill with files or ranges that are never selected for automatic migration.

---

You can use the `dmscanfs(8)` command to print file information to standard output (`stdout`).

## Selection of Migration Candidates

The `dmfsfree(8)` utility processes each ordered candidate list sequentially, seeking candidates to migrate and possibly free. The extent of the selection process is governed by values defined for the filesystem in the DMF configuration file as described in "policy Object" on page 364.

The most essential parameters are as follows:


- `FREE_SPACE_MINIMUM`
- `FREE_SPACE_TARGET`
- `MIGRATION_TARGET`

For more information about these parameters, see:

- "Automated Space-Management Parameters for a Managed Filesystem" on page 369
- "Automated Space-Management Parameters for a DCM MSP `STORE_DIRECTORY`" on page 376

When `dmfsmon` detects that the free space on a filesystem has fallen below the level you have set as `FREE_SPACE_MINIMUM`, it invokes `dmfsfree` to select a sufficient number of candidates to meet the `FREE_SPACE_TARGET`. The `dmfsfree` utility ensures that these files are migrated and releases their disk blocks. It then selects additional candidates to meet the `MIGRATION_TARGET` and migrates them.

Figure 11-1 shows the relationship of automated space management migration targets to each other. Migration events occur when file activity causes free filesystem space to drop below `FREE_SPACE_MINIMUM`. `dmfsmon` generates a candidate list and begins to migrate files and free the disk blocks until the `FREE_SPACE_TARGET` is met, and then it migrates regular files (creating dual-state files) until the `MIGRATION_TARGET` is met.



**Figure 11-1** Relationship of Automated Space Management Targets

If `dmfsmon` does not find enough files to migrate (because all remaining files are exempt from migration), it uses another configuration parameter to decrement `FREE_SPACE_MINIMUM`.

`FREE_SPACE_DECREMENT` specifies the percentage of filesystem space by which `dmfsmon` will decrement `FREE_SPACE_MINIMUM` if it cannot find enough files to migrate to reach `FREE_SPACE_MINIMUM`. For example, suppose `FREE_SPACE_MINIMUM` is set to 10 and `FREE_SPACE_DECREMENT` is set to 2. If `dmfsmon` cannot find enough files to migrate to reach 10% free space, it will decrement `FREE_SPACE_MINIMUM` to 8 and try to find enough files to migrate so that 8% of the filesystem is free. If `dmfsmon` cannot achieve this percentage, it will decrement `FREE_SPACE_MINIMUM` to 6. `dmfsmon` will continue until it reaches a value for `FREE_SPACE_MINIMUM` that it can achieve, and it will try to maintain that

new value. `dmfsmon` restores `FREE_SPACE_MINIMUM` to its configured value when it can be achieved. The default value for `FREE_SPACE_DECREMENT` is 2.

---

**Note:** DMF manages real-time partitions differently than files in a normal partition. The `dmfsfree` command can only migrate files in the non-real-time partition; it ignores files in the real-time partition. Any configuration parameters you set will apply only to the non-real-time partition. Files in the real-time partition can be manually migrated with the commands `dmget(1)`, `dmput(1)`, and `dmmigrate(8)`. Files are retrieved automatically when they are read.

---

## Space Management and the DCM MSP

DMF prevents the disk cache manager (DCM) media-specific process (MSP) cache from filling by following the same general approach it takes with managed filesystems, with the following differences:

- The disk MSP (`dmdskmsp`) monitors the cache, instead of a separate monitoring program such as `dmfsmon`.
  - The `dmdskfree` utility controls the movement of cache files to tape. This is analogous to `dmfsfree`.
- 

**Note:** The DCM MSP uses parameters that are similar to those used for the disk MSP, although some names are different. See "policy Object" on page 364.

---

## Automated Space Management Log File

All of the space-management commands record their activities in a common log, `autolog.yyyymmdd` (where `yyymmdd` is the year, month, and day of file creation). The first space-management command to execute on a given day creates the log file for that day. This file resides in the directory `SPOOL_DIR/daemon_name` (The `SPOOL_DIR` value is specified by the `SPOOL_DIR` configuration parameter; see "base Object" on page 277). The space-management commands create the `daemon_name` subdirectory in `SPOOL_DIR` if it does not already exist. The full pathname of the common log file follows:

`SPOOL_DIR/daemon_name/autolog.yyyymmdd`

Each line in the `autolog` file begins with the time of message issue, followed by the name of the host where the message issuer ran, and the process number and program name of the message issuer. The remainder of the line contains informative or diagnostic information such as the following:

- Name of the filesystem being processed
- Number of files selected for migration and freeing
- Number of disk blocks that were migrated and freed
- Names of any other DMF commands executed
- Command's success or failure in meeting the migration and free-space targets

The following excerpt shows the format of an `autolog` file (line breaks shown here for readability):

```
23:39:35:702-V zap 237082-dmfsmon /dmfusr1 - free_space=39.79, minimum=38
23:39:35:702-V zap 237082-dmfsmon /dmfusr3 - free_space=15.48,minimum=15
23:40:55:723-I zap 237082-dmfsmon Started 3409 for execution on /dmfusr3
23:40:56:782-I zap 3409-dmfsfree /dmfusr3 - Number of blocks in the filesystem = 122232448
23:40:56:782-I zap 3409-dmfsfree /dmfusr3 - Number of blocks in the free space target = 24446490 (20%)
23:40:56:782-I zap 3409-dmfsfree /dmfusr3 - Number of blocks currently free = 18287168 (15.0%)
23:40:56:782-I zap 3409-dmfsfree /dmfusr3 - Number of blocks to free = 6159322 (5.0%)
23:40:56:782-I zap 3409-dmfsfree /dmfusr3 - Number of blocks in the migration target = 97785960 (80%)
23:40:56:782-I zap 3409-dmfsfree /dmfusr3 - Number of blocks currently migrated = 74419040 (60.9%)
23:40:56:782-I zap 3409-dmfsfree /dmfusr3 - Number of blocks to migrate = 5079752 (4.2%)
23:40:56:782-I zap 3409-dmfsfree /dmfusr3 - Summary of files: online = 3760, offline = 6537, unmigrating
= 30, partial = 0
23:40:56:782-I zap 3409-dmfsfree /dmfusr3 - Number of candidates = 3629, rejected files = 0, rejected
ranges = 0
23:41:31:150-I zap 3409-dmfsfree /dmfusr3 - Migrated 5104824 blocks in 169 files
23:41:31:150-I zap 3409-dmfsfree /dmfusr3 - Freed 6164480 blocks in 303 files
23:41:31:150-O zap 3409-dmfsfree /dmfusr3 - Exiting: minimum reached - targets met by outstanding requests.
```



## The DMF Daemon

The DMF daemon, `dmfdaemon(8)`, is the core component of DMF. The daemon exchanges messages with commands, the kernel, the media-specific processes (MSPs), and the library servers (LSs).

When DMF is started, the daemon database is automatically initialized. To start the daemon manually, use the DMF startup script, as follows:

```
# service dmf start
```



---

**Caution:** For instructions about starting and stopping DMF and the mounting service in an HA environment, see *High Availability Guide for SGI InfiniteStorage*.

---

Typically, DMF should be initialized as part of the normal system startup procedure by using a direct call in a system startup script in the `/etc/rc2.d` directory.

The following sections provide additional information:

- "Daemon Processing" on page 515
- "Daemon Database and `dmdadm`" on page 517
- "Daemon Logs and Journals" on page 525

## Daemon Processing

After initialization, `dmfdaemon` performs the following steps:

1. Isolates itself as a daemon process.
2. Checks for the existence of other `dmfdaemon` processes. If another `dmfdaemon` exists, the newer one terminates immediately.
3. Initializes the daemon log.
4. Opens the daemon database.
5. Initializes the daemon request socket.
6. Initiates the MSPs and LSs.

7. Enters its main request processing.

The daemon uses log files and journal files as described in "Daemon Logs and Journals" on page 525.

The main request processing section of the DMF daemon consists of the following sequence:

1. The `select(2)` system call, which is used to wait for requests or for a default time-out interval
2. A request dispatch switch to read and process requests detected by the `select` call
3. A time processor, which checks activities (such as displaying statistics and running the administrator tasks) done on a time-interval basis

This processing sequence is repeated until a stop request is received from the `dmdstop(8)` command, which is normally executed via an `/etc/init.d` script by the service `dmf stop` command line. When a normal termination is received, the MSPs and LSs are terminated, the daemon database is closed, and the logs are completed.

A typical request to the daemon starts with communication from the requester. The requester is either the kernel (over the DMF device interface) or a user-level request (from the command pipe). A user-level command can originate from the automated space-management commands or from an individual user.

After receipt, the command is dispatched to the appropriate command processor within the daemon. Usually, this processor must communicate with an MSP or LS before completing the specified request. The commands are queued within the daemon and are also queued to a specific group of daemon database entries. All entries referring to the same file share the same BFID. The command is dormant until the reply from the MSP/LS is received or the MSP/LS terminates. When command processing is completed, a final reply is sent to the issuing process, if it still exists.

A final reply usually indicates that the command has completed or an error has occurred. Often, error responses require that you analyze the daemon log file to obtain a full explanation of the error. An error response issued immediately usually results from an invalid or incorrect request (for example, a request to migrate a file that has no data blocks). A delayed error response usually indicates a database, daemon, MSP, or LS problem.

## Daemon Database and `dmdadm`

This section discusses the following:

- "Overview of the Daemon Database and `dmdadm`" on page 517
- "`dmdadm` Directives" on page 518
- "`dmdadm` Field and Format Keywords" on page 520
- "`dmdadm` Text Field Order" on page 524

### Overview of the Daemon Database and `dmdadm`

The daemon database resides in the directory `HOME_DIR/daemon_name`. The daemon database contains information about the offline copies of a given file, as well as some information about the original file. The daemon database also contains the bit-file identifier (BFID), which is assigned when the file is first migrated.

Other information maintained on a per-entry basis includes the following:

- File size (in bytes)
- MSP or volume group (VG) name and recall path
- Date and time information, including the following:
  - Time at which the record was created
  - Time at which the record was last updated
  - A check time for use by the administrator
  - A soft-delete time, indicating when the entry was soft-deleted
- Original device and inode number
- Base portion of the original filename, if known

The `dmdadm(8)` command provides maintenance services for the daemon database.

`dmdadm` executes directives from `stdin` or from the command line when you use the `-c` option. All directives start with a directive name followed by one or more parameters. Parameters may be positional or keyword-value pairs, depending on the command. White space separates the directive name, keywords, and values.

When you are inside the `dmdadm` interface, you see the following prompt:

```
adm command_number >
```

At this point, the command has a 30-minute timeout associated with it. If you do not enter a response within 30 minutes of the prompt having been displayed, the `dmdadm` session terminates with a descriptive message. This behavior on all the database administrative commands limits the amount of time that an administrator can lock the daemon and MSP/LS databases from updates.

## `dmdadm` Directives

The `dmdadm` directives are as follows:

| <b>Directive</b>    | <b>Description</b>                                                                                                                                                     |
|---------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>count</code>  | Displays the number of records that match the expression provided.                                                                                                     |
| <code>create</code> | Creates a record.                                                                                                                                                      |
| <code>delete</code> | Deletes the specified records.                                                                                                                                         |
| <code>dump</code>   | Prints the specified records to standard out in ASCII; each field is separated by the pipe character ( <code> </code> ).                                               |
| <code>help</code>   | Displays help.                                                                                                                                                         |
| <code>list</code>   | Shows the fields of selected records. You may specify which fields are shown.                                                                                          |
| <code>load</code>   | Applies records to the daemon database obtained from running the <code>dump</code> directive.                                                                          |
| <code>quit</code>   | Stops program execution after flushing any changed database records to disk. The abbreviation <code>q</code> and the string <code>exit</code> produce the same effect. |
| <code>set</code>    | Specifies the fields to be shown in subsequent <code>list</code> directives.                                                                                           |
| <code>update</code> | Modifies the specified records.                                                                                                                                        |

The syntax for the `dmdadm` directives is as follows:

```
count selection [limit]  
create bfid settings  
delete selection [limit]  
dump selection [limit]  
help
```

```
list selection [limit] [format]  
load filename  
quit (or q or exit)  
set format  
update selection [limit] to settings...
```

where:

- The *selection* parameter specifies the records to be acted upon.
- The *limit* parameter restricts the records acted upon.
- The *bfid* parameter for the `create` directive specifies the bit-file identifier (BFID) for the record being created.
- The *settings* parameter for the `create` and `update` directives specifies one or more fields and their values.
- The *format* parameter selects the way in which output is displayed. Any program or script that parses the output from this command should explicitly specify a format; otherwise the default is used, which may change from release to release.

The value for *selection* can be one of the following:

- A BFID or range of BFIDs
- The keyword `all`
- A period (`.`), which recalls the previous selection
- An expression involving any of the above, field value comparisons, `and`, `or`, or parentheses

A field value comparison may use the following to compare a field keyword to an appropriate value:

```
< (less than)  
> (greater than)  
= (equal to)  
!= (not equal to)  
<= (less than or equal to)  
>= (greater than or equal to)
```

The syntax for *selection* is as follows:

```
selection ::= or-expr
or-expr ::= and-expr [ or or-expr ]
and-expr ::= nested-expr [ and or-expr ]
nested-expr ::= comparison | ( or-expr )
comparison ::= bfid-range | field-keyword op field-value
op ::= < | > | = | != | >= | <=
bfid-range ::= bfid [ - bfid ] | [ bfid - [ bfid ] ] | key-macro
key-macro ::= all
field-keyword ::= name or abbreviation of the record field
field-value ::= appropriate value for the field
bfid ::= character representation of the bfid
```

Thus valid values for *selection* could be any of the following:

```
305c74b200000010-305c74b200000029
7fffffff000f4411-
-305c74b20000004c8
all
origsize>1m
. and origage<7d
```

## **dmcdadm Field and Format Keywords**

The *field* parameter keywords listed below can be used as follows:

- In a *selection* parameter to select records
- In a *settings* parameter as part of a keyword-value pair, in order to specify new values for a field
- In a *format* parameter

When specifying new values for fields, some of the field keywords are valid only if you also specify the `-u` (unsafe) option.

| <b>Keyword</b>             | <b>Description</b>                                                                                                                                                                                  |
|----------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>checkage (ca)</code> | The time at which the record was last checked; the same as <code>checktime</code> , except that it is specified as an <i>age string</i> (see below). Valid only in unsafe ( <code>-u</code> ) mode. |

|                 |                                                                                                                                                      |
|-----------------|------------------------------------------------------------------------------------------------------------------------------------------------------|
| checktime (ct)  | The time at which the record was last checked; an integer that reflects raw UNIX or Linux time. Valid only in unsafe (-u) mode.                      |
| deleteage (da)  | The time at which the record was soft-deleted; the same as deletetime, except that it is specified as an age string. Valid only in unsafe (-u) mode. |
| deletetime (dt) | The time at which the record was soft-deleted; an integer that reflects raw UNIX or Linux time. Valid only in unsafe (-u) mode.                      |
| mspname (mn)    | The name of the MSP or VG with which the file is associated; a string of up to 8 characters. Valid only in unsafe (-u) mode.                         |
| mspkey (mk)     | The string that the MSP or VG can use to recall a record; a string of up to 50 characters. Valid only in unsafe (-u) mode.                           |
| origage (oa)    | Time at which the record was created; the same as origtime, except that it is specified as an age string.                                            |
| origdevice (od) | Original device number of the file; an integer.                                                                                                      |
| originode (oi)  | Original inode number of the file; an integer.                                                                                                       |
| origname (on)   | Base portion of the original filename; a string of up to 14 characters.                                                                              |
| origsize (os)   | Original size of the file; an integer.                                                                                                               |
| origtime (ot)   | Time at which the record was created; an integer that reflects raw UNIX or Linux time.                                                               |
| origuid (ou)    | Original user ID of the record; an integer.                                                                                                          |
| updateage (ua)  | Time at which the record was last updated; the same as updatetime, except that it is specified as an age string.                                     |
| updatetime (ut) | Time at which the record was last updated; an integer that reflects raw UNIX or Linux time.                                                          |

The time field keywords (checktime, deletetime, origtime, and updatetime) can have one of the following values:

- now

- UNIX or Linux *raw time* (that is, seconds since January 1, 1970)

These keywords display their value as raw time. The value comparison `>` used with the date keywords means newer than the value given. For example, `>36000` is newer than 10AM on January 1, 1970, and `>852081200` is newer than 10AM on January 1, 1997.

The age field keywords (`checkage`, `deleteage`, `origage`, and `updateage`) let you express time as a string. They display their value as an integer followed by the following:

w (weeks)  
d (days)  
h (hours)  
m (minutes)  
s (seconds)

For example, `8w12d7h16m20s` means 8 weeks, 12 days, 7 hours, 16 minutes, and 20 seconds old.

The comparison `>` used with the age keywords means older than the value given (that is, `>5d` is older than 5 days).

A *limit* parameter in a directive restricts the records acted upon. It consists of one of the following keywords followed by white space and then a value:

| Keyword                       | Description                                                                                                                                                                                                                                                                                                                                                                                                                    |
|-------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>recordlimit (r1)</code> | Limits the number of records acted upon to the value that you specify; an integer.                                                                                                                                                                                                                                                                                                                                             |
| <code>recordorder (ro)</code> | Specifies the order that records are scanned: <ul style="list-style-type: none"><li>• <code>bfid</code>, which specifies that the records are scanned in BFID order.</li><li>• <code>data</code>, which specifies that the records are scanned in the order in which they are found in the daemon database data file. <code>data</code> is more efficient for large databases, although it is essentially unordered.</li></ul> |

The *format* parameter selects a format to use for the display. If, for example, you want to display fields in a different order than the default or want to include fields that are not included in the default display, you specify them with the format parameter. The format parameter in a directive consists of one of the following:



```
format default
format keyword
format field-keywords
```

The `format keyword` form is intended for parsing by a program or script and therefore suppresses the headings.

The *field-keywords* may be delimited by colons or white space; white space requires the use of quotation marks.

---

**Note:** BFID is always included as the first field and need not be specified.

---

For any field that takes a byte count, you may append one of the following letters (in either uppercase or lowercase) to the integer to indicate that the value is to be multiplied (all of which are powers of 1000, not 1024):

```
k or K for 1 thousand
m or M for 1 million
g or G for 1 billion
```

The following is sample output from the `dmdadm list` directive; `recordlimit 20` specifies that you want to see only the first 20 records.

```
adm 3>list all recordlimit 20
```

| BFID             | ORIG<br>UID | ORIG<br>SIZE | ORIG MSP<br>AGE NAME | MSP<br>KEY |
|------------------|-------------|--------------|----------------------|------------|
| 305c74b200000010 | 20934       | 69140480     | 537d silo1           | 88b49f     |
| 305c74b200000013 | 26444       | 279290       | 537d silo1           | 88b4a2     |
| 305c74b200000014 | 10634       | 67000        | 537d silo1           | 88b4a3     |
| 305c74b200000016 | 10634       | 284356608    | 537d silo1           | 88b4a5     |
| 305c74b200000018 | 10634       | 1986560      | 537d silo1           | 88b4a7     |
| 305c74b20000001b | 26444       | 232681       | 537d silo1           | 88b4aa     |
| 305c74b20000001c | 10015       | 7533688      | 537d silo1           | 88b4ab     |
| 305c74b200000022 | 8964        | 23194990     | 537d silo1           | 88b4b1     |
| 305c74b200000023 | 1294        | 133562368    | 537d silo1           | 88b4b2     |
| 305c74b200000024 | 10634       | 67000        | 537d silo1           | 88b4b3     |
| 305c74b200000025 | 10634       | 284356608    | 537d silo1           | 88b4b4     |
| 305c74b200000026 | 10634       | 1986560      | 537d silo1           | 88b4b5     |
| 305c74b200000027 | 1294        | 1114112      | 537d silo1           | 88b4b6     |
| 305c74b200000028 | 10634       | 25270        | 537d silo1           | 88b4b7     |
| 305c74b200000029 | 1294        | 65077248     | 537d silo1           | 88b4b8     |

```
305c74b20000002b 9244      2740120  537d silo1  88b4ba
305c74b200000064 9335           9272  537d silo1  88b4f3
305c74b200000065 9335      10154  537d silo1  88b4f4
305c74b200000066 9335           4624  537d silo1  88b4f5
305c74b200000067 9335      10155  537d silo1  88b4f6
adm 4>
```

The following example displays the number of records in the daemon database that are associated with user ID 11789 and that were updated during the last five days:

```
adm 3>count origuid=11789 and updateage<5d
72 records found.
```

### **dmdadm Text Field Order**

The text field order for daemon records generated by the `dmdump(8)`, `dmdumpj(8)`, and the `dump` directive in `dmdadm` is listed below. This is the format expected by the `load` directives in `dmdadm`:

1. bfid
2. origdevice
3. originode
4. origsize
5. origtime
6. updatetime
7. checktime
8. deletetime
9. origuid
10. origname
11. mspname
12. mspkey

To isolate the `mspname` and `mspkey` from the daemon records soft-deleted fewer than three days ago, use the following command:

```
dmdadm -c "dump deleteage<3d and deletetime>0" | awk "-F|" '{print $11,$12}'
```

## Daemon Logs and Journals

The DMF daemon uses log files to track various types of activity. Journal files are used to track daemon database transactions.

The ASCII log of daemon actions has the following format (*SPOOL\_DIR* refers to the directory specified by the *SPOOL\_DIR* configuration parameter):

```
SPOOL_DIR/daemon_name/dmdlog.yyyymmdd
```

The convention is that *yyyy*, *mm*, and *dd* correspond to the date on which the log file was created (representing year, month, and day, respectively). Log files are created automatically by the DMF daemon.

---

**Note:** Because the DMF daemon will continue to create log files and journal files without limit, you must remove obsolete files periodically by configuring the `run_remove_logs` and `run_remove_journals` tasks in the configuration file, as described in "taskgroup Object" on page 304.

---

The DMF daemon automatically creates journal files that track daemon database transactions. They have the following pathname format (*JOURNAL\_DIR* refers to the directory defined by the *JOURNAL\_DIR* configuration parameter):

```
JOURNAL_DIR/daemon_name/dmd_db.yyyymmdd[.hhmmss]
```

Existing journal files are closed and new ones created in two circumstances:

- When the first transaction after midnight occurs
- When the journal file reaches size defined by the *JOURNAL\_SIZE* configuration parameter

When the first transaction after midnight occurs, the existing open journal file is closed, and the suffix `.235959` is appended to the current filename no matter what the time (or date) of closing. The closed file represents the last (or only) transaction log of the date *yyymmdd*. A new journal file with the current date is then created.

When the journal file reaches `JOURNAL_SIZE`, the file is closed and the suffix `.hhmmss` is added to the name; `hh`, `mm`, and `ss` represent the hour, minute, and second of file closing. A new journal file with the same date but no time is then created.

For example, the following shows the contents of a `JOURNAL_DIR/daemon_name` directory on 15 June 1998:

```
dmd_db.19980604.235959 dmd_db.19980612.235959
dmd_db.19980605.235959 dmd_db.19980613.145514
dmd_db.19980608.235959 dmd_db.19980613.214233
dmd_db.19980609.235959 dmd_db.19980613.235959
dmd_db.19980610.235959 dmd_db.19980614.235959
dmd_db.19980611.094745 dmd_db.19980615
dmd_db.19980611.101937
dmd_db.19980611.110429
dmd_db.19980611.235959
```

For every date on which daemon database transactions occurred, there will exist a file with that date and the suffix `.235959`, with the exception of an existing open journal file. Some dates have additional files because the transaction log reached `JOURNAL_SIZE` at a specified time and the file was closed.

You can configure `daemon_tasks` parameters to remove old journal files (using the `run_remove_journals.sh` task and the `JOURNAL_RETENTION` parameter. For more information, see "taskgroup Object" on page 304.



**Warning:** If a daemon database becomes corrupt, recovery consists of applying journals to a backup copy of the database. Database recovery procedures are described in "Recovery and Restoration of DMF Database" on page 646.

---

## The DMF Lock Manager

The `dmlockmgr(8)` process must be executing at all times for any DMF process to safely access and update a DMF database. The `dmlockmgr` process and its clients — such as `dmatls`, `dmfdaemon(8)`, `dmvoladm(8)`, and `dmcatadm(8)` — communicate through files, semaphores, and message queues. There are times when abnormal process terminations will result in non-orderly exit processing that will leave files and/or interprocess communication (IPC) resources allocated. As a DMF administrator, periodically you will want to look for these resources to remove them.

---

**Note:** `HOME_DIR` and `SPOOL_DIR` refer to the values of the `HOME_DIR` and `SPOOL_DIR` parameter, respectively, in the DMF configuration file. See "base Object" on page 277.

---

The `dmlockmgr` files used by the database utilities are found in several different places. There are the following types of files:

- "dmlockmgr Communication and Log Files" on page 527
- "dmlockmgr Individual Transaction Log Files" on page 529

### dmlockmgr Communication and Log Files

The `dmlockmgr` communication and activity log files are all found in a directory formed by `HOME_DIR/RDM_LM`. The `HOME_DIR/RDM_LM` and `HOME_DIR/RDM_LM/ftok_files` directories contain the token files used to form the keys that are used to create and access the IPC resources necessary for the `dmlockmgr` to communicate with its clients, its standard output file, and the transaction file.

The `dmlockmgr` token files have the form shown in Table 13-1 on page 528.

**Table 13-1** dmlockmgr Token Files

| File                                                              | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
|-------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>HOME_DIR</i> /RDM_LM/dmlockmgr                                 | Used by the dmlockmgr and its clients to access dmlockmgr's semaphore and input message queue                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| <i>HOME_DIR</i> /RDM_LM/ftok_files/ft <i>nnnn</i>                 | Preallocated token files that are not currently in use. As processes attempt to connect to dmlockmgr, these files will be used and renamed as described below. <i>nnnn</i> is a four-digit number 0000-0099.                                                                                                                                                                                                                                                                                                                                                                                                  |
| <i>HOME_DIR</i> /RDM_LM/ftok_files/ft <i>nnnn</i> . <i>xxxpid</i> | <p>The renamed version of the preallocated token files. <i>nnnn</i> is a four-digit number 0000-0099. <i>xxx</i> is a three-character process identifier with the following meaning:</p> <ul style="list-style-type: none"> <li>• atr = dmatread</li> <li>• ats = dmatsnf</li> <li>• cat = dmcataadm</li> <li>• ddb = dmdadm</li> <li>• dmd = dmfdemon</li> <li>• dmv = dmmove</li> <li>• hde = dmhdelete</li> <li>• lfs = dmloadfs</li> <li>• lib = dmatls</li> <li>• sel = dmselect</li> <li>• vol = dmvoladm</li> </ul> <p><i>pid</i> is the numeric process ID of the process connected to dmlockmgr.</p> |

The IPC resources used by DMF are always released during normal process exit cleanup. If one of the dmlockmgr client processes dies without removing its message queue, dmlockmgr will remove that queue when it detects the death of the client. The token files themselves are periodically cleaned up by the dmlockmgr process.

---

**Note:** Normally, the `dmlockmgr` process is terminated as part of normal shutdown procedures. However if you wish to stop `dmlockmgr` manually, you must use the following command:

```
/usr/sbin/dmclripc -u dmlockmgr -z HOME_DIR/RDM_LM
```

This command will do all of the necessary IPC resource and token file maintenance.

---

If the `dmlockmgr` process aborts, all DMF processes must be stopped and restarted in order to relogin to a new `dmlockmgr` process. If the `dmfdaemon` or `dmatls` processes abort during a period when the `dmlockmgr` has died, when they restart they will attempt to restart the `dmlockmgr`. The new `dmlockmgr` process will detect existing DMF processes that were communicating with the now-dead copy of `dmlockmgr`, and it will send a termination message to those DMF processes.

The `dmlockmgr` maintains a log file that is named as follows, where *yyyy*, *mm*, and *dd* are the year, month, and day:

```
HOME_DIR/RDM_LM/dmlocklog.yyyymmdd
```

The log file is closed and a new one opened at the first log request of a new day, although these files typically are not large. These log files are removed via the `run_remove_log.sh` daemon task command. For more information about `run_remove_log.sh`, see "taskgroup Object" on page 304.

## dmlockmgr Individual Transaction Log Files

The individual transaction log files have the following form:

```
prefix.log
```

where *prefix* is the same format as the token filename described in Table 13-1 on page 528 as `ftnnnn.xxxpid`. The prefix associates a log file directly with the token file of the same name.

Most of these log files will be created in the *HOME\_DIR* under the daemon's and library servers' subdirectories. In almost all cases, the processes that create these log files will remove them when they exit. However, if a process terminates abnormally, its log file may not be removed. Transaction log files can sometimes become quite large, on the order of 10's of Mbytes. Most of these orphaned log files will be removed by the daemon as part of its normal operation.

Several DMF commands allow accessing copies of database files in places other than the *HOME\_DIR*. If an orphaned log is encountered in a location other than in the *HOME\_DIR*, it may be removed after it is clear that it is no longer in use. In order to verify that it is no longer in use, search the *HOME\_DIR/RDM\_LM/ftok\_files* directory for a file with the same name as the prefix of the log file. If no such *ftok\_files* file exists, it is safe to remove the log file.

The transaction activity file, *HOME\_DIR/RDM\_LM/vista.taf*, is the transaction log file that contains information about active transactions in the system. It is used to facilitate automatic database transaction processing.



---

**Caution:** Do not delete the *HOME\_DIR/RDM\_LM/vista.taf* file.

---



## Library Servers and Media-Specific Processes

This chapter discusses the following for library servers (LSs) and media-specific processes (MSPs):

- "LS Operations" on page 532
- "Cloud MSP" on page 569
- "FTP MSP" on page 573
- "Disk MSP" on page 576
- "DCM MSP" on page 579
- "dmdskvfy Command" on page 579
- "Moving Migrated Data" on page 579
- "LS Error Analysis and Avoidance" on page 580
- "LS Drive Scheduling" on page 582
- "LS Status Monitoring" on page 582

## LS Operations

This section discusses the following:

- "LS Overview" on page 532
- "LS Directories" on page 533
- "Media Concepts" on page 534
- "CAT Records" on page 536
- "VOL Records" on page 537
- "LS Journals" on page 538
- "LS Logs" on page 539
- "Volume Merging" on page 543
- "dmcatadm Command" on page 544
- "dmvoladm Command" on page 554
- "dmatread Command" on page 567
- "dmatsnf Command" on page 568
- "dmaudit verifymsp Command" on page 568

## LS Overview

The LS consists of the following programs:

```
dmats  
dmatwc  
dmatrc
```

The DMF daemon executes `dmats` as a child process. In turn, `dmats` executes `dmatwc` (the write child) to write data to tape and `dmatrc` (the read child) to read data from tape.

The `dmats` program maintains the following records in the LS database:

- Catalog (CAT) records, which contain information about the files that the LS maintains

- Volume (VOL) records, which contain information about the media that the LS uses

The database files are not text files and cannot be updated by standard utility programs. Detailed information about the database files and their associated utilities is provided in "CAT Records" on page 536 and "VOL Records" on page 537.

The LS provides a mechanism for copying active data from volumes that contain largely obsolete data to volumes that contain mostly active data. This process is referred to as *volume merging*. Data on LS volumes becomes obsolete when users delete or modify their files. Volume merging can be configured to occur automatically (see "LS Tasks" on page 441). It can also be triggered by marking LS volumes as sparse with the `dmvoladm(8)` command.

The LS provides the following utilities that read LS volumes directly:

- `dmatread(8)` copies all or part of a migrated file to disk
- `dmatsnf(8)` audits and verifies LS volumes

## LS Directories

Each instance of the LS needs three types of directories, one for each of the following:

- Database files for CAT and VOL records
- Database journal files
- Log files

Sites define the location of these directories by editing the base object configuration file parameters `HOME_DIR`, `JOURNAL_DIR`, and `SPOOL_DIR`, whose values are referred to as *HOME\_DIR*, *JOURNAL\_DIR*, and *SPOOL\_DIR* in this document. A given instance of the LS creates a subdirectory named after itself in each of these three directories.

For example, if an instance of the LS is called `cart1`, its database files reside in directory `HOME_DIR/cart1`. If another instance of the LS is called `cart2`, its database files reside in `HOME_DIR/cart2`. If an instance of the LS is called `cart3`, its database files reside in `HOME_DIR/cart3`.

Similarly, LS `cart1` stores its journal files in directory `JOURNAL_DIR/cart1` and its log files and other working files in `SPOOL_DIR/cart1`.

## Media Concepts

The LS takes full advantage of the capabilities of modern media devices, including data compression and fast media positioning. To accommodate these capabilities and to provide recovery from surface or other media defects, `dmatis` uses a number of structural concepts built on top of traditional media structure.

The components are as follows:

- The *block* is the basic structural component of most media technologies. It is the physical unit of I/O to and from the media. The optimal block size varies with the device type. For example, the default block size for an STK T10000A tape drive is 524288 bytes.
- A *chunk* is as much or as little of a user file as fits on the remainder of the media (see Figure 14-1 on page 536). Thus, every migrated file has at least one, and sometimes many, chunks. Such a concept is necessary because the capacity of a volume is unknown until written, both because of natural variation in the medium itself and because the effect of data compression varies with the data contents.
- A *zone* is a logical block containing many physical blocks ending with a media mark. A zone has a target size that is configurable by media type. The default zone size is 5000000 bytes.

The VG writes chunks into the zone until one of three conditions occurs:

- The zone size is exceeded
- The VG exhausts chunks to write
- The end of media is encountered


Thus, the actual zone size can vary from well below the target size to the entire volume. A zone never spans physical volumes.

The zone plays several roles:

- The zone size is the amount of data that triggers `dmatis` to start a process to write files to secondary storage.
- The LS maintains the beginning of each zone in its database. This allows the LS to use fast hardware positioning functions to return to the beginning, so that it can restore the chunks in that zone.

Because getting the media position and writing a media mark can be very costly, the concept of a zone and the target size provides a way to control the trade offs between write performance, safety, and recall speed.

Figure 14-1 illustrates the way files are distributed over chunks, zones, and volumes, depending upon the file size. In this example, the tape with volume serial number (VSN) VOL001 has two zones and contains six files and part of a seventh. The tapes with VSNs VOL002 and VOL003 contain the rest of file *g*. Notice that on VOL001 file *g* is associated with chunk 7, while on the other two tapes it is associated with chunk 1. File *g* has three VSNs associated with it, and each tape associates the file with a chunk and zone unique to that tape.



**Figure 14-1** Media Concepts

### CAT Records

Catalog (CAT) records store the location of each file chunk in terms of its volume, zone, and chunk number. The key for these records is the file's bit-file identifier (BFID).

---

**Note:** You do not explicitly create CAT records; they are created when files migrate.

---

There are the following files:

| <b>CAT Files</b>                                                 | <b>Description</b>                       |
|------------------------------------------------------------------|------------------------------------------|
| <code>tpcrdm.dat</code>                                          | Contains the catalog data records        |
| <code>tpcrdm.key1.keys</code> ,<br><code>tpcrdm.key2.keys</code> | Contains the indexes to the catalog data |

The `libsrv_db.dbd` LS database definition file in the same directory describes the CAT record files and their record structure.

All files are non-ASCII and cannot be maintained by standard utility programs. The `dmcatadm` command provides facilities to create, query, and modify CAT records (see "dmcatadm Command" on page 544).

---

**Note:** The ability to create or modify CAT records with `dmcatadm` is provided primarily for testing or error recovery purposes. In the normal course of operations, you would never use this capability.

---

## VOL Records

Volume (VOL) records in the LS database contain information about each volume that exists in the pool of tapes to be used by `dmatlis`. These records are indexed by the volume serial number (VSN) of each volume and contain information such as the following:

- Volume's type
- Estimated capacity
- Label type
- A number of flags indicating the state of the volume
- VG or allocation group

---

**Note:** Unlike CAT records, you must create VOL records before using `dmatis` for the first time.

---

There are the following files:

| <b>VOL Files</b>                                   | <b>Description</b>                              |
|----------------------------------------------------|-------------------------------------------------|
| <code>tpvr<sub>dm</sub>.dat</code>                 | Contains the volume data records                |
| <code>tpvr<sub>dm</sub>.vs<sub>n</sub>.keys</code> | Contains the indexes to the volume data records |

The `libsrv_db.dbd` LS database definition file in the same directory describes the VOL record files and their record structure.

The files contain binary data and require special maintenance utilities. The `dmvoladm` command provides facilities to create, query, and modify VOL records; for more information, see "dmvoladm Command" on page 554. Additional database maintenance utilities are described in "Recovery and Restoration of DMF Database" on page 646.

---

**Note:** If you have more than one instance of a VG, you must ensure that the volume sets for each are mutually exclusive.

---

## LS Journals

Each instance of `dmatis` protects its database by recording every transaction in a journal file. Journal file pathnames have the following format:

*JOURNAL\_DIR*/*ls\_name*/*libsr<sub>v</sub>\_db.yyyymmdd[.hhmmss]*

The LS creates journal files automatically.

Existing journal files are closed and new ones created in two circumstances:

- When the first transaction after midnight occurs
- When the journal file reaches the size defined by the `JOURNAL_SIZE` configuration parameter

When the first transaction after midnight occurs, the existing open journal file is closed and the suffix `.235959` is appended to the current filename no matter what



the time (or date) of closing. The closed file represents the last (or only) transaction log of the date *yyyymmdd*. A new journal file with the current date is then created.

When the journal file reaches `JOURNAL_SIZE`, the file is closed and the suffix *.hhmmss* is added to the name; *hh*, *mm*, and *ss* represent the hour, minute, and second of file closing. A new journal file with the same date but no time is then created.

For example, the following shows the contents of a *JOURNAL\_DIR/ls\_name* directory on 15 June 2004:

```
libsrv_db.20040527.235959  libsrv_db.20040606.235959
libsrv_db.20040528.235959  libsrv_db.20040607.235959
libsrv_db.20040529.235959  libsrv_db.20040608.235959
libsrv_db.20040530.235959  libsrv_db.20040609.235959
libsrv_db.20040531.235959  libsrv_db.20040610.235959
libsrv_db.20040601.235959  libsrv_db.20040611.235959
libsrv_db.20040602.235959  libsrv_db.20040612.235959
libsrv_db.20040603.235959  libsrv_db.20040613.235959
libsrv_db.20040604.235959  libsrv_db.20040614.235959
libsrv_db.20040605.235959  libsrv_db.20040615
```

For every date on which LS database transactions occurred, there will exist a file with that date and the suffix *.235959*, with the exception of an existing open journal file. Some dates may have additional files because the transaction log reached `JOURNAL_SIZE` at a specified time and the file was closed.

You can configure `daemon_tasks` parameters to remove old journal files (using the `run_remove_journals.sh` task and the `JOURNAL_RETENTION` parameter. For more information, see "taskgroup Object" on page 304.

If an LS database becomes corrupt, recovery consists of applying the journal files to a backup copy of the database.

## LS Logs

All DMF MSPs and LSs maintain log files named `m脾og.yyyymmdd` in the MSP/LS spool directory which, by default, is `SPOOL_DIR/m脾name`. `SPOOL_DIR` is configured in the `base` object of the configuration file; `m脾name` is the name of the MSP/LS in the `daemon` object of the configuration file; `yyymmdd` is the current year, month, and day.

These log files are distinct from the logs maintained by the DMF daemon; however, some of the messages that occur in the daemon log are responses that the MSP/LS generates. The content of the log is controlled by the `MESSAGE_LEVEL` configuration

parameter. For a description of the levels of logging available, see Table 10-1 on page 508 and the `dmf.conf(5)` man page.

The `mbsplog.yyyymmdd` file is the primary log for the LS and contains most of the messages. This file is written by `dmatls`. In addition, `dmatrc` and `dmatwc` create a `moverlog.yyyymmdd` log file each day in the subdirectory `moverlogs/hostname`.

This section describes informational statistics provided by the tape log files. These messages appear in the `SPOOL_DIR/msp_name/mbsplog.yyyymmdd` files. Timing information provided (such as MB transferred per second) should not be used as an accurate benchmark of actual data transfer rates. This information is provided for monitoring DMF and should only be used in comparison to similar data provided by DMF. Text in all uppercase references a parameter defined in the DMF configuration file. For more information, see Chapter 7, "DMF Configuration File" on page 271, the comments in the sample configuration file, and the `dmf.conf(5)` man page.

---

**Note:** Because the LS will continue to create log files and journal files without limit, you must remove obsolete files periodically by configuring the `run_remove_logs.sh` and `run_remove_journals.sh` tasks in the configuration file, as described in "taskgroup Object" on page 304.

---

**Example 14-1** LS Statistics Messages

The following is an example of LS statistics messages taken from an `msspllog.yyyymmdd` file. These messages are automatically and periodically issued by the LS.

```
08:46:00:404-I zap 237076-dmatls vg1.stats: children=2/2/0/2, btp=672617104/527956913/0, wc=1/2, cwc=?
08:46:00:404-I zap 237076-dmatls vg2.stats: children=0/0/0/2, btp=0/0/0, wc=0/2, cwc=?
08:46:00:404-I zap 237076-dmatls vg1.stats: data put=92957.718 mb, data recalled=24964.680 mb
08:46:00:404-I zap 237076-dmatls vg2.stats: data put=1239.537 mb, data recalled=1120.492 mb
08:46:00:404-I zap 237076-dmatls vg1.stats: Put_File - 0 8900 0 282 0
08:46:00:404-I zap 237076-dmatls vg1.stats: Get_File - 0 1809 0 0 0
08:46:00:404-I zap 237076-dmatls vg1.stats: Delete_File - 0 107618 0 0 0
08:46:00:404-I zap 237076-dmatls vg1.stats: Cancel_Req - 0 282 0 0 0
08:46:00:404-I zap 237076-dmatls vg1.stats: Flushall - 0 5 0 0 0
08:46:00:404-I zap 237076-dmatls vg1.stats: Merge - 44 0 0 0 0
08:46:00:404-I zap 237076-dmatls vg2.stats: Put_File - 0 1850 0 211 0
08:46:00:404-I zap 237076-dmatls vg2.stats: Get_File - 0 68 0 0 0
08:46:00:404-I zap 237076-dmatls vg2.stats: Delete_File - 0 4 0 0 0
08:46:00:404-I zap 237076-dmatls vg2.stats: Cancel_Req - 0 211 0 0 0
08:46:00:404-I zap 237076-dmatls vg2.stats: Flushall - 0 1 1 0 0
08:46:00:404-I zap 237076-dmatls vg1.stats: mc=2, ms=2000000000, mu=679346176, sm=0
```

The information provided by these entries is defined as follows:

- `children=2/2/0/2` represents the total child processes (2), the active child processes (2), the clean processes running (0), and the current maximum number of children the VG may have (2). Clean children are used when a `dmatrc` or `dmatwc` process dies without cleaning up.
- `btp=672617104/527956913/0` represents the bytes queued for putting (672617104), the threshold at which to start the next put child (527956913), and the bytes assigned to socket I/O (0)
- `wc=1/2` represents the active write child processes (1) and the configured value of `MAX_PUT_CHILDREN` (2)
- `cwc=?` represents the host name and process ID of the current write child (that is, the write child that is accepting data to write). `?` represents none.

The next set of lines gives the total amount of data put (such as 92957.718 MB) and recalled (such as 24964.680 MB).

The next set of six lines provide statistics for each type of VG request. Statistics information is provided only for requests that have been issued since the LS was started. These lines have the following format:

*request\_name*    *active*    *successful*    *errors*    *canceled*    *forwards*

where:

|                   |                                                                                                                                                                                                                                                                                                                                                                                                                        |
|-------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>active</i>     | Represents the number of requests not yet completed.                                                                                                                                                                                                                                                                                                                                                                   |
| <i>successful</i> | Represents the number of successfully completed requests.                                                                                                                                                                                                                                                                                                                                                              |
| <i>error</i>      | Represents the number of requests that completed with errors.                                                                                                                                                                                                                                                                                                                                                          |
| <i>canceled</i>   | Represents the number of canceled requests.                                                                                                                                                                                                                                                                                                                                                                            |
| <i>forwards</i>   | Represents the number of requests that were returned to the DMF daemon so it could forward them to another VG. For example, if the volume for a recall request in the primary VG was not in the library, but a copy existed in a secondary VG, the primary VG would return the request to the DMF daemon which would then forward it to the secondary VG, and the value displayed in this column would be incremented. |

The last set of lines provide the following information:

- *mc* is the configured value for *MERGE\_CUTOFF*, the cutoff to stop scheduling media for merging (such as 2)
- *ms* is the configured value for *CACHE\_SPACE*, the merge cache space available (such as 2000000000 bytes)
- *mu* is the merge cache space used (such as 679346176 bytes)
- *sm* is the number of socket merge children (0)

The LS write child (*dmatwc*) and read child (*dmatrc*) also produce statistics messages in the *moverlog* file. These messages contain timing statistics whose format changes from release to release, and they are not documented in this manual.

## Volume Merging

---

**Note:** Merging is not appropriate for a volume configured as a fast-mount cache.

---

When users delete or modify their migrated files, the copy that is on secondary storage becomes obsolete. Over time, some volumes will become entirely empty and can be reused. However, most volumes experience a gradual increase in the ratio of obsolete data to active data; such volumes are said to be *sparsely populated* or *sparse*. To reclaim the unused space on these volumes, DMF provides a *volume merge* facility, which copies the active data from several sparse volumes to a new volume, thus freeing the sparse volumes for reuse. Volume merging can be configured to occur automatically by using the `run_merge_tapes.sh` or `run_merge_mgr.sh` tasks (see "LS Tasks" on page 441).

Volume merging can also be done manually. `dmatls` performs merge operations whenever sparse volumes and the necessary resources exist at the same time. Use the `dmvoladm select` directive to mark VG volumes as sparse. (The `select` directive is described in "dmvoladm Command" on page 554.) Because the merge processing occurs simultaneously with other DMF activities, it is easiest to configure DMF to automatically perform merges at night or during other periods of relatively low activity.

The `dmatls` utility can perform volume-to-volume merging. Volume-to-volume merging is accomplished by moving data across a socket connection between the LS read-child and the LS write-child. The benefit of using a socket to transfer data between volumes is that you do not have to reserve disk space. The drawback to using a socket for data transfer is the cost of linking the process that performs the read with the process that performs the write.

In busy environments that have heavy contention for drives, the close coupling between the socket's reader and writer can be costly, especially when short files are being transferred. For large files, the overhead and possible delays in waiting for both volumes to be mounted is small compared to the benefit of rapid transfer and zero impact on free disk space. For this reason, you can move small files through a disk cache and big files through a socket. This process is mediated by the following configuration parameters:

```
CACHE_DIR
CACHE_SPACE
MAX_CACHE_FILE
MERGE_CUTOFF
```

For more information, see Chapter 7, "DMF Configuration File" on page 271.

Using a small amount of disk space to hold small chunks can have a significant impact on the total time required to perform merges. The default configuration options are set to move 100% of merge data across sockets.

---

**Note:** It is important to avoid volume merging on more than one VG simultaneously if they share a device. If you initiate a merge process on more than one VG on the same device at the same time (either by entering the same time in the DMF configuration file or by triggering the process manually), both processes will compete for media transports. When a limited number of media transports are available, a deadlock can occur. If you chose not to configure DMF to perform merges automatically by configuring the `run_merge_tape.sh` or `run_merge_mgr.sh` tasks, ensure that your cron jobs that automatically initiate volume merging refrain from initiating a second merge process until after all previously initiated merges are complete. You can accomplish this by using the `dmvoladm` command within the cron job to check for volumes that have the `hsparse` flag, as shown in the following example for an LS with two VGs:

```
tapes=$(dmvoladm -m ls -c "count hsparse")
if [[ -z "$tapes" ]]; then
    # start merge on vg2
    dmvoladm -m ls -c "select hfull and threshold<=30 and vg=vg2"
fi
```

---

## **dmcatadm Command**

The `dmcatadm(8)` command provides maintenance services for CAT records.

When you are inside the `dmcatadm` interface, you see the following prompt:

```
adm command_number >
```

At this point, the command has a 30-minute timeout associated with it. If you do not enter a response within 30 minutes of the prompt having been displayed, the `dmcatadm` session terminates with a descriptive message. This behavior on all the database administrative commands limits the amount of time that an administrator can lock the daemon database and the LS database from updates.

---

**Note:** Most of these facilities, especially the ability to create and modify CAT records in the LS database, are intended primarily for testing or error recovery purposes.

---

### dmcatadm Directives

The `dmcatadm` command executes directives from `stdin` or from the command line when you use the `-c` option. All directives start with a directive name followed by one or more parameters. Parameters may be positional or keyword-value pairs, depending on the command. White space separates the directive name, keywords, and values.

The `dmcatadm` directives are as follows:

| <b>Directive</b>    | <b>Description</b>                                                                                                                                                     |
|---------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>count</code>  | Displays the number of records that match the expression provided.                                                                                                     |
| <code>create</code> | Creates a CAT record.                                                                                                                                                  |
| <code>delete</code> | Deletes the specified CAT records.                                                                                                                                     |
| <code>dump</code>   | Prints the specified CAT records to standard out in ASCII; each field is separated by the pipe character ( <code> </code> ).                                           |
| <code>help</code>   | Displays help.                                                                                                                                                         |
| <code>list</code>   | Shows the fields of selected CAT records. You may specify which fields are shown.                                                                                      |
| <code>load</code>   | Applies records to the LS database obtained from running the <code>dump</code> directive.                                                                              |
| <code>quit</code>   | Stops program execution after flushing any changed database records to disk. The abbreviation <code>q</code> and the string <code>exit</code> produce the same effect. |
| <code>set</code>    | Specifies the fields to be displayed in subsequent <code>list</code> directives.                                                                                       |
| <code>update</code> | Modifies the specified CAT records.                                                                                                                                    |
| <code>verify</code> | Verifies the LS database against the daemon database.                                                                                                                  |

The first parameter of most directives specifies the records to manipulate, and the remaining parameters are keyword-value pairs.

The syntax for the `dmcatadm` directives is summarized as follows:

```
count selection [limit]  
create bfile settings . . .  
delete selection [limit]  
dump selection [limit]  
help  
list selection [limit] [format]  
load filename  
quit (or q or exit)  
set [format]  
update selection [limit] to settings . . .  
verify selection [entries] [vnames] [limit]
```

The parameters are as follows:

- The *selection* parameter specifies the records to be acted upon. The value for *selection* can be one of the following:
  - A *bfile* or range of *bfiles* in the form *bfile* [-] [*bfile*]. *bfile*- specifies all records starting with *bfile*, and *-bfile* specifies all records up to *bfile*.
  - The keyword `all`
  - A period (`.`), which recalls the previous selection
  - An expression involving any of the above, field value comparisons, `and`, `or`, or parentheses

A field value comparison may use the following to compare a field keyword to an appropriate value:

```
< (less than)  
> (greater than)  
= (equal to)  
!= (not equal to)  
<= (less than or equal to)  
>= (greater than or equal to)
```



The syntax for *selection* is as follows:

```

selection      ::= or-expr
or-expr       ::= and-expr [ or or-expr ]
and-expr      ::= nested-expr [ and or-expr ]
nested-expr   ::= comparison | ( or-expr )
comparison   ::= key-range | field-keyword op field-value
op           ::= < | > | = | != | <= | >=
bfid-range    ::= bfid [ - bfid ] | [ bfid - [ bfid ] ] | key-macro
key-macro     ::= all
field-keyword ::= name or abbreviation of the record field
field-value   ::= appropriate value for the field
key          ::= character representation of the record bfid

```

Thus valid *selections* could be any of the following:

```

305c74b200000010-305c74b200000029
7fffffff000f4411-
-305c74b20000004c8
all
chunkoffset>0
chunknumber>0 and writeage<5d
. and writeage>4d
vsns=S07638

```

- The *limit* parameter restricts the records acted upon.
- The *bfid* parameter for the `create` directive specifies the bit-file identifier (BFID) for the record being created. The value for *bfid* may be a BFID designator in the form of a hexadecimal number.
- The *settings* parameter for the `create` and `update` directives specify one or more fields and their values.
- The *format* parameter selects the way in which output is displayed. Any program or script that parses the output from this command should explicitly specify a format; otherwise the default is used, which may change from release to release.
- The *entries* parameter specifies a file of daemon database entries.
- The *vgnames* parameter specifies the names of the VGs associated with the records.

**dmccatadm Keywords**

You can use the *field* keywords listed below as part of the following:

- A *selection* parameter to select records
- A *format* parameter
- A *settings* parameter to specify new values for a field, in which case you must specify a keyword-value pair

A keyword-value pair consists of a keyword followed by white space and then a value. When specifying new values for fields, some of the keywords are valid only if you also specify the `-u` (unsafe) option. The abbreviation for each of the keywords is given in parenthesis following its name.

| <b>Keyword</b>                | <b>Description</b>                                                                                                                                                                                                                                                                                             |
|-------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>cflags (cf)</code>      | For future use.                                                                                                                                                                                                                                                                                                |
| <code>chunkdata (cd)</code>   | Specifies the actual number of bytes written to tape by the VG for the chunk. In the case of sparse files, this field will be smaller than <code>chunklength</code> . This is valid only in unsafe ( <code>-u</code> ) mode.                                                                                   |
| <code>chunklength (cl)</code> | The size of the chunk in bytes; an integer. This is valid only in unsafe ( <code>-u</code> ) mode.                                                                                                                                                                                                             |
| <code>chunknumber (cn)</code> | The ordinal of the chunk on its volume. For example, 1 if the chunk is the first chunk on the volume, 2 if it is the second, and so on. Not valid as part of a <i>settings</i> parameter in an <code>update</code> directive.                                                                                  |
| <code>chunkoffset (co)</code> | The byte offset within the file where the chunk begins; an integer. For example, the first chunk of a file has <code>chunkoffset 0</code> . If that first chunk is 1,000,000 bytes long, the second chunk would have <code>chunkoffset 1000000</code> . This is valid only in unsafe ( <code>-u</code> ) mode. |
| <code>chunkpos (cp)</code>    | The block offset within the zone where the chunk begins — a hexadecimal integer. For example, the first chunk in a zone has <code>chunkpos 1</code> . A value of 0 means unknown. Valid only in unsafe ( <code>-u</code> ) mode.                                                                               |
| <code>filesize (fs)</code>    | The original file size in bytes, an integer. This is valid only in unsafe ( <code>-u</code> ) mode.                                                                                                                                                                                                            |

|                  |                                                                                                                                                                                                                                                                                                                                                                                                             |
|------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| readage (ra)     | The date and time when the chunk was last read; the same as <code>readdate</code> , except specified as <i>age</i> .                                                                                                                                                                                                                                                                                        |
| readcount (rc)   | The number of times the chunk has been recalled to disk; an integer.                                                                                                                                                                                                                                                                                                                                        |
| readdate (rd)    | The date and time when the chunk was last read, an integer that reflects raw UNIX or Linux time.                                                                                                                                                                                                                                                                                                            |
| volgrp (vg)      | The VG name. This keyword is valid for LSs only. This keyword is not valid as part of a <i>settings</i> parameter. Changing this field in an existing record is valid only in unsafe (-u) mode.                                                                                                                                                                                                             |
| vsn (v)          | The volume serial numbers; a list of one or more 6-character alphanumeric volume serial numbers separated by colons (:). This keyword is not valid as part of a <i>settings</i> parameter in an <code>update</code> directive.                                                                                                                                                                              |
| writeage (wa)    | The date and time when the chunk was written; the same as <code>writedate</code> , except specified as <i>age</i> . This is valid only in unsafe (-u) mode.                                                                                                                                                                                                                                                 |
| writedate(wd)    | The date and time when the chunk was written, an integer that reflects raw UNIX or Linux time. This is valid only in unsafe (-u) mode.                                                                                                                                                                                                                                                                      |
| zoneblockid (zb) | Allows just the block ID portion of the <code>zonepos</code> to be displayed, returned, or changed. This is valid only in unsafe (-u) mode.                                                                                                                                                                                                                                                                 |
| zonenumber (zn)  | Allows just the zone number portion of the <code>zonepos</code> to be displayed, returned, or changed. This is valid only in unsafe (-u) mode.                                                                                                                                                                                                                                                              |
| zonepos (zp)     | The physical address of the zone on the volume, expressed in the form <i>integer/hexadecimal-integer</i> , designating a zone number and block ID. A value of zero is used for <i>hexadecimal-integer</i> if no block ID is known. <i>integer</i> is the same as <code>zonenumber</code> , and <i>hexadecimal-integer</i> is the same as <code>zoneblockid</code> . This is valid only in unsafe (-u) mode. |

The date field keywords (`readdate` and `writedate`) have one of the following values:

- `now`
- Raw UNIX or Linux time (seconds since January 1, 1970)

These keywords display their value as raw UNIX or Linux time. The value comparison `>` used with the date keywords means newer than the value given. For example, `>36000` is newer than 10AM on January 1, 1970, and `>852081200` is newer than 10AM on January 1, 1997.

The age field keywords (`readage` and `writeage`) let you express time as *age* in a string in a form. They display their value as an integer followed by the following:

w (weeks)  
d (days)  
h ( hours)  
m ( minutes)  
s (seconds)

For example, `8w12d7h16m20s` means 8 weeks, 12 days, 7 hours, 16 minutes, and 20 seconds old.

The comparison `>` used with the age keywords means older than the value given (that is, `>5d` is older than 5 days).

The *limit* parameter in a directive limits the records acted upon. It consists of one of the following keywords followed by white space and then a value:

| <b>Keyword</b>                | <b>Description</b>                                                                                                                                                                                                                                                                                                                                          |
|-------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>recordlimit (r1)</code> | Limits the number of records acted upon to the value that you specify; an integer.                                                                                                                                                                                                                                                                          |
| <code>recordorder (ro)</code> | Specifies the order that records are scanned: <ul style="list-style-type: none"><li>• <code>data</code> specifies that records are scanned in the order in which they are stored in the LS database, which is fastest but essentially unordered</li><li>• <code>key</code> specifies that records are scanned in ascending order of the chunk key</li></ul> |

- `vsn` specifies that records are scanned in ascending order of the chunk VSN

The following keywords specify files of daemon database entries:

| <b>Keyword</b>            | <b>Description</b>                                                                                                                                                                                                                                             |
|---------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>entries (e)</code>  | Specifies a file of daemon database entries. This keyword applies to the <code>verify</code> directive and consists of the word <code>entries</code> (or its abbreviation <code>e</code> ) followed by a string.                                               |
| <code>vgnames (vn)</code> | Specifies the names of the VGs associated with the record. This keyword applies to the <code>verify</code> directive and consists of the word <code>vgnames</code> (or its abbreviation <code>vn</code> ) followed by a quoted, space-separated list of names. |

The *format* parameter in a directive consists of the word `format` followed by white space and then one of the following:

- The word `default`
- The word `keyword` (suppresses the headings and is intended for parsing by a program or script)
- A list of field keywords, which may be delimited by colons or spaces (spaces require the use of quoting)

---

**Note:** The BFID is always included as the first field and need not be specified.

---

For any field that takes a byte count, you may append one of the following letters (in either uppercase or lowercase) to the integer to indicate that the value is to be multiplied (all of which are powers of 1000, not 1024):

`k` or `K` for 1 thousand  
`m` or `M` for 1 million  
`g` or `G` for 1 billion

For information about the role of the `dmcatadm(8)` command in database recovery, see "Recovery and Restoration of DMF Database" on page 646.

**Example 14-2** dmcatadm list Directive

The following is sample output from the dmcatadm list directive. The file with key 3273d5420001e244 has two chunks because it spans two physical tape volumes; the first chunk contains bytes 0–24821759, and the second chunk bytes 24821760 (the CHUNK OFFSET) to the end of the file.

```
adm 3>list 3273d5420001e242- recordlimit 10
```

| KEY              | WRITE AGE | CHUNK OFFSET | CHUNK LENGTH | CHUNK NUM | VSN    |
|------------------|-----------|--------------|--------------|-----------|--------|
| 3273d5420001e242 | 61d       | 0            | 77863935     | 13        | S12940 |
| 3273d5420001e244 | 61d       | 0            | 24821760     | 168       | S12936 |
| 3273d5420001e244 | 61d       | 24821760     | 23543808     | 1         | S12945 |
| 3273d5420001e245 | 61d       | 0            | 51019776     | 2         | S12945 |
| 3273d5420001e246 | 61d       | 0            | 45629440     | 59        | S12938 |
| 3273d5420001e247 | 61d       | 0            | 35586048     | 60        | S12938 |
| 3273d5420001e248 | 61d       | 0            | 9568256      | 3         | S12944 |
| 3273d5420001e249 | 61d       | 0            | 14221312     | 4         | S12944 |
| 3273d5420001e24a | 61d       | 0            | 458752       | 5         | S12944 |
| 3273d5420001e24b | 61d       | 0            | 14155776     | 6         | S12944 |

The following is sample output from the dmcatadm list directive for an LS. The file with key 3b4b28f2000000000000ae80 has 2 chunks because it was migrated to two different VGs within this LS. The output from the dmvoladm list directive that follows shows that VSN 000700 is assigned to the VG named vg8a15, and VSN 000727 is assigned to the VG named vg8a05.

```
# dmcatadm -m ls1
adm 1>list 3b4b28f2000000000000ae80- recordlimit 4
```

| KEY                      | WRITE<br>AGE | CHUNK<br>OFFSET | CHUNK<br>LENGTH | CHUNK<br>NUM | VSN    |
|--------------------------|--------------|-----------------|-----------------|--------------|--------|
| 3b4b28f2000000000000ae80 | 1d           | 0               | 2305938         | 120          | 000700 |
| 3b4b28f2000000000000ae80 | 4d           | 0               | 2305938         | 32           | 000727 |
| 3b4b28f2000000000000ae82 | 1d           | 0               | 234277          | 247          | 003171 |
| 3b4b28f2000000000000ae82 | 1d           | 0               | 234277          | 186          | 003176 |

```
adm 2> quit
```

```
# dmvoladm -m ls1
adm 1>list vsn=000700
```

| VSN    | VOLGRP | LB | DATA<br>LEFT | DATA<br>WRITTEN | EOT<br>CHUNK | EOT<br>ZONE | HFLAGS   | WR/FR<br>AGE |
|--------|--------|----|--------------|-----------------|--------------|-------------|----------|--------------|
| 000700 | vg8a15 | a1 | 150.280473   | 233.786093      | 123          | 9           | -----u-- | 1d           |

```
adm 2>list vsn=000727
```

| VSN    | VOLGRP | LB | DATA<br>LEFT | DATA<br>WRITTEN | EOT<br>CHUNK | EOT<br>ZONE | HFLAGS | WR/FR<br>AGE |
|--------|--------|----|--------------|-----------------|--------------|-------------|--------|--------------|
| 000727 | vg8a05 | a1 | 159.107337   | 200.443980      | 102          | 6           | -----  | 1d           |

### dmcatadm Text Field Order

The text field order for chunk records generated by the `dmdump(8)`, `dmdumpj(8)`, and the `dump` directive in `dmcatadm` is listed below. This is the format expected by the `load` directives in `dmcatadm`:

1. C (indicates the chunk record type)
2. bfid (hexadecimal digits)
3. filesize
4. writedata
5. readdate
6. readcount

7. `chunkoffset`
8. `chunklength`
9. `chunkdata`
10. `chunknumber`
11. `flags` (in octal)
12. `zoneposition` (`zonenumber/zoneblockid`) (in hexadecimal)
13. `vsn`
14. `chunkpos` (in hexadecimal)

## **dmvoladm Command**

This section discusses the following:

- "dmvoladm Overview" on page 554
- "dmvoladm Directives" on page 555
- "dmvoladm Field Keywords" on page 557
- "dmvoladm Text Field Order" on page 563
- "dmvoladm Examples" on page 564

## **dmvoladm Overview**

The `dmvoladm(8)` command provides maintenance services for VOL records. In addition to the creation and modification of volume records, `dmvoladm` has an important role in the recovery of VOL records from an LS database checkpoint and is the mechanism that triggers volume merge activity.

When you are inside the `dmvoladm` interface, you see the following prompt:

```
adm command_number >
```

At this point, the command has a 30-minute timeout associated with it. If you do not enter a response within 30 minutes of the prompt having been displayed, the `dmvoladm` session terminates with a descriptive message. This behavior on all the



database administrative commands limits the amount of time that an administrator can lock the daemon database and the LS database from updates.

### dmvoladm Directives

The `dmvoladm` command executes directives from `stdin` or from the command line when you use the `-c` option. The syntax is the same as for `dmcatadm`: a directive name followed by parameters or paired keywords and values, all separated by white space.

| Directive           | Description                                                                                                                                                                                  |
|---------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>count</code>  | Displays the number of records that match the expression provided.                                                                                                                           |
| <code>create</code> | Creates a VOL record.                                                                                                                                                                        |
| <code>delete</code> | Deletes the specified VOL records.                                                                                                                                                           |
| <code>dump</code>   | Prints the specified VOL records to standard output in ASCII. Each field is separated by the pipe character ( <code> </code> ).                                                              |
| <code>help</code>   | Displays help.                                                                                                                                                                               |
| <code>list</code>   | Shows the fields of selected VOL records. You may specify which fields are shown.                                                                                                            |
| <code>load</code>   | Applies VOL records to the LS database obtained from running the <code>dump</code> directive.                                                                                                |
| <code>quit</code>   | Stops program execution after flushing any changed records to disk. The abbreviation <code>q</code> and the string <code>exit</code> produce the same effect.                                |
| <code>repair</code> | Causes <code>dmvoladm</code> to adjust the usage information for specified volumes based on CAT records in the LS database. This directive is valid only in unsafe ( <code>-u</code> ) mode. |
| <code>select</code> | Marks selected volumes as being sparse. Equivalent to <code>update expression</code> to <code>hsparse on</code> .                                                                            |
| <code>set</code>    | Specifies the fields to be shown in subsequent <code>list</code> directives.                                                                                                                 |
| <code>update</code> | Modifies the specified VOL records.                                                                                                                                                          |
| <code>verify</code> | Verifies the LS database against the daemon database.                                                                                                                                        |

The syntax for the `dmvoladm` directives is summarized as follows:

```
count [limit]
create vsnlist volgrpspec [settings]
```

```
delete selection [limit]  
dump selection [limit]  
help  
list selection [limit] [format]  
load filename  
quit (or q, or exit)  
repair selection  
select selection [limit]  
set format  
update selection [limit] to settings  
verify selection
```

The *volgrpspec* parameter consists of the keyword *volgrp* (or *vg*), followed by a value for that keyword.

The value for *vsolist* may be a single 6-character volume serial number (VSN) or a range of VSNs separated by the hyphen (-) character. A VSN string is case insensitive and may consist entirely of letters, entirely of digits, or a series of letters followed by digits. In a range of VSNs, the first must be lexically less than the second.

The value for *selection* may be one of the following:

- A *vsolist* or range of VSNs in the form *vsol[-vsol]*. *vsol-* specifies all records starting with *vsol*, and *-vsol* specifies all records up to *vsol*.
- A period (.), which recalls the previous selection.
- The name of one of the flags in the keyword list that follows in this section.
- One of the words *all*, *used*, *empty*, or *partial* or any of the *hold flags* (*hflags*), whose meanings are as follows:

| <b>Flag</b>    | <b>Description</b>                                   |
|----------------|------------------------------------------------------|
| <i>all</i>     | Specifies all volumes in the LS database             |
| <i>empty</i>   | Specifies all volumes in which data left is 0        |
| <i>partial</i> | Specifies used volumes in which <i>hfull</i> is off  |
| <i>used</i>    | Specifies all volumes in which data written is not 0 |

- An expression involving *vsolists*, field-value comparisons, *and*, *or*, or parentheses.

A field value comparison may use the following to compare a field keyword to an appropriate value:

< (less than)  
 > (greater than)  
 = (equal)  
 != (not equal)  
 <= (less than or equal to)  
 >= (greater than or equal to)

The syntax for *selection* is as follows:

```

selection      ::= or-expr
or-expr       ::= and-expr [ or or-expr ]
and-expr      ::= nested-expr [ and or-expr ]
nested-expr   ::= comparison | ( or-expr )
comparison   ::= vsnlist | field-keyword op field-value
op           ::= < | > | = | != | >= | <=
vsn-range    ::= vsn [ - vsn ] | [vsn - [vsn]] | key-macro
key-macro    ::= all | empty | used | partial | flag(s)
field-keyword ::= name or abbreviation of the record field
field-value  ::= appropriate value for the field
vsnlist     ::= character representation of the volume serial number
  
```

Thus valid *selections* could be any of the following:

```

tape01-tape02
tape50-
-vsn900
all
hoa or hro
used and hfull=off
datawritten>0 and hfull=off
. and eotchunk>3000 and (eotchunk<3500 or hfree=on)
hfull and threshold<30
  
```

### dmvoladm Field Keywords

You can use the *field* keywords listed below as part of the following:

- A *selection* parameter to select records
- A *format* parameter
- A *settings* parameter to specify new values for a field, in which case you must specify a keyword-value pair

A keyword-value pair consists of a keyword followed by white space and then a value. When specifying new values for fields, some of the keywords are valid only if you also specify the `-u` (unsafe) option:

| <b>Keyword</b>                | <b>Description</b>                                                                                                                                                                                                                                                                                                                                                                                                                            |
|-------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>blocksize (bs)</code>   | Specifies the data block size in bytes when the tape was first written; an integer. This keyword is used only when mounting volumes with existing valid data. When an empty volume is first written, the VG uses the default value for the volume type, unless it is overridden by a value in the <code>BLOCK_SIZE</code> parameter for the drive group in the DMF configuration file. This is valid only in unsafe ( <code>-u</code> ) mode. |
| <code>chunksleft (cl)</code>  | Specifies the number of active chunks on the volume; an integer. This is valid only in unsafe ( <code>-u</code> ) mode.                                                                                                                                                                                                                                                                                                                       |
| <code>dataleft (dl)</code>    | Specifies the number of bytes of active data on the volume. You specify this number as an integer, but for readability purposes it is displayed in megabytes (MB). This is valid only in unsafe ( <code>-u</code> ) mode.                                                                                                                                                                                                                     |
| <code>datawritten (dw)</code> | Specifies the maximum number of bytes ever written to the volume. You specify this number as an integer, but for readability purposes it is displayed in MB. This is valid only in unsafe ( <code>-u</code> ) mode.                                                                                                                                                                                                                           |
| <code>eotblockid (eb)</code>  | Specifies the block ID of the chunk containing the end-of-volume marker (historically known as <i>EOT</i> for <i>end-of-tape</i> ); a hexadecimal integer. This is valid only in unsafe ( <code>-u</code> ) mode.                                                                                                                                                                                                                             |
| <code>eotchunk (ec)</code>    | Specifies the number of the chunk containing the end-of-volume marker; an integer. This is valid only in unsafe ( <code>-u</code> ) mode.                                                                                                                                                                                                                                                                                                     |
| <code>eotpos (ep)</code>      | Specifies the absolute position of the end-of-volume marker zone in the form <i>integer/hexadecimal-integer</i> , designating a zone number and block ID. A value of zero is used for <i>hexadecimal-integer</i> if no block ID is known. <i>integer</i> the same as <code>eotzone</code> , and <i>hexadecimal-integer</i> is the same as <code>eotblockid</code> . This is valid only in unsafe ( <code>-u</code> ) mode.                    |

---

|                |                                                                                                                                                                                                                        |
|----------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| eotzone (ez)   | Specifies the number of the zone containing the end-of-volume marker; an integer. This is valid only in unsafe (-u) mode.                                                                                              |
| hflags (hf)    | Specifies the flags associated with the record. See the description of <i>flags</i> keywords. Not valid as part of a <i>settings</i> parameter.                                                                        |
| label (lb)     | Specifies the label type: <ul style="list-style-type: none"><li>• a1 (ANSI label)</li><li>• n1 (no label, not allowed for COPAN MAID or JBFS)</li><li>• s1 (standard label for IBM tapes)</li></ul> The default is a1. |
| tapesize (ts)  | Specifies the estimated capacity in bytes; an integer. The default is 0. This field must be accurately set in order to estimate remaining capacity.                                                                    |
| threshold (th) | Specifies the ratio of dataleft to datawritten as a percentage. This field is valid only as part of a <i>selection</i> parameter.                                                                                      |
| upage (ua)     | Specifies the date and time of the last update to the volume's database record. The same as for update, except that it is expressed as <i>age</i> . This is not valid as part of a <i>settings</i> parameter.          |
| update (ud)    | Specifies the date and time of the last update to the volume's database record, expressed as an integer that reflects raw UNIX or Linux time. This is not valid as part of a <i>settings</i> parameter.                |
| version (v)    | Specifies the DMF media format version, an integer. This is valid only in unsafe (-u) mode.                                                                                                                            |
| volgrp (vg)    | Specifies the VG or allocation group. Changing this field in an existing record is valid only in unsafe (-u) mode.                                                                                                     |
| wfage (wa)     | Specifies the date and time that the volume was written to or freed for reuse. The same as for wfdate, except that it is expressed as <i>age</i> . This is valid only in unsafe (-u) mode.                             |

`wfdate (wd)` Specifies the date and time that the volume was written to or freed for reuse, expressed as an integer that reflects raw UNIX or Linux time. This is valid only in unsafe (-u) mode.

The date field keywords (`update` and `wfdate`) have a value of one of the following:

- `now`
- UNIX or Linux raw time (seconds since January 1, 1970)

These keywords display their value as raw time. The value comparison `>` used with the date keywords means newer than the value given. For example, `>36000` is newer than 10AM on January 1, 1970, and `>852081200` is newer than 10AM on January 1, 1997.

The age field keywords (`upage` and `wfage`) let you express time as *age* as a string.

The age keywords display their value as an integer followed by the following:

`w` (weeks)  
`d` (days)  
`h` ( hours)  
`m` ( minutes)  
`s` (seconds)

For example, `8w12d7h16m20s` means 8 weeks, 12 days, 7 hours, 16 minutes, and 20 seconds old.

The comparison `>` used with the age keywords means older than the value given (that is, `>5d` is older than 5 days).

The *limit* parameter in a directive limits the records acted upon. It consists of one of the following keywords followed by white space and then a value. The abbreviation for the keyword is given in parentheses following its name, if one exists:

| <b>Keyword</b>                           | <b>Description</b>                                                                                                                        |
|------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------|
| <code>datalimit (no abbreviation)</code> | Specifies a value in bytes. The directive stops when the sum of <code>dataleft</code> of the volumes processed so far exceeds this value. |
| <code>recordlimit (r1)</code>            | Specifies a number of records; an integer. The directive stops when the number of volumes processed equals this value.                    |

`recordorder (ro)` Specifies the order that records are scanned; may be either `data` or `vsu`. `vsu` specifies that the records are scanned in ascending order of the chunk VSN. `data` specifies that the records are scanned in the order in which they are found in the LS database, which is fastest but essentially unordered.

The *format* parameter in a directive consists of the word `format` followed by white space and then one of the following:

- The word `default`
- The word `keyword` (which suppresses the headings and is intended for parsing by a program or script)
- A list of field and or flag keywords that may be delimited by colons or spaces (spaces require the use of quoting)

The VSN is always included as the first field and need not be specified.

The *flag* keywords listed below can be used to change the settings of the *hold flags* (*hflags*). They can also be used as part of selection or format parameters:

| <b>Keyword</b>                        | <b>Description</b>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
|---------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>herr (he)</code>                | Indicates an LS database inconsistency for this volume. It is displayed as <code>e-----</code> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
| <code>hextern (hx)</code>             | <i>(OpenVault only)</i> Indicates that the volume was not in the library. It is displayed as <code>-----x</code> . If the <code>hextern</code> flag is set, the volume cannot be merged. DMF periodically obtains from OpenVault the list of volumes that are currently in the library. If a volume is not in the library, DMF will set its <code>hextern</code> flag; if the volume is added to the library, DMF will eventually clear its <code>hextern</code> flag, but up to 75 minutes can pass before DMF notices this change. This flag does not apply to COPAN MAID configurations. |
| <code>hflags (no abbreviation)</code> | <i>(Not valid as part of a <i>settings</i> parameter.)</i> Shows the complete set of hold flags as a 9-character string. Each flag has a specific position and alphabetic value. If the flag is off, a hyphen(-) is displayed in its position; if the flag is on, the alphabetic character is displayed in that position.                                                                                                                                                                                                                                                                   |

|                         |                                                                                                                                                                                                                                                                                                                                    |
|-------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| hfree (no abbreviation) | Indicates that the volume has no active data and is available for reuse after <code>HFREE_TIME</code> has expired, displayed as <code>-f-----</code> . See the <code>dmf.conf(5)</code> man page for information about the <code>HFREE_TIME</code> configuration parameter. This is valid only in unsafe ( <code>-u</code> ) mode. |
| hfull (hu)              | Indicates that the volume cannot hold any more data; displayed as <code>-----u--</code> .                                                                                                                                                                                                                                          |
| hlock (hl)              | Indicates that the volume cannot be used for either input or output. This is a transient condition; the flag will be cleared by the LS after <code>REINSTATE_VOLUME_DELAY</code> has expired and at LS startup. Displayed as <code>----l----</code> .                                                                              |
| hoa (ho)                | Indicates that the volume is not to be used for either input or output, displayed as <code>--o-----</code> . This value is only set or cleared by the site administrator.                                                                                                                                                          |
| hro (hr)                | Indicates that the volume is read-only, displayed as <code>---r-----</code> ; this inhibits the LS from using the volume for output. This value is only set or cleared by the site administrator.                                                                                                                                  |
| hsite1 (hl)             | Reserved for site use; ignored by DMF. Not normally displayed; see the <code>dmvoladm(8)</code> man page for details. <code>hsite2</code> , <code>hsite3</code> , and <code>hsite4</code> are also available.                                                                                                                      |
| hsparse (hs)            | Indicates that the volume is considered sparse and thus a candidate for a volume merge operation, displayed as <code>-----s-</code> .                                                                                                                                                                                              |
| hvfy (hv)               | Indicates that this tape should be tested and/or replaced when next empty; until that time, it is read-only. Displayed as <code>----v----</code> . This value is set by DMF but only cleared by the site administrator.                                                                                                            |

For any field that takes a byte count, you may append one of the following letters (in either uppercase or lowercase) to the integer to indicate that the value is to be multiplied (all of which are powers of 1000, not 1024):

k or K for 1 thousand  
m or M for 1 million  
g or G for 1 billion



For information about the role of the `dmvoladm` command in LS database recovery, see "Recovery and Restoration of DMF Database" on page 646. For details about `dmvoladm` syntax, see the man page.

#### `dmvoladm` Text Field Order

The text field order for volume records generated by the `dmdump(8)`, `dmdumpj(8)`, and the `dump` directive in `dmvoladm` is listed below. This is the format expected by the `load` directives in `dmvoladm`:

1. `v` (indicates the volume record type)
2. `vsn`
3. `volgrp`
4. `lbtype`
5. `capacity`
6. `blocksize`
7. `hflags` (in octal)
8. `version`
9. `datawritten`
10. `eotchunk`
11. `eotposition` (`eotzone/eotblockid`) (in hexadecimal)
12. `dataleft`
13. `chunksleft`
14. `wfdate`
15. `update`
16. `id` (in octal). This field indicates the type of process that last updated the record.

**dmvoladm Examples**

**Example 14-3** dmvoladm update Directive

The following unsets the hlock for C02M02, indicating that the volume can now be used for either input or output:

```
adm 8>update C02M02 to hlock off
```

**Example 14-4** dmvoladm list Directive to Show Information for Multiple VSNs

The following example illustrates the default format for the list directive when using an LS. The column marked HFLAGS uses a format similar to the ls -l command in that each letter has an assigned position and its presence indicates that the flag is on. The positions spell out the string eforvlusx, representing herr, hfree, hoa, hro, hvfy, hlock, hfull, hsparse, and hextern.

```
adm 1> list 000683-000703
```

| VSN    | VOLGRP | LB | DATA LEFT  | DATA WRITTEN | EOT CHUNK | EOT ZONE | HFLAGS   | WR/FR AGE |
|--------|--------|----|------------|--------------|-----------|----------|----------|-----------|
| 000683 | vg8a01 | a1 | 0.000000   | 0.000000     | 1         | 1        | -----    | 3d        |
| 000700 | vg8a00 | a1 | 267.539255 | 287.610294   | 124       | 7        | -----u-- | 2d        |
| 000701 | vg8a00 | a1 | 288.342795 | 308.147798   | 136       | 8        | -----u-- | 2d        |
| 000702 | vg8a00 | a1 | 255.718902 | 288.302830   | 120       | 7        | -----u-- | 2d        |
| 000703 | ag8    | a1 | 0.000000   | 0.000000     | 1         | 1        | -----    | 3d        |

**Example 14-5** dmvoladm list Directive to Show Volumes with a Specific Flag

The following example illustrates using the list command to show only volumes having their hfull flag set:

```
adm 1>list hfull
```

| VSN    | VOLGRP | LB | DATA LEFT  | DATA WRITTEN | EOT CHUNK | EOT ZONE | HFLAGS   | WR/FR AGE |
|--------|--------|----|------------|--------------|-----------|----------|----------|-----------|
| 000701 | vg8a00 | a1 | 288.342795 | 308.147798   | 136       | 8        | -----u-- | 2d        |
| 000702 | vg8a00 | a1 | 255.718902 | 288.302830   | 120       | 7        | -----u-- | 2d        |
| 000704 | vg8a00 | a1 | 252.294122 | 292.271410   | 119       | 7        | -----u-- | 2d        |
| 000705 | vg8a00 | a1 | 250.207666 | 304.603059   | 143       | 7        | -----u-- | 2d        |
| 000706 | vg8a00 | a1 | 265.213875 | 289.200534   | 144       | 7        | -----u-- | 2d        |
| 000707 | vg8a00 | a1 | 278.744448 | 310.408119   | 140       | 7        | -----u-- | 2d        |
| 000708 | vg8a00 | a1 | 260.827748 | 295.956588   | 136       | 7        | -----u-- | 2d        |

```

000709  vg8a00  al    253.481897    283.615678    138    8  -----u--    2d
000710  vg8a00  al    265.100985    291.243235    141    7  -----u--    2d
000711  vg8a00  al    276.288446    305.782035    144    7  -----u--    2d
000712  vg8a00  al    250.415786    275.606243    138    7  -----u--    2d
000716  vg8a00  al    287.964765    304.321543    144    7  -----u--    2d
000717  vg8a00  al    280.795058    287.084534    144    7  -----u--    2d
000718  vg8a00  al     0.000415    300.852018    180    27 -----u--    3d
003127  vg9a01  al    417.383784    461.535047    209    10 -----u--    2d
003128  vg9a01  al    427.773679    460.716741    229    11 -----u--    2d

```

**Example 14-6** dmvoladm list Directive to Customize a List of Fields

The following example shows one way you can customize the list format to show only the fields that you want to see.

```

adm 21>list S03232-S03254 format "eotchunk eotzone eotpos"
          EOT   EOT
VSN      CHUNK  ZONE   EOTPOS
-----
S03232   10     2  2/4294967295
S03233   2      2  2/4294967295
S03234  598     2  2/4294967295
S03235   18     2  2/4294967295
S03236   38     2  2/4294967295
S03237   92     2  2/4294967295
S03238   1      1  1/4294967295
S03239   1      1  1/4294967295
S03240   1      1  1/4294967295
S03241  325     2  2/4294967295
S03242   81     2  2/4294967295
S03243   26     2  2/4294967295
S03244   1      1  1/4294967295
S03245   26     2  2/4294967295
S03246   5      2  2/4294967295
S03247  186     2  2/4294967295
S03248   17     2  2/4294967295
S03249  526     2  2/4294967295
S03250   1      1  1/4294967295
S03251  533     2  2/4294967295
S03252  157    17 17/2147483648
S03253  636     2  2/4294967295

```

S03254 38 2 2/4294967295

Another way to accomplish this is to use the `set format` command with the same keyword list.

**Example 14-7** `dmvoladm list` Directive to Show Multiple Flags

The following example gives a convenient way to show the setting of multiple flags:

```
adm 23>list 003232-003254 format "hfree hfull hlock hoa hro"
```

```
hfree hfull hlock hoa hro
```

```
VSN
```

```
-----
003232 off on off off off
003233 off off off off off
003234 off off off off off
003235 off off off off off
003236 off on off off off
003237 off on off off off
003238 off on off off off
003239 off on off off off
003240 off off off off off
003241 off on off off off
003242 off on off off off
003243 off off off off off
003244 off off off off off
003245 off on off off off
003246 off off off off off
003247 off on off off off
003248 off on off off on
003249 on off off off on
003250 on off off off on
003251 on off off off on
003252 on off off off on
003253 off on off off on
003254 off on off off on
```

**Example 14-8** `dmvoladm list` Directive to Display Volumes Assigned to a VG

The following example shows how to display only those volumes assigned to the VG named `vg9a00`.

```
adm 3>list vg=vg9a00
```

| VSN    | VOLGRP | LB | DATA LEFT | DATA WRITTEN | EOT CHUNK | EOT ZONE | HFLAGS | WR/FR AGE |
|--------|--------|----|-----------|--------------|-----------|----------|--------|-----------|
| 003210 | vg9a00 | a1 | 1.048576  | 1.048576     | 3         | 2        | -----  | 11d       |
| 003282 | vg9a00 | a1 | 11.534336 | 11.534336    | 13        | 2        | -----  | 7d        |

**dmatread Command**

You can use `dmatread(8)` to copy all or part of the data from a migrated file back to disk. You might want to do this if, for example, a user accidentally deleted a file and did not discover that the deletion had occurred until after the database entries had been removed by the hard delete procedure. Using backup copies of the databases from before the hard delete was performed, `dmatread` can restore the data to disk, assuming that the tape volume has not been reused in the meantime.

**Example 14-9** Restoring Hard-deleted Files Using `dmatread`

To copy migrated files back to disk, perform the following steps:

1. Determine the BFID of the file you want to restore. You can use backup copies of `dmdlog` or your `dbrec.dat` files, or a restored backup copy of the deleted file's inode (and the `dmattr` command).
2. Using backup copies of the LS database, execute a `dmatread(8)` command similar to the following:

```
dmatread -p /a/dmbackup -B 342984C5000000000000084155
```

`342984C5000000000000084155` is the BFID of the file to be restored, and `/a/dmbackup` is the directory containing the backup copies of the LS database. Your file will be restored to the current directory as `B342984C5000000000000084155`.

**Note:** DMF does not know the original name of the file; you must manually move the restored data to the appropriate file.

If you have access to chunk and VSN information for the file to be restored, you can use the `dmatread -c` and `-v` options and avoid using backup copies of the LS database. In this case, `dmatread` will issue messages indicating that the chunk is not found in the current LS database, but it will continue with the request and restore the file as described in this example.

### **`dmatsnf` Command**

You can use `dmatsnf(8)` to verify the readability of the LS volumes or to audit their contents. The `dmatsnf` script is a wrapper around the `dmatsnfb` binary. Both the script and the binary are installed on the DMF server, but only the binary is installed on parallel data-mover nodes. In most cases, you will execute `dmatsnf`. When using `dmatsnf`, in most cases you will only need to specify the VSNs, the volume's volume group, and the type of reports desired. For more information about how the binary and script work together, see the `dmatsnf(8)` man page.

---

**Note:** The `dmatsnf(8)` and `dmatread(8)` commands verify the integrity of the library server (LS) volumes on MAID shelves and recover data from them. For those volumes that are mountable only on a parallel data-mover node, use of these commands is simplified if there is passwordless `ssh(8)` connection from the DMF server to the parallel data-mover node. For more information about these commands, see their man pages.

---

You can also use `dmatsnf` to verify one or more volumes against the LS database or to generate journal entries, which you can add to the LS database by using the `load` directive in `dmvoladm` and `dmcatadm`.

You may also generate text database records that you can apply to the LS database using the `load` directive in `dmcatadm` and `dmvoladm`. You can use the text records to add the contents of a few volumes to the LS database (however, this is impractical for large numbers of volumes).

### **`dmaudit verifymsp` Command**

You can use the `verifymsp` option of the `dmaudit(8)` command to check the consistency of the daemon database and LS database after an MSP, LS, DMF daemon, or system failure. This command captures the database files and compares the contents of the daemon database with each LS database. Any problems are reported to standard output, but no attempt is made to repair them.

You can also perform a similar function directly using `dmactvfy(8)` after taking a snapshot.

## Cloud MSP

This section discusses the following:

- "Cloud MSP Overview" on page 569
- "Cloud MSP Processing of Requests" on page 569
- "Cloud MSP Activity Log" on page 571
- "Cloud MSP Messages" on page 571
- "Cloud MSP Limitations and Considerations" on page 572

### Cloud MSP Overview

The cloud MSP allows the DMF daemon to manage data by moving it to a cloud storage service:

- Scality RING private cloud
- Amazon Simple Storage Service (S3) public cloud
- Other products that present a service interface that is compatible with S3, in a private cloud

The cloud MSP does not need a private database to operate; all information necessary to retrieve offline files is kept in the daemon database, DMF configuration file, and login information file. The login information file contains a password that must be kept private. As a safeguard, the MSP will not operate if the login information file is readable by anyone other than the system administrator.

### Cloud MSP Processing of Requests

The cloud MSP is always waiting for requests to arrive from the DMF daemon. To improve efficiency, it holds `PUT` and `DELETE` requests briefly and groups similar requests together into a single cloud session:

- No `PUT` request will be held longer than 60 seconds

- No DELETE request will be held longer than 5 seconds
- 

**Note:** GET requests are not held.

---

The cloud MSP will stop holding requests if it has a large amount of work to do (more than 1024 individual files or 8 MB of data). The cloud MSP also limits the number of cloud services that can be active at once and the rate at which new sessions can be initiated.

After a request has been held for the appropriate amount of time, it enters a ready state. Processing usually begins immediately, but may be delayed if resources are not available.

The following limits affect the maximum number of requests that can be processed:

- An administrator-controlled limit on the maximum number of concurrent cloud-service sessions per MSP (`CHILD_MAXIMUM`).
- An administrator-controlled limit on the number of child processes that are guaranteed to be available for processing delete requests (`GUARANTEED_DELETES`).
- An administrator-controlled limit on the number of child processes that are guaranteed to be available for processing `dmget(1)` requests (`GUARANTEED_GETS`).
- A system-imposed limit to the number of cloud-service sessions in any 60-second period. This limit is seldom a concern because of the MSP's ability to transfer many files in one session.

The following steps occur:

1. Requests are processed by forking off a child process.
2. The parent process immediately resumes waiting for requests to arrive from the DMF daemon.
3. The child process attempts to initiate a cloud-service session on the backend. If multiple IP addresses are specified with the `CLOUD_HOST` configuration parameter, one will be chosen at random until a connection is established (see "msp Object Parameters for a Cloud MSP" on page 449).
4. After a connection is established, the child process provides any required user name and password information to the cloud server.



5. Requests are distributed to the running child processes on a first-come, first-served basis. Requests are not batched; children handle at most one request at a time. Requests handed to any particular child process might be freely intermixed; a given child may handle any combination of PUT, GET, or DELETE operations (even if `GUARANTEED_GETS` or `GUARANTEED_DELETES` is set in the DMF configuration file).

The stored files are not verbatim copies of the user files. They are stored using the same format used when writing volumes.

## Cloud MSP Activity Log

All DMF MSPs maintain log files named `m脾log.yyyymmdd` in the MSP spool directory which, by default, is `SPOOL_DIR/m脾name`. `SPOOL_DIR` is configured in the `base` object of the configuration file; `m脾name` is the name of the MSP in the `daemon` object of the configuration file; `yyymmdd` is the current year, month, and day.

The activity log shows the arrival of new requests, the successful completion of requests, failed requests, creation and deletion of child processes, and all cloud transactions. Sensitive information (passwords and account information) does not appear in the activity log. In addition, the MSP lists the contents of its internal queues in its activity log if it is given an `INTERRUPT` signal.

---

**Note:** Because the cloud MSP will continue to create log files without limit, you must remove obsolete files periodically by configuring the `run_remove_logs` task in the configuration file, as described in "taskgroup Object" on page 304.

---

## Cloud MSP Messages

The MSP also recognizes and handles the following messages issued from the DMF daemon:

| Message | Description                                                                                                                                                                                                                                                                                                                   |
|---------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| CANCEL  | Issued when a previously requested action is no longer necessary, for example, when a file being migrated with a PUT request is removed. The MSP is able to cancel a request if it is being held or if it is waiting for resources. A request that has begun processing cannot be canceled and will run to normal completion. |

|          |                                                                                                                                                                  |
|----------|------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| FINISH   | Issued during normal shutdown. When the MSP receives a FINISH message, it finishes all requested operations as quickly as it can and then exits.                 |
| FLUSHALL | Issued in response to the <code>dmddidle(8)</code> command. When the MSP receives a FLUSHALL message, it finishes all requested operations as quickly as it can. |

## Cloud MSP Limitations and Considerations

Note the following:

- Security issues:
  - SSL and HTTPS are not supported.
  - Migrated data is not encrypted.
  - Scality supports only a clear-text password.
  - HTTP Basic Authentication is not enabled by default on Scality systems.
- Support issues:
  - The cloud MSP, Scality, and S3 support only IPv4.
  - The cloud MSP does not support Amazon Glacier.
- A given cloud can be a single point of failure, therefore redundant copies within one cloud do not sufficiently protect against data loss. SGI therefore highly recommends that you migrate data to a second location (to another cloud instance, tape, or disk).
- The cloud MSP breaks up files into 1-MiB chunks. To potentially minimize access times, you may want to use substitution strings to randomize the order of keys (rather than using sequentially named keys); see "NAME\_FORMAT Details" on page 446.
- The `dmatread(8)` and `dmatsnf(8)` utilities do not work on cloud storage.
- The `dmcheck(8)` command and the validation operation in DMF Manager verify that at least one cloud host is available.
- If the cloud must be restored to a previous state, inconsistencies may arise: remote files that reappear after being deleted are never removed, and remote files that

disappear unexpectedly result in data loss. There is presently no way to detect these inconsistencies. You should avoid situations that require the cloud to be restored to a previous state.

## FTP MSP

This section discusses the following:

- "FTP MSP Overview" on page 573
- "FTP MSP Processing of Requests" on page 573
- "FTP MSP Activity Log" on page 575
- "FTP MSP Messages" on page 576
- "FTP MSP Limitations and Considerations" on page 576

### FTP MSP Overview

The FTP MSP allows the DMF daemon to manage data by moving it to a remote machine. Data is moved to and from the remote machine with the protocol described in RFC 959 (FTP). The remote machine must understand this specific protocol.

The FTP MSP does not need a private database to operate; all information necessary to retrieve offline files is kept in the daemon database, DMF configuration file, and login information file. The login information file contains a password that must be kept private. As a safeguard, the MSP will not operate if the login information file is readable by anyone other than the system administrator.

### FTP MSP Processing of Requests

The FTP MSP is always waiting for requests to arrive from the DMF daemon. To improve efficiency, it holds `PUT` and `DELETE` requests briefly and groups similar requests together into a single FTP session:

- No `PUT` request will be held longer than 60 seconds
- No `DELETE` request will be held longer than 5 seconds

---

**Note:** GET requests are not held.

---

The FTP MSP will stop holding requests if it has a large amount of work to do (more than 1024 individual files or 8 MB of data). The FTP MSP also limits the number of FTP sessions that can be active at once and the rate at which new sessions can be initiated.

After a request has been held for the appropriate amount of time, it enters a ready state. Processing usually begins immediately, but may be delayed if resources are not available.

The following limits affect the maximum number of requests that can be processed:

- An administrator-controlled limit on the maximum number of concurrent FTP sessions per MSP (CHILD\_MAXIMUM).
- An administrator-controlled limit on the number of child processes that are guaranteed to be available for processing delete requests (GUARANTEED\_DELETES).
- An administrator-controlled limit on the number of child processes that are guaranteed to be available for processing `dmget(1)` requests (GUARANTEED\_GETS).
- A system-imposed limit of 85 FTP sessions in any 60-second period. This limit is seldom a concern because of the MSP's ability to transfer many files in one session.

The following steps occur:

1. Requests are processed by forking off a child process.
2. The parent process immediately resumes waiting for requests to arrive from the DMF daemon.
3. The child process attempts to initiate an FTP session on the remote FTP server.
4. If the remote machine has multiple IP addresses in the name system, only the first is tried.
5. After a connection is established, the child process provides any required user name, password, account, and default directory information to the remote FTP server.
6. PUT, GET, or DELETE operations are then performed as requested by the DMF daemon.

Binary transfer mode is used for all data transfer. Passive mode (the `PASV` or `EPSV` commands) will be tried, but the child process will fall back to the active mode (the `PORT` or `EPRT` commands). Block mode (the `MODE B` command) will be tried in order to allow the data connection to be used for multiple transfers, but the child process will fall back to a single data connection per transfer if the server does not support `MODE B`, which is the most likely case.

7. Requests are distributed to the running child processes on a first-come, first-served basis. Requests are not batched; children handle at most one request at a time. Requests handed to any particular child process might be freely intermixed; a given child may handle any combination of `PUT`, `GET`, or `DELETE` operations (even if `GUARANTEED_GETS` or `GUARANTEED_DELETES` is set in the DMF configuration file).

The stored files are not verbatim copies of the user files. They are stored using the same format used to write volumes, and you can use MSP utilities such as `dmatread` and `dmatsnf` to access the data in them.

## FTP MSP Activity Log

All DMF MSPs maintain log files named `m脾log.yyyymmdd` in the MSP spool directory which, by default, is `SPOOL_DIR/m脾name`. `SPOOL_DIR` is configured in the `base` object of the configuration file; `m脾name` is the name of the MSP in the `daemon` object of the configuration file; `yyymmdd` is the current year, month, and day.

The activity log shows the arrival of new requests, the successful completion of requests, failed requests, creation and deletion of child processes, and all FTP transactions. Sensitive information (passwords and account information) does not appear in the activity log. In addition, the MSP lists the contents of its internal queues in its activity log if it is given a `SIGINT` signal.

---

**Note:** Because the FTP MSP will continue to create log files without limit, you must remove obsolete files periodically by configuring the `run_remove_logs` task in the configuration file, as described in "taskgroup Object" on page 304.

---

## FTP MSP Messages

The MSP also recognizes and handles the following messages issued from the DMF daemon:

| Message  | Description                                                                                                                                                                                                                                                                                                                                |
|----------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| CANCEL   | Issued when a previously requested action is no longer necessary, for example, when a file being migrated with a <code>PUT</code> request is removed. The MSP is able to cancel a request if it is being held or if it is waiting for resources. A request that has begun processing cannot be canceled and will run to normal completion. |
| FINISH   | Issued during normal shutdown. When the MSP receives a <code>FINISH</code> message, it finishes all requested operations as quickly as it can and then exits.                                                                                                                                                                              |
| FLUSHALL | Issued in response to the <code>dmdidle(8)</code> command. When the MSP receives a <code>FLUSHALL</code> message, it finishes all requested operations as quickly as it can.                                                                                                                                                               |

## FTP MSP Limitations and Considerations

Note the following:

- The FTP MSP supports only a clear-text password.
- If the remote filesystem must be restored to a previous state, inconsistencies may arise: remote files that reappear after being deleted are never removed, and remote files that disappear unexpectedly result in data loss. There is presently no way to detect these inconsistencies. You should avoid situations that require the remote filesystem to be restored to a previous state.

## Disk MSP

This section discusses the following:

- "Disk MSP Overview" on page 577
- "Disk MSP Processing of Requests" on page 577
- "Disk MSP Activity Log" on page 578

## Disk MSP Overview

The disk MSP (`dmdskmsp`) migrates data into a directory that is accessed on the current system. It uses POSIX file interfaces to open, read, write, and close files. The directory may be NFS-mounted, unless the disk MSP is configured as a disk cache manager MSP (see "DCM MSP" on page 579). The data is read and written with `root` (UID 0) privileges. By default, `dmdskmsp` stores the data in a blocked format that is specific to DMF, which allows the MSP to do the following:

- Keep metadata with a file
- Keep sparse files sparse when they are recalled
- Verify that a file is intact on recall

The disk MSP does not need a private database to operate; all information necessary to retrieve offline files is kept in the daemon database and DMF configuration file.

The disk MSP may also be used as an import MSP. In this case, it only permits recalls and copies the data unchanged for a recall.

## Disk MSP Processing of Requests

The disk MSP is always waiting for requests to arrive from the DMF daemon. To improve efficiency, it holds `PUT` and `DELETE` requests briefly and groups similar requests together into a single session:

- No `PUT` request will be held longer than 60 seconds
- No `DELETE` request will be held longer than 5 seconds

---

**Note:** `GET` requests are not held.

---

The disk MSP will stop holding requests if it has a large amount of work to do (more than 1024 individual files or 8 MB of data).

After a request has been held for the appropriate amount of time, it enters a ready state. Processing usually begins immediately, but may be delayed if resources are not available.

The following administrator-controlled limits affect the maximum number of requests that can be processed:

- Maximum number of concurrent operations per MSP (`CHILD_MAXIMUM`)
- Number of child processes that are guaranteed to be available for processing delete requests (`GUARANTEED_DELETES`)
- Number of child processes that are guaranteed to be available for processing `dmget(1)` requests (`GUARANTEED_GETS`)

Requests are processed by forking off a child process. The parent process immediately resumes waiting for requests to arrive from the DMF daemon.

Requests are shared out amongst the running child processes on a first-come, first-served basis. Requests are not batched; children handle at most one request at a time. Requests handed to any particular child process might be freely intermixed; a given child may handle any combination of PUT, GET, or DELETE operations (even if `GUARANTEED_GETS` or `GUARANTEED_DELETES` is set in the DMF configuration file).

The stored files are not verbatim copies of the user files. They are stored using the same format used to write tapes, and you can use MSP utilities such as `dmatread` and `dmatsnf` to access the data in them.

## Disk MSP Activity Log

All DMF MSPs maintain log files named `m脾log.yyyymmdd` in the MSP spool directory which, by default, is `SPOOL_DIR/mspname`. `SPOOL_DIR` is configured in the `base` object of the configuration file; `mspname` is the name of the MSP in the `daemon` object of the configuration file; `yyymmdd` is the current year, month, and day).

The log file shows the arrival of new requests, the successful completion of requests, failed requests, and creation and deletion of child processes. In addition, the MSP lists the contents of its internal queues in its activity log if it is given an `INTERRUPT` signal.

---

**Note:** Because the disk MSP will continue to create log files without limit, you must remove obsolete files periodically by configuring the `run_remove_logs` task in the configuration file, as described in "taskgroup Object" on page 304.

---



## DCM MSP

The *Disk cache manager (DCM) MSP* is the disk MSP configured for *n*-tier capability using a dedicated filesystem as a cache. The DCM MSP provides fast access for files whose activity levels remain high while also providing migration to tape/MAID/JBFS for those files requiring less frequent access.

To allow the disk store that is managed by the disk MSP to function as a dynamically managed cache (as opposed to a static store), the DCM MSP creates and maintains a filesystem attribute on each file that is created in the MSP `STORE_DIRECTORY`. This attribute is used by the `dmdskfree` process to evaluate files for downward migration and for possible removal from the disk cache. For this reason, the DCM MSP `STORE_DIRECTORY` must be a local XFS or CXFS filesystem mount point with DMAPI enabled.

The DCM MSP supports *dual-resident state*, in which files reside in the cache and also in a lower VG. This provides the access speed of a disk file, but allows that cache file to be quickly released without the need to first write it to tape/MAID/JBFS. This is directly analogous to the concept of a dual-state file in the standard managed filesystem.

Automated movement in the opposite direction (from tape/MAID/JBFS back to the cache) is not available. Any recalls of files that no longer have copies held in the cache will come directly from tape/MAID/JBFS; they are not recalled via the cache and they can only be restored to the cache by an explicit `dmmove(8)` command.

## `dmdskvfy` Command

The `dmdskvfy` command verifies that copies of migrated files in DCM and disk MSPs are consistent with the daemon database entries that refer to them.

## Moving Migrated Data

The `dmmove(8)` command moves copies of offline or dual-state files to a specified set of MSPs, VGs, or MGs. The options specified on command line indicate which targets are to contain migrated copies of a file after the move process is completed. All other migrated copies are hard-deleted unless you use the `dmmove -d` to select specific copies for deletion.

If a file's migrated state is offline, `dmmove` recalls the file to disk and then remigrates it to the specified targets. (The one exception to this is that if a disk cache manager disk MSP copy exists, the file will be moved directly from that file copy.) The file is recalled to a scratch filesystem that is specified by the `MOVE_FS` configuration parameter. When the migration process is complete, the online copy is removed. If the file is dual-state, `dmmove` does not need to recall the file first, but instead uses the existing online copy.

The `dmselect(8)` command can be used to determine which files you want to move. `dmselect` selects files based on age, size, ownership, and MSP criteria. The output from the `dmselect` command can be as input to the `dmmove` command. The `dmmove` command also accepts a list of pathnames as input.

See the `dmselect(8)` and `dmmove(8)` man pages for all of the possible options and further information.

## LS Error Analysis and Avoidance

The drive group component of the LS monitors media use, analyzes failures, and uses this information to avoid future errors.

The drive group component can react to some failures without looking for any patterns of behavior. Among these are the following:

- Mounting service failure. If the mounting service is TMF, by default, DMF makes one attempt to restart it. If this attempt does not succeed, DMF notifies the administrator by e-mail and waits for the administrator's intervention. When TMF is back again, DMF resets the auto-restart flag so that if TMF fails again, it will once again make one attempt to restart it.

If OpenVault is the mounting service, by default, no attempt is made to restart it. Instead, an e-mail is sent to the administrator.

A site can set the number of automatic restart attempts by using the drive group's `MAX_MS_RESTARTS` configuration parameter, but caution and thorough testing are advised. There are many possible failure modes for a mounting service, and automated restarts might not always be appropriate.

- Volume is not in the library. Obviously, this problem will not be fixed by trying again. To prevent further access, the volume is locked by setting the `HLOCK` flag, as described below, and the user requests that triggered the access attempt are

retried on another tape, if possible; otherwise, they are aborted. The administrator is notified by e-mail.

- For TMF only, a tape mount was cancelled by an operator or administrator. Although the user requests are retried or aborted, the volume is not disabled. If the volume were disabled, it would be inaccessible for a period of time (default 24 hours) unless `dmvoladm` were used to preempt this delay. All operators do not necessarily have access to the `dmvoladm` command.

Because the reason for the cancellation is unknown to DMF, repeated requests for the same volume are quite possible, and the operator might have to cancel each one.

The drive group handles other types of failure by examining the recent history of the volume and the drive that was used. The drive group maintains records of past I/O errors and uses these to control the way it reacts to future errors.

For example, if a tape has been unusable several times in a row, even though different drives were used, the drive group concludes that the problem most likely involves the tape rather than the drive. Therefore, it suspends use of that tape, forcing DMF to migrate to a different tape in that VG or to recall the file from another tape held by a different VG. This suspension is usually done by setting the `HLOCK` flag in the tape's entry in the VOL record of the LS database. This makes the tape inaccessible to the VG for both reading and writing until it is automatically cleared after `REINSTATE_VOLUME_DELAY` minutes.

If a variety of volumes fail on a specific drive but are usable on other drives, a drive problem is likely, and the drive can be automatically configured down if permitted by the administrator's setting of `DRIVES_TO_DOWN` to a value higher than its default of zero. When a drive is configured down in this way, it is configured up again after `REINSTATE_DRIVE_DELAY` minutes.

The analyses of drive and volume errors are performed independently of each other; it is possible for one additional error to result in both the drive and the volume being disabled.

There are several reasons for reinstating drives and volumes after a delay. The most important is that the analyses of previous failures might lead to a faulty conclusion in some situations, such as when DMF is under a very light load, or when multiple failures occur concurrently. A wrong diagnosis might impact DMF's performance, and should not be accepted indefinitely. Disabling a suspected drive or volume for a while is usually enough to break any repetitive cycles of failure. If such patterns reestablish

themselves when the reinstatement occurs, the drive group will again analyze the behavior, possibly reaching a different conclusion, and again try to prevent it.

There are some variations from these general reactions. For example, if a tape with existing data on it is diagnosed as faulty when appending new data, instead of setting the `HLOCK` flag, the drive group sets `HVFY`, which results in the tape being used in a read-only mode until eventually emptied by merges or hard deletion of its files. At that time, the administrator may choose to test it and possibly replace or delete it. If it is to be returned to service, the `HVFY` flag should be cleared by using `dmvoladm`. Full details of these procedures are included in the email sent to the administrator at the time of the error.

If it is considered desirable to return a volume or drive to service earlier than defined in the DMF configuration, the appropriate command (`dmvoladm`, `tmconfig`, or `ov_drive`) can be safely used.

## LS Drive Scheduling

When multiple VGs are requesting the use of more drives than exist in the drive group, the resource scheduler is used to decide which VGs should wait and which should be assigned the use of the drives.

The resource scheduler is only aware of volume-group activity on the drives in its drive group. This excludes activity such as XFS backups and direct media use by the system's users; this use does not prevent the LS from working properly, although it might be less than optimal.

## LS Status Monitoring

You can observe the performance of the LS in two ways:

- Monitor its log file with a tool like `tail -f`, which allows an experienced administrator to follow the flow of events as they happen
- Use the resource watcher component, when enabled by use of the `WATCHER` parameter in the `libraryserver` configuration stanza

The resource watcher is intended to give the administrator a view of the status of an LS and some of its components. It maintains a set of text files on disk that are rewritten as events happen. These files can be found in the following directory:

*SPOOL\_DIR/libraryserverObjectName/\_resourcewatcherObjectName*

*SPOOL\_DIR* is defined in the DMF configuration file (for example `/dmf/spool`), as are the names of the `libraryserver` and `resourcewatcher` objects (for example, `lsname` and `rwname`). The easiest way to find the precise path is to look in the LS log file for messages like the following:

```
rwname.config_changed: URL of home page is file:/dmf/spool/lsname/_rwname/lsname.html
```

This message is issued at DMF startup or whenever the configuration file is altered or its modification time changes; for example, by using the `touch(1)` command.

The `SPOOL_DIR/lsname/_rwname` directory contains files with names ending in `.html`, which are automatically refreshing HTML files. You can access these files by using a browser running on the same machine. The following example shows an LS page that contains links to drive group pages, and they in turn have links to VG pages, if the VGs are active at the time:

```
netscape file:/dmf/spool/lsname/_rwname/lsname.html
```

If running the browser on the DMF machine is inconvenient, you can include the directory in your HTTP server configuration to allow those same pages to be accessed via the web.

This directory also contains files whose names end in `.txt`, designed to be parsed with programs like `awk`. The data format is described by comments within those files and can be compared with the equivalent HTML files.

If the format of the text ever changes, the version number will change. If the changes are incompatible with previous usage, the number before the decimal point is altered. If they are compatible, the number after the decimal point is altered.

An example of compatibility is adding extra fields to the end of existing lines or adding new lines. Programs using these files should check the version number to ensure compatibility. Also, it might be useful to check the following:

- DMF version shown by `dmversion(1)`
- Linux kernel version shown by `uname(1)`
- Linux distribution version shown by `head /etc/*release`



## DMF Maintenance

This chapter contains the following:

- "Retaining Old DMF Daemon Log Files" on page 585
- "Retaining Old DMF Daemon Journal Files" on page 586
- "Cleaning Up Obsolete Database Entries" on page 586
- "Using `dmfill`" on page 587
- "Viewing Drive Statistics" on page 587
- "Temporarily Disabling Components" on page 589

See also:

- "Restoring Files from Backups" on page 643
- "Recovery and Restoration of DMF Database" on page 646

### Retaining Old DMF Daemon Log Files

The DMF daemon generates the `SPOOL_DIR/daemon/dmdlog.yyyymmdd` log file, which contains a record of DMF activity and can be useful for problem solving for several months after creation. All MSPs and LSs generate a `SPOOL_DIR/msp_or_ls_name/msplog.yyyymmdd` log file, which also contains useful information about its activity. The LS also generates `SPOOL_DIR/ls_name/moverlogs/hostname/moverlog.yyyymmdd` log files, which also contain useful information about its activity. These log files should be retained for a period of some months. Log files more than a year old are probably not very useful.

Do not use DMF to manage the `SPOOL_DIR` filesystem.

The `dmfsmon(8)` automated space management daemon generates a log file in `SPOOL_DIR/daemon/autolog.yyyymmdd`, which is useful for analyzing problems related to space management.

To manage the log files, configure the `run_remove_logs.sh` task, which automatically deletes old log files according to a policy you set. See "taskgroup Object" on page 304, for more information.

## Retaining Old DMF Daemon Journal Files

The DMF daemon and the LS generate journal files that are needed to recover databases in the event of filesystem damage or loss. You also configure DMF to generate backup copies of those databases on a periodic basis. You need only retain those journal files that contain records created since the oldest database backup that you keep. Although in many cases only the most recent database backup copy is sufficient, SGI recommends that you keep several generations for additional safety.

For example, if you configure DMF to generate daily database backups and retain the three most recent backup copies, then at the end of 18 July there would be backups from the 18th, 17th, and 16th. Only the journal files for those dates need be kept for recovery purposes.

To manage the journal files and the backups, configure the `run_remove_journals.sh` and `run_copy_databases.sh` tasks. These tasks automatically delete old journal files and generate backups of the databases according to a policy you set. See "taskgroup Object" on page 304, for more information.

## Cleaning Up Obsolete Database Entries

When a file is migrated by DMF, a database record is created for each MSP/VG copy of the file. When the file is deleted or modified, those records point to copies that no longer correspond to any file in the filesystem. At this point, DMF tags these records as *soft-deleted*.

Soft-deleted database records must remain in the database as long as the original file might reappear as an offline file as the result of a full or partial filesystem restore. This amount of time is defined by the `DUMP_RETENTION` configuration parameter (see "taskgroup Object Parameters" on page 312).

After soft-deleted records pass the `DUMP_RETENTION` time, they are obsolete. At that point, they become candidates for *hard-deletion*, which permanently removes the records from the database. This decreases the total number of database records (for which there is a maximum of 4 billion). See "Use a Task to Perform Hard-Deletes Periodically" on page 131.



**Caution:** Do not hard-delete a database record until after you are sure that the corresponding file will never be restored.

---



## Using `dmfill`

The `dmfill(8)` command allows you to fill a restored filesystem to a specified capacity by recalling offline files. When you execute `xfsdump -a`, only inodes are backed up for all files that have been migrated (including dual-state files). Therefore, when the filesystem is restored, only the inodes are restored, not the data. You can use `dmfill` in conjunction with `xfsrestore` to restore a corrupted filesystem to a previously valid state. `dmfill` recalls migrated files in the reverse order of migration until the requested fill percentage is reached or until there are no more migrated files left to recall on this filesystem.

## Viewing Drive Statistics

To view statistics about drives across the DMF environment, you can use the `dmtapestat(8)` command as `root` from the DMF server. By default, `dmtapestat` displays the following fields (known as the *default field selection list*), in ascending order by drive name:

| <b>Field</b>             | <b>Description</b>                       |
|--------------------------|------------------------------------------|
| <code>vg</code>          | Volume group                             |
| <code>vsn</code>         | Volume serial number (VSN)               |
| <code>dg</code>          | Drive group                              |
| <code>drive</code>       | Drive name                               |
| <code>node</code>        | Node name                                |
| <code>pid</code>         | Process ID                               |
| <code>bytes_moved</code> | Total number of bytes moved by the drive |
| <code>op</code>          | Current drive operation                  |
| <code>status</code>      | Status of the filesystem                 |

For example, the following output shows that drive C02d00 is idle:

```
# dmtapestat
VG      VSN      DG      DRIVE  NODE      PID      BYTES_MOVED  OP  STATUS
dg_c02  C02d00          0      0          U      Idle
dg_c02  C02d01          0      0          U      Idle
dg_c02  C02d02          0      0          U      Idle
dg_c02  C02d03          0      0          U      Idle
dg_c02  C02d04          0      0          U      Idle
dg_c02  C02d05          0      0          U      Idle
dg_c02  C02d06          0      0          U      Idle
vg_c03  C03W00  dg_c03  C03d00  dignity2  29799  193986560    G  Waiting at zone 145
vg_c03  C03S00  dg_c03  C03d01  dignity2  29280  351272960    G  Waiting at zone 1654
vg_c03  C03L00  dg_c03  C03d02  dignity2   944   59768832    G  Waiting at zone 1407
vg_c03  C03J00  dg_c03  C03d03  dignity2  1934   9437184     G  Waiting at zone 36
vg_c03  C03G00  dg_c03  C03d04  dignity2   694  123731968    G  Waiting at zone 1687
vg_c03  C03B00  dg_c03  C03d05  dignity2  29536  229638144    G  Waiting at zone 1230
vg_c03  C03T00  dg_c03  C03d06  dignity2   677  105906176    G  Waiting at zone 321
```

You can customize the `dmtapestat` output by providing field names known to the common arena and using the following options to manipulate the display:

- To add fields to the output, in addition to the default field selection list:

```
-a field1[ , field2. . . ]
```

- To change the list of fields displayed (overriding the default field selection list):

```
-c field1[ , field2. . . ]
```

The fields are displayed in the order specified.

- To sort the output by the specified fields:

```
-s field1[ , field2. . . ]
```

By default, `-s` sorts in ascending order. To specify descending order for a specific field, prefix the field with the minus ("-") sign. If you want to include white space, you must enclose the list of fields with quotation marks.

For example, to display the `pid`, `drive`, and `access_time` fields with the output sorted in descending order by process ID, enter the following:

```
# dmtapestat -c pid,drive,access_time -s -pid
PID    DRIVE    ACCESS_TIME
10491  C03d02  1317251582
10479  C03d05  1317251592
9985   C03d04  1317251572
9485   C03d01  1317251582
8950   C03d03  1317251590
8410   C03d06  1317251585
8384   C03d00  1317251580
0      C02d01  1317213541
0      C02d00  1317223473
0      C02d03  1317216907
0      C02d02  1317223560
0      C02d05  1317223292
0      C02d04  1317213499
0      C02d06  1317223472
```

For more information about available drive arena fields, see the `dmtapestat(8)` man page.

## Temporarily Disabling Components

If you are using OpenVault, you can choose to temporarily disable a specific path to a drive (the *drive control program* or *DCP*), individual drives, or the entire library of drives. When you temporarily disable a drive in OpenVault, a mount request for that drive will block. (If you permanently disable a drive, a mount will be rejected).

---

**Note:** When you disable an OpenVault DCP, drive, or library, new mounts are immediately disabled but there might be running processes that are already using the drives. For safety, you must wait for DMF to notice that the component has been disabled and for those processes to stop before performing maintenance.

---

This section discusses the following:

- "Disable an OpenVault DCP" on page 590
- "Disable an OpenVault Drive" on page 591

- "Disable an OpenVault Library" on page 592
- "Disable a TMF Drive" on page 594
- "Stop the COPAN VTL" on page 595

## Disable an OpenVault DCP

To temporarily disable one path to a drive (which still permits new mounts using other paths to that drive) when the drive is not in use, do the following:

1. Disable the DCP by using the following `ov_dcp(8)` command, where *drive\_expr* and *dcp\_expr* may be regular expressions:

```
# ov_dcp -T drive_expr dcp_expr
```

For example, to disable the DCP `t200d2@node1` for the `t200d2` drive (line breaks shown here for readability):

```
# ov_dcp -T t200d2 t200d2@node1
```

DCPs:

| Drive Name                                                        | DCP Name     | DCP Disabled | DCP Host | DCP Type | DCP Priority |
|-------------------------------------------------------------------|--------------|--------------|----------|----------|--------------|
| DCP Control Path                                                  |              |              |          |          |              |
| t200d2                                                            | t200d2@node1 | temporary    | node1    | Ultrium6 | 1000         |
| /dev/ts/pci0000:0c:00.0/fc/21120090a5003194-22120090a5003194/lun0 |              |              |          |          |              |

After some time (up to 6 minutes), DMF will notice this new DCP state and will shut down any mover children using this DCP.

To permanently disable the path, use the `-D` option.

---

**Note:** The behavior is different for a non-mover process, such as for `dmat.snf(8)`, `dmatread(8)`, or `xfsdump(8)`. If one of these processes already has a volume mounted when the DCP/drive/library is disabled, the process will continue to completion. If using `-T` and one of these processes specifically asks for a mount in that drive, the mount will block. (If using `-D`, the mount will fail.) If a drive is disabled and one of these processes requests a mount without specifying a particular drive, it will be directed to an enabled drive in the drive group.

---

2. Verify that the path to the DCP is now unusable. For example, use the `ov_stat(8)` command to display the status of the DCPs for the `t200d2` drive:

```
# ov_stat -D t200d2 -x
DCPName      DriveName Usable SoftState   Disabled  MsgLevel
t200d2@node1 t200d2   false disconnected temporary debug
t200d2_2@node1 t200d2   true  ready        false     debug
```

To later reenable the DCP, use the `-E` option.

For more information, see the following man pages:

```
ov_dcp(8)
ov_dumptable(8)
```

## Disable an OpenVault Drive

To temporarily disable one or more drives, do the following:

1. Disable the individual drives by using the `ov_drive(8)` command. where `drive_expr` may be a regular expression:

```
# ov_drive -T drive_expr
```

For example, to disable all drives that have names that begin with `t200`:

```
# ov_drive -T 't200.*'
Drives:
Drive          Drive Group   Disabled   Vendor Product
Serial Number
t200d3         drives        temporary  IBM ULTRIUM-TD5  1013003194
t200d1         drives        temporary  IBM ULTRIUM-TD6  1011003194
t200d2         drives        temporary  IBM ULTRIUM-TD6  1012003194
```

After some time (up to 6 minutes), DMF will notice this new drive state and will shut down any mover children using these drives.

---

**Note:** The behavior is different for a non-mover process. See the Note above in "Disable an OpenVault DCP" on page 590.

---

To permanently disable a drive, use the `-D` option instead. For more details, see the `ov_drive(8)` man page.

2. Verify that the drives are disabled by using the `ov_stat(8)` command. To display the status of all drives, use the `-d` option:

```
# ov_stat -d
```

To verify specific drives, use the `-D` option. For example, the following output shows that all of the drives that begin with `t200` are unusable and temporarily disabled:

```
# ov_stat -D 't200.*'
DriveName Group Usable Access Disabled SoftState HardState Occupied PCL
t200d1     drives false true  temporary ready      unloaded false
t200d2     drives false true  temporary ready      unloaded false
t200d3     drives false true  temporary ready      unloaded false
```

To reenable the drives, use the `ov_drive -E`. For more information, see the `ov_drive(8)` man page.

## Disable an OpenVault Library

To disable the entire library, do the following:

1. Disable the library by using one of the following `ov_library(8)` command lines. After some time (up to 6 minutes), DMF will notice this new library state and will shut down any mover children using the drives in this library. For more details, see the `ov_library(8)` man page.

---

**Note:** The behavior is different for a non-mover process. See the **Note** above in "Disable an OpenVault DCP" on page 590.

---

- If you make copies of files in separate libraries, you can use the following command to disable the primary library and redirect recalls to the other library, where `lib_expr` may be a regular expression:

```
# ov_library -D lib_expr
```

For example:

```
# ov_library -D t120
```

After you use this command, the `ov_stat` command will report a Disabled state of permanent. So long as the other library is not also disabled with the `-D` option, recall requests will be forwarded to the other library. Migrate requests to the disabled library will queue. An OpenVault mount request to this library (such as if you are using `xfbackup`) would fail.

- If there is not another library, use the following command.

```
# ov_library -T lib_expr
```

For example:

```
# ov_library -T t120
```

2. Verify the Disabled state of the library by using the `-l` option to `ov_stat`. For example, the following output shows that the `t120` library is temporarily disabled:

```
# ov_stat -l
LibraryName Usable Disabled
t120         false temporary
t200         true  false
```

3. Verify that all of the drives in the library have a `SoftState` state of `ready` (and are therefore currently unused) by using the `ov_stat -d` command. For example, the following output shows that although the drives are still enabled (with a `false` state for `Disabled` because only the library was disabled), they are unused (because the `SoftState` state is `ready`):

```
# ov_stat -d
DriveName Group Usable Access Disabled SoftState HardState Occupied PCL
t120d1    drives true  true  false  ready  unloaded false
t120d2    drives true  true  false  ready  unloaded false
t120d3    drives true  true  false  ready  unloaded false
```

To reenble the library, use the `ov_library -E` option.

For more information, see the following man pages:

- `ov_library(8)`
- `ov_stat(8)`

## Disable a TMF Drive

To disable TMF drives, do the following:

1. Disable the drives by using the `tmconfig(8)` command:

```
# tmconfig drivenames down
```

For example, to disable the two drives `tape01` and `tape03`:

```
# tmconfig tape01:tape03 down
```

After some time (up to 6 minutes), DMF will notice this new drive state and will shut down any mover children using these drives.

---

**Note:** The behavior is different for a non-mover process. See the Note above in "Disable an OpenVault DCP" on page 590.

---

2. Verify that the drives are unused and have a `stat` status of `down` by examining the output of the `tmstat(8)` command:

```
# tmstat
```

For example, the following output shows that both `tape01` and `tape03` are down (down in the `stat` field) and unused (empty `user` and `session` fields):

```
# tmstat
user  session  group  a  stat  device  stm  rl  ivsn  evsn  blocks
      dga     -  down  tape01
      dga     -  down  tape03
```

To reenable the drives, use the `tmconfig up` command.

For more information, see the following man pages:

- `tmconfig(8)`
- `tmstat(8)`



## Stop the COPAN VTL

Following is one way stop COPAN VTL:

1. Disable the COPAN VTL drives gracefully. See "Temporarily Disable Components Before Maintenance" on page 128.

Do not proceed to the next step until you verify that all of the drives are disabled.

2. Stop the LCPs associated with the COPAN drives:

- If you have only COPAN drives, stop all of the LCPs:

```
# ov_stop lcp
```

- If you have a mix of COPAN VTLs and physical tape libraries, stop just the COPAN LCPs:

```
# ov_stop COPAN_LCP1 COPAN_LCP2 ...
```

For example, if there are four COPAN LCPs named C00-C03:

```
# ov_stop C00 C01 C02 C03
```

3. When you want to restart the COPAN VTL, restart the LCPs associated with the COPAN VTL:

- If you have only COPAN drives, start all of the LCPs:

```
# ov_start lcp
```

- If you have a mix of COPAN VTLs and physical tape libraries, start just the COPAN LCPs:

```
# ov_start COPAN_LCP1 COPAN_LCP2 ...
```

For example, if there are four COPAN LCPs named C00-C03:

```
# ov_start C00 C01 C02 C03
```

4. Reenable the COPAN drives, where *COPAN\_drive\_expr* may be a regular expression:

```
# ov_drive -E COPAN_drive_expr
```



## DMF SOAP Server

This chapter discusses the following:

- "Overview of DMF SOAP" on page 597
- "Accessing the DMF SOAP and WSDL" on page 599
- "Starting and Stopping the DMF SOAP Service" on page 600
- "Security/Authentication" on page 601
- "DMF SOAP Sample Client Files" on page 601

### Overview of DMF SOAP

DMF provides access to the following functions via the DMF Simple Object Access Protocol (SOAP) web service:

```
dmarchive
dmattr
dmget
dmoper
dmprojid
dmput
dmrestore
dmsoapquery
dmtag
dmversion
```

---

**Note:** A limited set of options are available for these commands via DMF SOAP. For more information, click on the operation name in the SOAP interface and read the information under the **Documentation** heading displayed.

---

DMF SOAP log files are kept in *SPOOL\_DIR*/dmfsoap.

Figure 16-1 shows an example of the documentation for the `ws_dmattr` operation.




Figure 16-1 DMF SOAP Operation Documentation

## Accessing the DMF SOAP and WSDL

To access DMF SOAP, do the following:

1. Point your browser to the following secure address:

```
https://YOUR_DMF_SERVER:11110/server.php
```

2. Accept the security certificate.

---

**Note:** DMF SOAP generates its own SSL certificates, rather than having the SSL certificates signed by a commercial certificate authority. Therefore, the certificate warning is safe to ignore.

---

3. Enter the DMF SOAP service user name (`dmfsoap`) and password. The default password is `INSECURE`.

---

**Note:** To change the password to something site-specific (`NEWPASSWORD`), run the following command:

```
# htpasswd2 -b -c /usr/share/dmfsoap/passwords/passwds dmfsoap NEWPASSWORD
```

---

4. To access the web service definition language (WSDL) definition, click on **WSDL** in the interface. Figure 16-2 shows an example. Use the browser's **Save As...** feature to save the WSDL to a file for consumption.

```

<xsd:complexType>
- <xsd:complexType name="dmgetRequest">
  - <xsd:all>
    <xsd:element name="username" type="xsd:string" minOccurs="1" maxOccurs="1"/>
    <xsd:element name="getbyterangeArray" type="tns:byterangeArray" minOccurs="0"/>
    <xsd:element name="priority" type="xsd:int" minOccurs="0" maxOccurs="1"/>
    <xsd:element name="mspvplist" type="xsd:string" minOccurs="0" maxOccurs="1"/>
    <xsd:element name="names" type="tns:namesArray" minOccurs="1"/>
  </xsd:all>
</xsd:complexType>
- <xsd:complexType name="dmputRequest">
  - <xsd:all>
    <xsd:element name="username" type="xsd:string" minOccurs="1" maxOccurs="1"/>
    <xsd:element name="release" type="xsd:boolean" minOccurs="0" maxOccurs="1"/>
    <xsd:element name="freedbyterangeArray" type="tns:byterangeArray" minOccurs="0"/>
    <xsd:element name="keptbyterangeArray" type="tns:byterangeArray" minOccurs="0"/>
    <xsd:element name="mspvplist" type="xsd:string" minOccurs="0" maxOccurs="1"/>
    <xsd:element name="names" type="tns:namesArray" minOccurs="1"/>
  </xsd:all>
</xsd:complexType>
- <xsd:complexType name="dmarchiveRequest">
  - <xsd:all>
    <xsd:element name="username" type="xsd:string" minOccurs="1" maxOccurs="1"/>
    <xsd:element name="preserveattrs" type="xsd:boolean" minOccurs="0" maxOccurs="1"/>
    <xsd:element name="skipexisting" type="xsd:boolean" minOccurs="0" maxOccurs="1"/>
    <xsd:element name="replaceexisting" type="xsd:boolean" minOccurs="0" maxOccurs="1"/>
    <xsd:element name="updateexisting" type="xsd:boolean" minOccurs="0" maxOccurs="1"/>
    <xsd:element name="priority" type="xsd:int" minOccurs="0" maxOccurs="1"/>
  </xsd:all>

```

Figure 16-2 WSDL Definition

## Starting and Stopping the DMF SOAP Service

This section discusses the following:

- "Starting the dmsoap Service" on page 601
- "Preventing Automatic Start of dmsoap After Reboot" on page 601
- "Explicitly Stopping dmsoap" on page 601

## Starting the `dmfsoap` Service

The `dmfsoap` service for DMF SOAP is off by default.

To start the service explicitly, execute the following on the DMF server:

```
dmfserver# service dmfsoap start
```

## Preventing Automatic Start of `dmfsoap` After Reboot

To prevent automatic startup of the DMF environment, execute the following `chkconfig(8)` commands as `root` on the DMF server:

```
dmfserver# chkconfig dmfsoap off
```

## Explicitly Stopping `dmfsoap`

To stop the DMF environment daemons explicitly, execute the following on the DMF server:

```
dmfserver# service dmfsoap stop
```

## Security/Authentication

DMF SOAP uses basic access authentication, via HTTPS, when making a request. Encapsulated in the request is the user name on the DMF system. DMF SOAP checks that the user name supplied is a valid and executes the DMF command as that user. However, no additional authentication is done; the client has complete responsibility for user authentication.

## DMF SOAP Sample Client Files

DMF provides the following sample PHP files via the web interface that you can use to remotely access the DMF SOAP service:

```
dmarchive.php  
dmattr.php  
dmget.php  
dmoper.php
```

```
dmprojid.php
dmput.php
dmrestore.php
dmsoapquery.php
dmtag.php
dmversion.php
```

These files are installed in the following directory:

```
/usr/share/doc/dmf-VERSION/info/sample/dmfsoap_client
```

These files are simply for demonstration purposes. You can copy them the remote machine from which you want to access the DMF SOAP service and modify as needed.



**Caution:** There is no security provided by these sample files.

---

To use the sample files, you must install the following packages:

```
php5-soap
php-curl
php5-openssl
```

For more information, see the README file and the comments in the .php files.

For example, the following is the sample file for dmget.php (line breaks added here for readability):

```
<?php
#
# Copyright 2012 SGI. All rights reserved.
#
# This is a simple example SOAP Client interface to the DMF SOAP
# Service supporting the dmget interface.
# Note: You may need to install the php curl and php openssl
# packages on your machine.
#
# Nothing SOAP related yet. Just set up some variables specific
# to dmget and parse the command line arguments.
$priority = null;
$getByteRangeArray = array();
$getbyterange_cnt = 0;
$getbyterange = false;
```



```

$request = array();
$namesArray = array();
for( $i = 0; $i < $argc; $i++ ) {
    if( $argv[$i] == '-h' ) {
        echo "Usage: php dmget.php WSDL login password username
[-U priority] [-B getbyterange-list] fullpathnametofile1 fullpathnametofile2 \nWhere
getbyterange-list can be a comma separated list (no spaces)\nExamples:\n\tphp dmget.php
https://machine.com:11110/server.php?wsdl dmfsoap INSECURE username
-B 0:4000 /dmf_fs/testfile\n";
        exit;
    }
    if( $argv[$i] == '-B' ) {
        $i++;
        $getbyterange = true;
        $values_array = explode(",", $argv[$i]);
        foreach($values_array as $value) {
            $value_array = explode(":", $value);
            $start = $value_array[0];
            $end = $value_array[1];
            $getByteRangeArray[$getbyterange_cnt] = array('start' =>
$start, 'end' => $end);$getbyterange_cnt = $getbyterange_cnt + 1;
        }
        continue;
    }
    if( $argv[$i] == '-U' ) {
        $i++;
        $priority = $argv[$i];
        continue;
    }
    if( $i < 5 ) {
        continue;
    }
    array_push($namesArray, $argv[$i]);
}

# Here's the SOAP work
$wsdl = $argv[1];
$login = $argv[2];
$password = $argv[3];
$username= $argv[4];
$request['username']=$username;

```

```
$request['getbyterangeArray']=$getByteRangeArray;
$request['priority']=$priority;
$request['names']=$namesArray;

# First, initialize the connection.
$client = new SoapClient($wsdl, array('login'=>$login, 'password'=>$password));

# Now make the request
try {
    $result = $client->ws_dmget($request);
} catch( SoapFault $fault ) {
    print("Sorry, $argv[0] returned the following ERROR: ".$fault->faultcode."-".$fault->faultstring."\n");
    return;
}

# Finally print the results
print_r($result);

?>
```

## DMF Queue Viewing

This section discusses the following:

- "QView Tab and the `dmqview` Command" on page 605
- "Taking a Snapshot of the DMF Requests" on page 606
- "Queue Reports" on page 606
- "Canceling a Request" on page 613
- "Reprioritizing a Request" on page 615
- "Modifying the Report Output" on page 615
- "Example of Queue-Related Tasks" on page 619
- "Database Tables and Fields" on page 620

### QView Tab and the `dmqview` Command

The **QView** tab of DMF Manager and the `dmqview(8)` command display information about the internal DMF processing queues. You must log into DMF Manager to use **QView** or be `root` to run `dmqview`.

The reports that the tools display contain details about how requests relate to each other, which you can use to answer questions such as the following:

- How many recalls are in the queue?
- Where is the request for a specific file in the queue, relative to other requests?
- What is the ID of a given request, so that I can cancel or reprioritize it?

The **QView** tab in DMF Manager also lets you directly cancel and reprioritize requests; the `dmcancel(8)` and `dmrepri(8)` commands provide the same functionality for the command line.

## Taking a Snapshot of the DMF Requests

To view queue information, you must first take a snapshot of the current DMF requests by using the `dmqview --snap` option or by using the following **QView** menu selection in DMF Manager:

```
QView  
> Refresh QView
```

This action pauses DMF activity in order to create several relational-database tables (see "PostgreSQL Database Tables" on page 621) that reflect all of the current DMF requests. There may be hundreds of thousands of requests in the queue. The snapshot normally completes in a few seconds, but may take longer if a daemon is working on a time-consuming operation and does not immediately notice the snapshot request. The snapshot represents a static view of the requests and therefore will become stale over time. However, because it momentarily halts all activity, you should refresh the snapshot only when necessary.

## Queue Reports

After a snapshot exists, you can issue a series of queries against that snapshot by selecting various reports:

- "Summary Report and Corresponding State Reports" on page 606
- "Composite Reports" on page 609

---

**Note:** These queries have no affect on the daemon, but they can impact performance if they require joining multiple database tables in order to access the required data. If a refresh is required, you can select the **Refresh QView** menu again.

---

## Summary Report and Corresponding State Reports

The **Summary** report displays a brief listing of all request states, as supplied by the **Chunk** (`chunk`) and **Request** (`dmn_request`) database tables, see "PostgreSQL Database Tables" on page 621.

Each item reported by a bar graph at the top of the page has a corresponding detailed report listed under the **Summary** heading. Figure 17-1 shows an example. You can also click on a bar in the graph to display that state report.




Figure 17-1 QView: Summary Reports

The summary report is available at the command line with the `--report summary` option:

```
# dmqview --report summary
      REPORT summary:   SNAPSHOT: 2015-03-20 10:33:39+00:00
      Status            Count            Bytes
wait_drive            33            330005736
      active            22            220003828
```

The report names used by the command line are lowercase and one string (such as `--report wait_host`). See the `dmqview(8)` man page for details.

All reports other than **Active** and **MSP Active** indicate that the requests are waiting to be processed. Some reports are specific to the library server (LS), a media-specific process (MSP), or a volume group (VG).

**Table 17-1** Summary Reports

| Report Name           | Description                                                                                                                                            |
|-----------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Active</b>         | Displays the requests that are being worked on by a data-mover process of the LS.                                                                      |
| <b>Database Query</b> | Displays the requests that are waiting because a database query is being performed.                                                                    |
| <b>Ejected</b>        | Displays the requests that are waiting because the physical tape has been ejected.                                                                     |
| <b>Inaccessible</b>   | Displays the requests that are waiting because a volume cannot be mounted. This status usually means that there is an issue with the physical library. |
| <b>Mounting</b>       | Displays the requests that are waiting for the required volume to be mounted.                                                                          |
| <b>MSP Active</b>     | Displays the requests that are being worked on by an MSP.                                                                                              |
| <b>No Drives</b>      | Displays the requests that are waiting because there are no usable drives. (For example, all of the drives may be down.)                               |
| <b>No Tapes</b>       | Displays the requests that are waiting because there are no usable volumes.                                                                            |
| <b>OV Query</b>       | Displays the requests that are waiting for the LS to query OpenVault.                                                                                  |
| <b>Stuck</b>          | Displays the requests that are waiting because of a physical tape that is stuck in the library.                                                        |

| Report Name            | Description                                                                                                                                                                                                                                                                  |
|------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Wait Drive</b>      | Displays the requests that are waiting for a drive. (Usable drives exist, but are unavailable. A drive may be unavailable for a variety of reasons, such as because it is handling another request or because the VG is already using the maximum number of drives allowed.) |
| <b>Wait Drive Type</b> | Displays the requests that are waiting for a drive of the correct type. (Other drives may be available, but are inappropriate.)                                                                                                                                              |
| <b>Wait Host</b>       | Displays the requests that are waiting for the host on which the volume will be mounted.                                                                                                                                                                                     |
| <b>Wait Migrate</b>    | Displays socket merge requests that are waiting for a write child to be started.                                                                                                                                                                                             |
| <b>Wait Mover</b>      | Displays the requests that are waiting for a data-mover process.                                                                                                                                                                                                             |
| <b>Wait Zone</b>       | Displays the requests that are waiting because there is not yet enough migrate data queued to start a mover process.                                                                                                                                                         |

## Composite Reports

The reports listed in Table 17-2 represent states that are compiled by examining multiple tables, rather than states literally reflected in the **Chunk** (`chunk`) and **Request** (`dmn_request`) database tables, as in the detailed summary reports above. Figure 17-2 shows an example **Processing** report.

**Table 17-2** Composite Reports

| Report Name    | Description                                                                                                                                                                                                                                 |
|----------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Blocked</b> | Displays those requests that are currently in the queue but are stopped because an earlier request for the same file is being processed. (A request will be displayed by either the <b>Processing</b> report or the <b>Blocked</b> report.) |
| <b>Merge</b>   | Displays those requests that are currently merging data.                                                                                                                                                                                    |


| Report Name       | Description                                                                                                                                                                                                                                                                                                                        |
|-------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Migrate</b>    | Displays those requests that are in the process of migrating, both explicit requests submitted via the <code>dmput</code> command and requests submitted to <code>dmfdaemon</code> in order to free filesystem space as part of automated space management. The <b>Migrate</b> report is a subset of the <b>Processing</b> report. |
| <b>Pending</b>    | Displays those requests that are in the queue but are waiting to become active. This includes requests that are waiting for a data-mover process, a drive, or a zone to become available. In most cases, the delay is temporary.                                                                                                   |
| <b>Processing</b> | Displays all requests that are working or are waiting for any reason, other than stopped due to a prior request for the same file. (A request will be displayed by either the <b>Processing</b> report or the <b>Blocked</b> report.)                                                                                              |
| <b>Read</b>       | Displays all requests that are processing and currently either reading or queued to read data from LS volumes. Merges are not included in this report.                                                                                                                                                                             |
| <b>Recall</b>     | Displays recall requests from explicit <code>dmget</code> , <code>dmunput</code> , and <code>dmmove</code> commands and kernel <code>krclrea</code> requests to read an offline file. The <b>Recall</b> report is a subset of the <b>Processing</b> report.                                                                        |



| Report Name    | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
|----------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Request</b> | <p>Display all requests to dmfd daemon that have been explicitly requested via the command line or by the kernel. (However, merges do not appear in this report.) The request types are as follows:</p> <ul style="list-style-type: none"><li>• archive puts a file under DMF management by using the dmarchive command</li><li>• backup migrates a file by using the dmput, dmmigrate, or dmfsfree command</li><li>• copy copies a portion of a migrated file to disk by using the dmcop or dmarchive command</li><li>• krclrea recalls an offline file for reading, performed by the kernel</li><li>• krclvoi recalls of an offline file prior to overwriting or truncating, performed by the kernel</li><li>• move moves a migrated file to new MSP or VG by using the dmmove or dmfsfree command</li><li>• recall requests that a file or portion of a file be retrieved by using the dmget command</li><li>• usrvoid retrieves a file and remove it from DMF management by using the dmunput command</li></ul> |
| <b>Write</b>   | <p>Displays all requests for which data-mover processes are currently writing data to volumes, which can be from migrates or merges issued by dmfd daemon or by explicit dmfsfree or dmmove commands. The <b>Write</b> report is a subset of the <b>Migrate</b> report.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |

---

## 17: DMF Queue Viewing



**Figure 17-2 Processing Report**

The report names used by the command line are lowercase (such as `--report processing`). See the `dmqview(8)` man page for details.

## Canceling a Request

To cancel a request, select it and choose **Cancel Request**, as shown in Figure 17-3.

**Note:** Canceling a request refreshes the snapshot. Canceling can also have consequences, such as I/O failures in the application that generated the request. For more information, see the `dmcancel(8)` man page.

The screenshot shows the SGI DMF Manager web interface. The main content area displays a summary for a snapshot taken on 2015-03-20 at 13:51:54+00:00. Below the summary are two bar charts: one for 'Count' and one for 'Bytes (MB)', both showing data for 'Wait Drive', 'Mounting', and 'Active' states. The primary focus is a table of processing requests. The table has columns for Request ID, Type, Priority, BFID, Drive Group, Volume Group, VSN, Source Path, and Destination Path. Request 24525 is selected, and a context menu is open over it, with 'Cancel Request...' highlighted. Other requests in the table include 24527, 24518, 24526, 24528, 24519, 24520, 24521, 24522, 24523, 24524, 24490, and 24494.

| Request ID | Type   | Priority | BFID                     | Drive Group | Volume Group | VSN    | Source Path                | Destination Path                |
|------------|--------|----------|--------------------------|-------------|--------------|--------|----------------------------|---------------------------------|
| 24527      | recall | 666      | 550c029f0000000000001b09 | L001        | L001v6       | C00GBO | /dmfus1/ministim/10Mfile48 |                                 |
| 24518      | recall | 666      | 550c029f0000000000001b00 | L001        | L001v6       | C00GBO | /dmfus1/ministim/10Mfile4  |                                 |
| 24525      | recall | 666      | 550c029f0000000000001b07 | L001        | L001v6       | C00GBO | /dmfus1/ministim/10Mfile46 |                                 |
| 24526      |        |          | 550c029f0000000000001b08 | L001        | L001v6       | C00GBO | /dmfus1/ministim/10Mfile47 |                                 |
| 24528      |        |          | 550c029f0000000000001b0a | L001        | L001v6       | C00GBO | /dmfus1/ministim/10Mfile49 |                                 |
| 24519      | recall | 666      | 550c029f0000000000001b01 | L001        | L001v6       | C00GBO | /dmfus1/ministim/10Mfile40 |                                 |
| 24520      | recall | 666      | 550c029f0000000000001b02 | L001        | L001v6       | C00GBO | /dmfus1/ministim/10Mfile41 |                                 |
| 24521      | recall | 666      | 550c029f0000000000001b03 | L001        | L001v6       | C00GBO | /dmfus1/ministim/10Mfile42 |                                 |
| 24522      | recall | 666      | 550c029f0000000000001b04 | L001        | L001v6       | C00GBO | /dmfus1/ministim/10Mfile43 |                                 |
| 24523      | recall | 666      | 550c029f0000000000001b05 | L001        | L001v6       | C00GBO | /dmfus1/ministim/10Mfile44 |                                 |
| 24524      | recall | 666      | 550c029f0000000000001b06 | L001        | L001v6       | C00GBO | /dmfus1/ministim/10Mfile45 |                                 |
| 24490      | copy   | 555      | 550c029f0000000000001b2a | L001        | L001v7       | C00GCE |                            | /dmfus1/ministim/10Mfile88.copy |
| 24494      | copy   | 555      | 550c029f0000000000001b29 | L001        | L001v7       | C00GCE |                            | /dmfus1/ministim/10Mfile87.copy |
| 24495      | copy   | 555      | 550c029f0000000000001b28 | L001        | L001v7       | C00GCE |                            | /dmfus1/ministim/10Mfile86.copy |

Figure 17-3 Canceling a Request

To cancel a request via the command line, view one of the reports (such as `processing`) to determine the request ID and the `dmfdaemon` PID, and use those as input to the `dmcancel` command. For example, to cancel the processing of the request for `/dmfusrl/ministim/10Mfile46`:

---

**Note:** The examples in this chapter have been adjusted for purposes of display, such as compression of white space and truncation or omission of fields.

---

```
# dmqview -r processing
REPORT: processing DMF Daemon PID: 19352 SNAPSHOT: 2015-03-20 13:51:54+00:00
Line   ReqID   Type    BFID   Priority   VG      VSN      Source Path
  1     24527  recall  550c029f0000000000001b09   666     L001v6  C00GBO  /dmfusrl/ministim/10Mfile48
  2     24518  recall  550c029f0000000000001b00   666     L001v6  C00GBO  /dmfusrl/ministim/10Mfile4
  3     24525  recall  550c029f0000000000001b07   666     L001v6  C00GBO  /dmfusrl/ministim/10Mfile46
  4     24526  recall  550c029f0000000000001b08   666     L001v6  C00GBO  /dmfusrl/ministim/10Mfile47
  5     24528  recall  550c029f0000000000001b0a   666     L001v6  C00GBO  /dmfusrl/ministim/10Mfile49
...
# dmcancel -p 19352 24525
```

For more information, see the `dmcancel(8)` man page.

## Reprioritizing a Request

To reprioritize a request, select it and choose **Change Priority**.

---

**Note:** Reprioritizing a request refreshes the snapshot.

---

To reprioritize a request via the command line, view one of the reports (such as `processing`) to determine the request ID and the `dmfdaemon` PID, and use those as input to the `dmrepri` command. For example, to reprioritize the processing of file `/dmfusrl/ministim/10Mfile49` so that it has the highest priority:

```
# dmqview -r processing
REPORT: processing   DMF Daemon PID: 19352   SNAPSHOT: 2015-03-20 13:51:54+00:00
Line   ReqID   Type    BFID   Priority   VG      VSN      Source Path
  1     24527  recall  550c029f00000000000001b09   666     L001v6  C00GBO  /dmfusrl/ministim/10Mfile48
  2     24518  recall  550c029f00000000000001b00   666     L001v6  C00GBO  /dmfusrl/ministim/10Mfile4
  3     24525  recall  550c029f00000000000001b07   666     L001v6  C00GBO  /dmfusrl/ministim/10Mfile46
  4     24526  recall  550c029f00000000000001b08   666     L001v6  C00GBO  /dmfusrl/ministim/10Mfile47
  5     24528  recall  550c029f00000000000001b0a   666     L001v6  C00GBO  /dmfusrl/ministim/10Mfile49
...
# dmrepri -p 19352 -U 1024 24528
```

For more information, see the `dmrepri(8)` man page.

## Modifying the Report Output

This section discusses the following:


- "Modifying the QView Display" on page 615
- "Modifying the `dmqview` Output" on page 617

## Modifying the QView Display

The reports are based on information gathered from various database tables and fields. You can modify the output of these reports by adding or subtracting the fields shown by selecting the following:

**QView> Show QView Fields**

For example, Figure 17-4 shows the fields available for the **Active** report. Those fields that are checked are shown by default; to modify the report, you can select additional fields or deselect default fields. (For more information about the fields, see "Database Tables and Fields" on page 620.)



**Figure 17-4** Fields Available for Display by a QView **Active** Report

Different reports use different database tables. For example, the above shows that the **Active** report uses the **Request** (dmn\_request), **Connect** (dmn\_connect), and **Chunk** (chunk) tables:

- To remove the **Priority** column from the report, deselect the **Priority** field under **Request**.
- To add the **Host** column, select the **Host** field under **Connect**.
- To apply your changes, click **Apply and Close**.

For details about the available reports, see "Queue Reports" on page 606.

For details about the individual fields, see "Database Tables and Fields" on page 620. This information is also available from the **Help** button on the **QView Fields Dialog** page and from the **What is ...** selection for each column header in the report.

You can also customize the graphical display by using filters, similar to "Filtering Alerts" on page 225.

## Modifying the `dmqview` Output

With the command line, you can use the `--addfields` option to add the specified options or the `--onlyfields` option to restrict the output to only the specified fields. To view all available fields for a given report, use the `--fields` option. (For more details, see "Database Tables and Fields" on page 620.)

You can further control the display with the `--whereorders` option, which lets you modify the PostgreSQL database query. You can include multiple conditions such as `=`, `AND`, `OR`, and `LIKE` (case-insensitive).

For example, the following displays all of the processing requests:

```
# dmqview --report processing
REPORT: processing   DMF Daemon PID: 19352   SNAPSHOT: 2015-03-20 09:16:32+00:00
Line  ReqID  Type      BFID  Priority  VG      VSN      Source Path
  1    1258  backup    550c029f0000000000000657    512    L001v3      /dmfusrl/ministim/10Mfile1
  2    1259  backup    550c029f0000000000000658    512    L001v3      /dmfusrl/ministim/10Mfile10
  3    1274  backup    550c029f0000000000000662    512    L001v5    C00E1G /dmfusrl/ministim/10Mfile3
  4    1275  backup    550c029f0000000000000663    512    L001v5    C00E1G /dmfusrl/ministim/10Mfile30
  5    1287  backup    550c029f000000000000066f    512    L001v6    C00E26 /dmfusrl/ministim/10Mfile41
  6    1289  backup    550c029f0000000000000671    512    L001v6    C00E26 /dmfusrl/ministim/10Mfile43
  7    1334  backup    550c029f0000000000000699    512    L001v8    C00EBN /dmfusrl/ministim/10Mfile9
  8    1335  backup    550c029f000000000000069a    512    L001v8    C00EBN /dmfusrl/ministim/10Mfile90
```

The following displays those requests in VG L001v5 or VG L001v8:

```
# dmqview --report processing --whereorders "(msp_request.vg='L001v5') OR (msp_request.vg='L001v8')"
```

REPORT: processing DMF Daemon PID: 19352 SNAPSHOT: 2015-03-20 09:16:32+00:00

| Line | ReqID | Type   | BFID                      | Priority | VG     | VSN    | Source Path                 |
|------|-------|--------|---------------------------|----------|--------|--------|-----------------------------|
| 1    | 1274  | backup | 550c029f00000000000000662 | 512      | L001v5 | C00E1G | /dmfusrl/ministim/10Mfile3  |
| 2    | 1275  | backup | 550c029f00000000000000663 | 512      | L001v5 | C00E1G | /dmfusrl/ministim/10Mfile30 |
| 3    | 1334  | backup | 550c029f00000000000000699 | 512      | L001v8 | C00EBN | /dmfusrl/ministim/10Mfile9  |
| 4    | 1335  | backup | 550c029f0000000000000069a | 512      | L001v8 | C00EBN | /dmfusrl/ministim/10Mfile90 |

The following displays the requests in LS L00 (BFID output truncated here for purposes of display):

```
# dmqview --report processing --addfields msp_request.ls --whereorders "(msp_request.ls='L00')"
```

REPORT: processing DMF Daemon PID: 19352 SNAPSHOT: 2015-03-20 09:16:32+00:00

| Line | ReqID | Type   | ...BFID | Priority | VG     | VSN    | Source Path                 | LS  |
|------|-------|--------|---------|----------|--------|--------|-----------------------------|-----|
| 1    | 1258  | backup | 5...657 | 512      | L001v3 |        | /dmfusrl/ministim/10Mfile1  | L00 |
| 2    | 1259  | backup | 5...658 | 512      | L001v3 |        | /dmfusrl/ministim/10Mfile10 | L00 |
| 3    | 1274  | backup | 5...662 | 512      | L001v5 | C00E1G | /dmfusrl/ministim/10Mfile3  | L00 |
| 4    | 1275  | backup | 5...663 | 512      | L001v5 | C00E1G | /dmfusrl/ministim/10Mfile30 | L00 |
| 5    | 1287  | backup | 5...66f | 512      | L001v6 | C00E26 | /dmfusrl/ministim/10Mfile41 | L00 |
| 6    | 1289  | backup | 5...671 | 512      | L001v6 | C00E26 | /dmfusrl/ministim/10Mfile43 | L00 |
| 7    | 1334  | backup | 5...699 | 512      | L001v8 | C00EBN | /dmfusrl/ministim/10Mfile9  | L00 |
| 8    | 1335  | backup | 5...69a | 512      | L001v8 | C00EBN | /dmfusrl/ministim/10Mfile90 | L00 |

**Note:** To act on a given field, the field must be present in the report by default or else supplied with the `--addfields` or `--onlyfields` options. Therefore, the above command line adds the `msp_request.ls` field, because it does not appear by default for the processing report).

For more information, see the `psql(1)` man page



## Example of Queue-Related Tasks

**Note:** The output spacing is adjusted and some fields are omitted for purposes of readability in this document.

Suppose that user Jane issued a `dmget` of her offline (OFL) file `/dmfusrl/jane/janefile` and after waiting some time asks the administrator why it has not been recalled yet. You as an administrator could do the following to determine if there is a problem:

1. Log in as root.
2. If there is no recent queue view snapshot, obtain one:

```
# dmqlview --snap
```

3. Display the entire list of requests:

```
# dmqlview --report request
REPORT: request   DMF Daemon PID: 8307   SNAPSHOT: 2015-03-25 17:04:10+00:00
Line ReqID      Type                BFID Priority          Source Path
  1    32  backup 4d9dd513000000000011a1a7    512 /dmfusrl/stim/operator/filevvp1
  2    34  krclrea 4d9dd5130000000000003ce53    512
  3    35  krclrea 4d9dd51300000000000034770    512
  4    36  krclrea 4d9dd51300000000000033ae5    512
  5    38  recall 4d9dd513000000000011a1a3    512 /dmfusrl/bob/bobfile
  6    39  recall 4d9dd513000000000011a1a5    512 /dmfusrl/bob/bobfile2
  7    40  recall 4d9dd513000000000011a1a6    512 /dmfusrl/jane/janefile
```

**Note:** This step is not required, but is included for completeness for this example.

4. Look for Jane's file in the list of requests:

```
# dmqlview --report recall --whereorders "(dmn_request_src_path like '%janefile%')"
REPORT: recall   DMF Daemon PID: 1346   SNAPSHOT: 2015-03-25 15:44:13+00:00
Line ReqID      Type                BFID Priority    VG    VSN          Source Path
  1    439  recall 4d9dd513000000000011a1a6    512 vgc07 C07KC0 /dmfusrl/jane/janefile
```

From the above, you can see that Jane's request will use the volume with volume serial number (VSN) C07KC0, from VG vgc07. This indicates that the request has been sent to a VG.

5. Because the request has been sent to a VG, you can use the `read` report to determine its current status:

```
# dmqlview --report read
REPORT: read   DMF Daemon PID: 8307  SNAPSHOT: 2015-03-25 17:04:10+00:00
Line ReqID    Type ...  VG    VSN      Status      Source Path
  1   38  recall ... vgc07 C07KC0 wait_drive  /dmfusrl/bob/bobfile
  2   39  recall ... vgc07 C07KC0 wait_drive  /dmfusrl/bob/bobfile2
  3   40  recall ... vgc07 C07KC0 wait_drive  /dmfusrl/jane/janefile
  4   34  krclrea ... vgc07 C07FB5 active
  5   35  krclrea ... vgc07 C07CBS active
  6   36  krclrea ... vgc07 C07DAD active
```

The above shows that Jane's request has a status of `wait_drive` (which means that it is waiting for a drive to become available) and that there are two other `recall` requests (`/dmfusrl/bob/bobfile` and `/dmfusrl/bob/bobfile2`) that will use the same volume.

6. To determine the order in which the requests will be recalled when the volume is mounted, you could use the following query:

```
# dmqlview --report read --addfields "chunk.chunk_number,chunk.zone_number,chunk.chunk_length" \
--whereorders "(chunk.vsn='C07KC0')" --sortBy chunk.chunk_number --sortorder ASC
REPORT: read   DMF Daemon PID: 8307  SNAPSHOT: 2015-03-25 17:04:10+00:00
Line ReqID    Type ...  VG    VSN      Status      Source Path ... Chunk Number Zone Number Chunk Length
  1   38  recall ... vgc07 C07KC0 wait_drive  /dmfusrl/bob/bobfile           155           10    70000000
  2   39  recall ... vgc07 C07KC0 wait_drive  /dmfusrl/bob/bobfile2         159           12   200000000
  3   40  recall ... vgc07 C07KC0 wait_drive  /dmfusrl/jane/janefile        161           13    80000000
```

Recall requests on a tape are processed in tape order (starting at the current tape position if the tape is already mounted and recalling files). Tape order is indicated by the chunk number. (If the tape in question was already mounted and doing work, the `Status` output would be `active` and you could use the `dmstat -t` option to determine the zone that is currently being used; zones are processed in tape order.)

## Database Tables and Fields

This section discusses the following:

- "PostgreSQL Database Tables" on page 621

- "Fields for the Chunk Database Table" on page 624
- "Fields for the Connect Database Table" on page 625
- "Fields for the Filesys Database Table" on page 627
- "Fields for the Daemon Request Database Table" on page 626
- "Fields for the Mover Database Table" on page 628
- "Fields for the MSP Request Database Table" on page 629

The table and field names used by the command line are lowercase and a single string and in some cases abbreviated, in the following format:

*tablename.fieldname*

For example, for the daemon request table and destination path:

`dmn_request.dst_path`

See the `dmqview(8)` man page for details.

## PostgreSQL Database Tables

The **QView** reports obtain information from several relational-database tables, depending upon the selected report. Each table has many fields; some fields may appear in multiple tables. Table 17-3 summarizes the database tables.

**Table 17-3** PostgreSQL Database Tables

| PostgreSQL Table | DMF Manager Name | Description                                                                                                                                                                                                                                                                                                                                                                                              |
|------------------|------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| chunk            | <b>Chunk</b>     | Contains one record for each data chunk used for a media-specific process (MSP) or VG request. (Most small files are written as single chunks. When a migrated file cannot fit onto a single volume, the file is split into multiple chunks.) See "Fields for the Chunk Database Table" on page 624.                                                                                                     |
| dmn_connect      | <b>Connect</b>   | Contains one record for each DMF client connection to dmfd daemon, specifying the node and program that made the connection. See "Fields for the Connect Database Table" on page 625.                                                                                                                                                                                                                    |
| dmn_request      | <b>Request</b>   | Contains one record for each request to dmfd daemon that involves data movement. (Multiple dmn_request records may reference a single dmn_connect record, but it is possible for a dmn_connect record to have no corresponding dmn_request record if none of the requests associated with that connection are related to data transfer.) See "Fields for the Daemon Request Database Table" on page 626. |
| filesystem       | <b>Filesys</b>   | Contains a record for each filesystem managed by DMF. See "Fields for the Filesys Database Table" on page 627.                                                                                                                                                                                                                                                                                           |
| globals          | —                | Contains the dmfd daemon process ID, which appears in the header of each report.                                                                                                                                                                                                                                                                                                                         |

---

| PostgreSQL Table          | DMF Manager Name   | Description                                                                                                                                                                                                                                                                                                                           |
|---------------------------|--------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>mover</code>        | <b>Mover</b>       | Contains one record for each read or write data-mover process within a VG. Many chunk records may point to a single <code>mover</code> record. See "Fields for the Mover Database Table" on page 628.                                                                                                                                 |
| <code>mosp_request</code> | <b>MSP Request</b> | Contains one record for each request sent to an MSP/VG. There may be multiple <code>mosp_request</code> records associated with a single <code>dmn_request</code> record. There may be multiple chunk records associated with a single <code>mosp_request</code> record. See "Fields for the MSP Request Database Table" on page 629. |

---

## Fields for the Chunk Database Table

Table 17-4 describes the fields available for the **Chunk** (`chunk`) database table.

**Table 17-4** Chunk Fields

| Field                    | Description                                                                                                                                                                                                                                                                                         |
|--------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>BFID</b>              | The bit-file identifier (BFID) assigned to each file during the migration process, which links a migrated file to its data on alternate media.                                                                                                                                                      |
| <b>Chunk Length</b>      | The length of the chunk, in bytes.                                                                                                                                                                                                                                                                  |
| <b>Chunk Offset</b>      | The byte location in the source file where the data transfer will begin.                                                                                                                                                                                                                            |
| <b>Drive Group</b>       | Name of the DMF drive group that contains the chunk.                                                                                                                                                                                                                                                |
| <b>Daemon Request ID</b> | The ID associated with this chunk by <code>dmfdaemon</code> .                                                                                                                                                                                                                                       |
| <b>File Offset</b>       | Byte offset within the destination file copy where the transfer is to begin. This value will match the <b>Chunk Offset</b> value for all request types except for a request issued by a <code>dmcopy</code> command.                                                                                |
| <b>MSP Request ID</b>    | A number that maps this record in the <code>chunk</code> table to the record in the <code>msp_request</code> table.                                                                                                                                                                                 |
| <b>Start Time</b>        | The time at which the request was received by the VG.                                                                                                                                                                                                                                               |
| <b>Status</b>            | The status of the request. A value of <code>active</code> indicates that the chunk is being processed by a data-mover process; any other value indicates why the request is not currently being processed. These states are reflected in the <b>Summary</b> and its corresponding detailed reports. |
| <b>Mover Type</b>        | The type of data-mover process that will act on this request (either <code>write</code> or <code>read</code> ).                                                                                                                                                                                     |
| <b>Type</b>              | The type of the chunk action (one of <code>merge</code> , <code>migrate</code> , or <code>recall</code> ).                                                                                                                                                                                          |
| <b>Volume Group</b>      | The name of the VG that contains this chunk.                                                                                                                                                                                                                                                        |

| Field              | Description                                                                                                                                                                                                    |
|--------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>VSN</b>         | The volume serial number (VSN) of the volume that contains this chunk. For chunks with a type of <code>migrate</code> , this field will be null until a data-mover process is forked to perform the migration. |
| <b>Zone Number</b> | The zone number within the volume (specified by the <b>VSN</b> field) where the chunk resides.                                                                                                                 |

## Fields for the Connect Database Table

Table 17-5 describes the fields for the **Connect** (`dmn_connect`) database table.

**Table 17-5** Connect Fields

| Field               | Description                                                                                                                                 |
|---------------------|---------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Connect ID</b>   | The connection ID number used to map <code>dmn_connect</code> and <code>dmn_request</code> records to the connection by which they arrived. |
| <b>CPU Type</b>     | The CPU architecture of the host that is running the program that created this connection (specified by the <b>Logical Name</b> field).     |
| <b>Host</b>         | The hostname where the program is running.                                                                                                  |
| <b>Instance</b>     | The instance ID of the program. (Normally, a process will only maintain one connection instance to <code>dmfdaemon</code> .)                |
| <b>Locale</b>       | The language being used by the program, as output by the Linux <code>locale(1)</code> command (such as <code>en_US.UTF-8</code> ).          |
| <b>Logical Name</b> | The program that created this connection to <code>dmfdaemon</code> (such as <code>/usr/bin/dmget</code> ).                                  |
| <b>OS Type</b>      | The operating system on the host where the program is running.                                                                              |
| <b>OS Version</b>   | The operating system version on the host where the program is running.                                                                      |

| Field               | Description                                                                                                                                                                                                                       |
|---------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Product Name</b> | The name and version of the software product of which the program is a member.                                                                                                                                                    |
| <b>SOAP User</b>    | True (t) if this connection was made using SOAP; in this case, the <b>User UID</b> and <b>User GID</b> will be the user ID and group ID of the user who executed the SOAP request. If SOAP was not used, this value is false (f). |
| <b>User GID</b>     | The group ID of the process that initiated the program.                                                                                                                                                                           |
| <b>User PID</b>     | The process ID of the process that initiated the program.                                                                                                                                                                         |
| <b>User UID</b>     | The user ID of the process that initiated the program.                                                                                                                                                                            |

### Fields for the Daemon Request Database Table

Table 17-6 describes the fields available for the **Daemon Request** (`dmn_request`) database table.

**Table 17-6** Daemon Request Fields

| Field                    | Description                                                                                                                                    |
|--------------------------|------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>BFID</b>              | The BFID for the requested file.                                                                                                               |
| <b>Client Request ID</b> | The client's request ID if this request arrived via a client connection (this field will be null for kernel requests).                         |
| <b>Connect ID</b>        | A number that maps this record in the <code>dmn_connect</code> table to the record in the <code>dmn_request</code> table.                      |
| <b>Destination Path</b>  | The destination path where the file is being transferred. This will be null except for copy and archive requests.                              |
| <b>File GID</b>          | The group ID of the owner of the file in the DMF-managed filesystem. (This field may be null depending upon the current state of the request.) |
| <b>File UID</b>          | The user ID of the owner of the file in the DMF-managed filesystem. (This field may be null depending upon the current state of the request.)  |



| Field               | Description                                                                                                                                                                                                 |
|---------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Fhandle</b>      | Handle for the file on which this request is based.                                                                                                                                                         |
| <b>Fshandle</b>     | Handle for the filesystem in which the file resides.                                                                                                                                                        |
| <b>Priority</b>     | Priority of the request, in the range 1 (lowest priority) through 1024 (highest priority). The default priority is 512.                                                                                     |
| <b>Request ID</b>   | The daemon request ID.                                                                                                                                                                                      |
| <b>Request Type</b> | The daemon request type.                                                                                                                                                                                    |
| <b>Source Path</b>  | The pathname of the file that is the basis of the request. (Note, this will be null for kernel <code>krclrea</code> and <code>krclvoi</code> requests because pathnames are not available from the kernel.) |
| <b>Start Time</b>   | The time at which this request was received by <code>dmfdaemon</code> .                                                                                                                                     |
| <b>Status</b>       | The status of this request, either <code>active</code> (displayed by the <b>Processing</b> report) or <code>blocked</code> (displayed by the <b>Blocked</b> report)                                         |

## Fields for the Filesys Database Table

Table 17-7 describes the fields available for the **Filesys** (`filesys`) database table.

**Table 17-7** Filesys Fields

| Field              | Description                                                                                                                                                                                                        |
|--------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Device</b>      | The device number ( <code>dev_t</code> ) for the filesystem.                                                                                                                                                       |
| <b>Device Name</b> | The device pathname for the filesystem. This could be in any of the following forms:<br><br><code>/dev/lxvm/<i>name</i></code><br><code>/dev/cxvm/<i>name</i></code><br><code>/dev/xvm-<i>N</i>/<i>name</i></code> |
| <b>Directory</b>   | The mount point for the filesystem.                                                                                                                                                                                |
| <b>Fshandle</b>    | The fhandle for the filesystem.                                                                                                                                                                                    |
| <b>FS Type</b>     | The filesystem type.                                                                                                                                                                                               |

## Fields for the Mover Database Table

Table 17-8 describes the fields available for the **Mover** (`mover`) database table.

**Table 17-8** Mover Fields

| Field               | Description                                                                                                                                                                                                                                                                                                                                                       |
|---------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Drive Group</b>  | The DMF drive group that contains the volume.                                                                                                                                                                                                                                                                                                                     |
| <b>Drive</b>        | The drive used for the mount. This will be null for data-mover processes with a status other than <code>active</code> .                                                                                                                                                                                                                                           |
| <b>Host</b>         | The host on which the volume will be mounted. This will be null for data-mover processes with a status other than <code>active</code> .                                                                                                                                                                                                                           |
| <b>Position</b>     | For data-mover processes in <code>pending</code> status, this is the relative position of the mover in the queue. For other status types, this field will be null.                                                                                                                                                                                                |
| <b>Priority</b>     | Priority of the highest-priority request assigned to the data-mover process for the volume, in the range 1 (lowest priority) through 1024 (highest priority). The default priority is 512. (If a data-mover process is using a tape and is at end-of-volume, it has a null priority.)                                                                             |
| <b>Status</b>       | The status of the request. A value of <code>active</code> indicates that the mover is processing the chunks assigned to it; any other value indicates why the request is not currently being processed. Only the <code>active</code> status is used for write movers because they are not created until both a volume and a drive are available at the same time. |
| <b>Type</b>         | The type of data-mover process, either <code>read</code> or <code>write</code> .                                                                                                                                                                                                                                                                                  |
| <b>Volume Group</b> | The VG that contains the volume.                                                                                                                                                                                                                                                                                                                                  |
| <b>VSN</b>          | VSN of the volume                                                                                                                                                                                                                                                                                                                                                 |

## Fields for the MSP Request Database Table

Table 17-9 describes the fields available for the **MSP Request** (`msp_request`) database table.

**Table 17-9** MSP Request Fields

| Field                         | Description                                                                                                                                              |
|-------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Daemon Request ID</b>      | The daemon request ID that created this MSP request.                                                                                                     |
| <b>Library Server</b>         | The LS associated with this request. For a disk MSP or a DCM MSP, this will be null.                                                                     |
| <b>MSP Destination Offset</b> | The byte location in the file where recalled data will be written. This field is only used for copy daemon requests and will be null in all other cases. |
| <b>MSP Key</b>                | The string used to identify the MSP/VG copy to be used for the recall. For migrate requests, this field will be null.                                    |
| <b>MSP Length</b>             | Length of the data transfer. For migrate requests, this will always match the file's length.                                                             |
| <b>MSP Request ID</b>         | A number that maps this record in the <code>msp_request</code> table to the <code>chunk</code> table.                                                    |
| <b>MSP Request Type</b>       | The type of this request, either <code>migrate</code> or <code>recall</code> .                                                                           |
| <b>MSP Source Offset</b>      | The byte location in the file where the data transfer will begin. For migrate requests, this will always be 0.                                           |
| <b>Priority</b>               | Priority of the request, in the range 1 (lowest priority) through 1024 (highest priority). The default priority is 512.                                  |
| <b>Volume Group</b>           | The VG associated with this request.                                                                                                                     |
| <b>Start Time</b>             | The time at which this request was sent to the MSP/VG.                                                                                                   |



## SGI LTFS

This chapter discusses the SGI Linear Tape File System (LTFS):

- "SGI LTFS Features" on page 631
- "SGI LTFS Requirements" on page 632
- "Best Practices for SGI LTFS" on page 632
- "SGI LTFS Configuration" on page 633
- "`sgi-ltfs` Command Examples" on page 637

Also see "LTFS in DMF Manager" on page 263.

### SGI LTFS Features

LTFS lets you access tape media with an interface that behaves like a hard disk. The content of an LTFS tape appears to users as a disk directory listing, which is easy to use with standard file operations. Because it is a tape format standard, LTFS lets you share data across platforms, similar to using a USB drive or memory stick.

SGI LTFS software provides LTFS capability for the following:

- Tapes: Ultrium5-1500, Ultrium6-2500, T10000T2
- Drives: LTO-5, LTO-6, T10000C, T10000D

SGI LTFS lets you do the following:

- Show information about LTFS cartridges/drives and configuration.
- Import new cartridges into the LTFS group.
- Format, mount, or unmount the LTFS on the imported cartridges.
- Eject a cartridge from a library managed by OpenVault.
- Reserve a drive exclusively for LTFS use.
- Borrow the drive from a drive group that belongs to another application, and then return the drive group after the operation completes. For example, you can

configure SGI LTFS so that it may temporarily borrow a drive from certain DMF drive groups. If an operation is issued when no drives in the reserved group are available, SGI LTFS will find a compatible drive in the list of specified DMF drive groups; after the operation completes, it will return the drive to DMF.

- Purge a cartridge record in the OpenVault catalog.
- Check an LTFS cartridge consistency.

## SGI LTFS Requirements

SGI LTFS is installed by the `sgi-ltfs` package. It is implemented based on HP LTFS 2.0.0.0 and is GPL licensed. It requires the OpenVault mounting service and runs on the host that is the OpenVault server. The drives to be used by LTFS must be accessible from the OpenVault server.

## Best Practices for SGI LTFS

This section discusses the following:

- "Avoid Parallel Use" on page 632
- "Verify Copies are Present Before Deleting Originals" on page 632
- "Ensure that Files are Online Before Copying to LTFS" on page 633

### Avoid Parallel Use

A tape drive provides sequential-access storage. For best performance, only one user/process should access a given LTFS tape at any point in time; multiple users/processes accessing in parallel will result in poor performance.

### Verify Copies are Present Before Deleting Originals

When you copy files to an LTFS filesystem, the data is held in filesystem cache until a sufficient amount is present; at that point, the data is copied to tape. If an error is present, it will not occur until the write to tape actually takes place. Therefore, you should always use the `ls(1)` command to verify that files are present in the LTFS filesystem before removing the original files.

## Ensure that Files are Online Before Copying to LTFS

You should ensure that files are online (that is, regular or dual-state) before copying them to LTFS. For example, you could use the following `dmget(1)` command to ensure that all of the files in `/mydir` are online:

```
# find /mydir -type -f print | dmget -a
```

After this completes, you can use the `cp(1)` command or any drag-and-drop interface to copy the online files from the filesystem managed by DMF to the LTFS filesystem.

---

**Note:** Recalling offline files before using drag-and-drop will make the copy process more efficient.

---

## SGI LTFS Configuration

This section discusses the following:

- "sgi-ltfs.conf File Format" on page 633
- "sgi-ltfs.conf Parameters" on page 634
- "sgi-ltfs.conf Examples" on page 635

### sgi-ltfs.conf File Format

The `/etc/sgi-ltfs.conf` file contains configuration parameters and their values. You can modify the file directly or by using the DMF Manager interface (see "LTFS in DMF Manager" on page 263). This file will be preserved when SGI LTFS is updated to a newer version.

The file consists of ASCII case-sensitive strings separated by white space in the following format:

```
PARAMETER_NAME      value
```

The `#` character indicates that the remainder of a line is a comment.

---

**Note:** Only comments in the leading comment block will be preserved when configuring with DMF Manager.

---

Most parameters have default values. The order in which parameters are listed is not important.

### **sgi-ltfs.conf Parameters**

The `/etc/sgi-ltfs.conf` file can contain the following parameters:

**BORROW\_FROM\_DG** Specifies a comma-separated list of one or more OpenVault drive groups that are owned by another application (such as DMF) from which LTFS may borrow drives. This parameter optionally also specifies the maximum number of drives that may be borrowed from the drive groups. The syntax is as follows (note that there is no space after the comma):

*name1[ , name2 . . . ] [ max\_drives ]*

You can include multiple instances of this parameter in order to specify different maximum numbers of drives for different sets of drive groups; the *max\_drives* value applies to each drive group listed for a given `BORROW_FROM_DG` parameter. The default for *max\_drives* is 1.

If you do not specify the parameter, LTFS will not borrow any drives and will use drives only from the drive group specified for `LTFS_DRIVE_GROUP`.

**LTFS\_CART\_GROUP** Specifies the single OpenVault cartridge group to be reserved for use by LTFS. The default is `ltfs_carts`.

**LTFS\_DRIVE\_GROUP** Specifies the single OpenVault drive group to be reserved for use by LTFS. The `sgi-ltfs` command will create this drive group for you if it does not already exist. The default is `ltfs_dg`.



**Caution:** After you have configured LTFS, you should be careful if you change this parameter. If you redefine this parameter but the old drive group is not empty, the drives in the old group will be unavailable to the `sgi-ltfs` command.

---



|                 |                                                                                                                                                                                                                                                                          |
|-----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| LTFS_MAX_DRIVES | Specifies the maximum number of drives that can be in the drive group specified by <code>LTFS_DRIVE_GROUP</code> at any given time. The default is 2.                                                                                                                    |
| LTFS_MOUNT_ROOT | Specifies the path that will be added to the tape name to form the mount point of the LTFS filesystem. The default is <code>/dmf/ltfs</code> . For example, an LTFS filesystem for tape <code>vsn123</code> will be mounted as <code>/dmf/ltfs/vsn123</code> by default. |
| LTFS_OV_KEYFILE | Specifies the path to the keyfile used by LTFS when connecting to the OpenVault server. The default is <code>/dmf/home/ltfs_keys</code> .                                                                                                                                |
| OV_SERVER       | Specifies the name associated with the IP address on which the OpenVault server is listening. The default is the hostname where you run the <code>sgi-ltfs</code> command.                                                                                               |

### **sgi-ltfs.conf Examples**

This section discusses the following:

- "Borrowing Drives (Simple)" on page 635
- "Borrowing Drives (More Complex)" on page 636
- "Using the LTFS Drive" on page 636

#### **Borrowing Drives (Simple)**

The following example uses default values for most of the parameters but permits up to two drives to be borrowed from the `dg1` drive group, which is owned by another application:

```
BORROW_FROM_DG    dg1
```

### Borrowing Drives (More Complex)

The following example borrows drives, using a more complex scenario:

```
OV_SERVER      my_host
LTFS_CART_GROUP    my_ltfs_cart_group
LTFS_DRIVE_GROUP  my_ltfs_dg
LTFS_MAX_DRIVES    3
LTFS_MOUNT_ROOT   /usr/ltfs
LTFS_OV_KEYFILE   /somewhere/ltfs_keys
BORROW_FROM_DG    dg1,dg2
BORROW_FROM_DG    dg3 3
BORROW_FROM_DG    dg4,dg5 2
```

The above example shows the following:

- The name of the OpenVault server is `my_host`
- The OpenVault cartridge group `my_ltfs_cart_group` and up to three drives in the OpenVault drive group `my_ltfs_dg` will be reserved for LTFS use
- The OpenVault keyfile is `/somewhere/ltfs_keys`
- The mount point of the LTFS filesystem will begin with `/usr/ltfs`
- In addition to the drives reserved above for LTFS use in `my_ltfs_dg`, LTFS can borrow drives that are normally managed by DMF as follows, up to a maximum of three borrowed drives total:
  - One drive (the default) from `dg1` or `dg2`
  - Three drives from `dg3`
  - Two drives from `dg4` or `dg5`

For example, LTFS could borrow two drives from `dg4` and one drive from `dg5`

### Using the LTFS Drive

The following example is similar, except that it will use the host where `sgi-ltfs` is executed as the OpenVault server and it will not borrow any drives (because there is

no `BORROW_FROM_DG` parameter). It will also use the default maximum of two drives from the `my_ltfs_dg` drive group:

```
LTFS_CART_GROUP      my_ltfs_cart_group
LTFS_DRIVE_GROUP    my_ltfs_dg
LTFS_MOUNT_ROOT     /usr/ltfs
LTFS_OV_KEYFILE     /somewhere/ltfs_keys
```

## sgi-ltfs Command Examples

This section discusses the following:

- "Reading an LTFS Tape" on page 637
- "Reserving a Drive and Preparing a New LTFS Tape" on page 638
- "Reading a T10000C-Formatted Tape on a T10000D Drive" on page 639
- "Reformatting a T100002 Tape" on page 639

For details about the `sgi-ltfs(8)` command, see the man page.

## Reading an LTFS Tape

To read an LTFS tape that contains data, do the following:

1. Import the tape with physical cartridge label `PCL22` to the LTFS group, which also requires that you specify the cartridge-type name:

For example, for a tape named of type `T10000T2`:

```
# sgi-ltfs -i PCL22 -T T10000T2
```

2. Mount the tape as an LTFS filesystem:

```
# sgi-ltfs -m PCL22
```

If no suitable drive is found in the LTFS group, `sgi-ltfs` will search drive groups that belong to other applications if they are listed as values for the `BORROW_FROM_DG` parameter in the `/etc/sgi-ltfs.conf` file (see "sgi-ltfs.conf Parameters" on page 634). By default, the filesystem will be mounted as `/dmf/ltfs/PCL22`.

3. Copy files from the tape:

```
# cp /dmf/ltfs/PCL22/* /my_dir
```

4. Unmount the filesystem:

```
# sgi-ltfs -u PCL22
```

If the drive was borrowed, it will be returned to the original drive group.

## Reserving a Drive and Preparing a New LTFS Tape

To reserve `drive2` that belongs to DMF and prepare a new LTFS tape, do the following:

1. Ensure that `drive2` is in one of the drive groups listed for the `BORROW_FROM_DG` parameter in the `/etc/sgi-ltfs.conf` file (see "sgi-ltfs.conf Parameters" on page 634).

2. Reserve the drive:

```
# sgi-ltfs -r drive2
```

3. Format the tape named `PCL33`:

```
# sgi-ltfs -f PCL33 -d drive2
```

4. Mount the tape:

```
# sgi-ltfs -m PCL33 -d drive2
```

5. Copy data to the tape:

```
# cp my_dir/* /dmf/ltfs/PCL33
```

6. Make sure that the files are on the tape:

```
# ls /dmf/ltfs/PCL33
```

7. Unmount the tape:

```
# sgi-ltfs -u PCL33
```

8. Eject the tape from the library:

```
# sgi-ltfs -e PCL33
```

9. Purge the tape information in the OpenVault system:

```
# sgi-ltfs -p PCL33
```

At this point, the tape can be reused.

### Reading a T1000C-Formatted Tape on a T1000D Drive

A tape formatted on a T1000C drive can be mounted read-only (using the `-n` option) on a T1000D drive.

---

**Note:** A tape formatted on a T1000D drive cannot be mounted on T1000C drive.

---

For example, suppose that the tape named `PCL33` was formatted on a T1000C drive. To mount it on a T1000D drive, enter the following:

```
# sgi-ltfs -m PCL33 -d t10kd -n
```

### Reformatting a T10002 Tape

To reformat a T10002 tape, specify the compatible drive and the force option (`-o` or `--force`). For example, if you want to change `PCL33` from T1000C-format to T1000D-format:

```
# sgi-ltfs -f PCL33 -d t10kd -o
```



## Troubleshooting

This chapter contains the following:

- "Replacing a Bad DMF Copy with a Good DMF Copy" on page 642
- "Restoring Files from Backups" on page 643
- "Recovery and Restoration of DMF Database" on page 646
- "Backup Consistency Errors" on page 650
- "Disaster Recovery Procedures" on page 650
- "Filesystem Errors" on page 658
- "Unable to Use the `dmi` Mount Option" on page 660
- "EOT Error" on page 660
- "Tape Drive Not Claimed by `ts`" on page 660
- "Drive Entry Does Not Correspond to an Existing Drive (OpenVault)" on page 660
- "Drive Does Not Exist (TMF)" on page 661
- "No Usable Drives" on page 661
- "DMF Manager Errors" on page 666
- "Delay In Accessing Files in an SMB/CIFS Network Share" on page 668
- "Operations Timeout or Abort on Windows" on page 669
- "Windows Explorer Hangs" on page 669
- "Poor Migration Performance" on page 669
- "Poor Recall Performance" on page 669
- "Remote Connection Failures" on page 670
- "yast2 Disk Space Warning" on page 670
- "Linux CXFS Clients Cannot Mount Managed Filesystems" on page 670
- "Mount Errors for a Drive" on page 671

- "Verifying the Integrity of Library Server Volumes" on page 672
- "dmemptytape Process Did Not Complete" on page 674
- "DMF Database Server Startup Issues" on page 674
- "Using SGI Knowledgebase" on page 675
- "Reporting Problems to SGI" on page 675

Also see the troubleshooting chapter of the *DMF 6 Client Guide for Windows Systems*.

## Replacing a Bad DMF Copy with a Good DMF Copy

If there are multiple copies of a file on secondary storage and one of them becomes corrupted, you can replace the corrupt copy with a good copy by using the `dmmove(8)` command. You can do this by supplying any of the following via standard input:

- The file handle
- BFID (by adding the `-b` option)
- Pathname (by adding the `-p` option)

For example, suppose that the copy of `/dmfusrl/myfile` has been corrupted on volume group `vg1`, but there is a good copy on `vg2`. You would do the following:

1. Delete (`-d`) the bad copy from `vg1` and retain the good copy on `vg2` (using `-p` to specify the file by its pathname supplied by standard input):

```
# echo "/dmfusrl/myfile" | dmmove -d vg1 -p vg2
```

2. Delete no copies, place a good copy on `vg1`, and retain the good copy on `vg2`:

```
# echo "/dmfusrl/myfile" | dmmove -d none -p vg1 vg2
```

---

**Note:** Using best practices, you should always explicitly state all of the MSPs/VGs from which a copy should be deleted (`none` in this case) and all of the MSPs/VGs into which a copy should be placed/retained. In this case, you must include `vg2` on the command line in order to retain the copy on `vg2`.

---

For more information, see the `dmmove(8)` and `dmattr(8)` man pages.



## Restoring Files from Backups

This section discusses the following:

- "Overview of Restoring Files" on page 643
- "Ensuring Accuracy with `xfsdump`" on page 645
- "Backing Up and Restoring Files without the DMF Scripts" on page 645
- "Filesystem Consistency with `xfsrestore`" on page 646

### Overview of Restoring Files

To restore files, use the `xfsrestore(8)` command or the **Recovery** tab in DMF Manager; see "Restoring Filesystems in DMF Manager" on page 255.

---

**Note:** The `xfsrestore` command may attempt to read, write, or delete files that are under DMF management. If this occurs while DMF is not running, the `xfsrestore` process may block indefinitely waiting for a DMF event to be completed. If you use `xfsrestore` to create or modify files in a filesystem that already contains files managed by DMF, you are more likely to encounter this issue than if you use `xfsrestore` to populate an empty filesystem. To avoid this problem, use `xfsrestore` while DMF is running.

---

The `xfsdump(8)` and `xfsrestore(8)` commands back up filesystems. These utilities are designed to perform the backup function quickly and with minimal system overhead. They operate with DMF in two ways:

- When `xfsdump` encounters an offline file, it does not cause the associated data to be recalled. This distinguishes the utility from `tar(1)` and `cpio(1)`, both of which cause the file to be recalled when they reference an offline file.
- The `dmmigrate(8)` command lets you implement a 100% migration policy that does not interfere with customary management of space thresholds.

The `xfsdump` command supports the `-a` option specifically for DMF. If you specify the `-a` option, `xfsdump` will back up DMF dual-state (DUL) files as if they were offline (OFL) files. That is, when `xfsdump` detects a file that is backed up by DMF, it retains only the inode for that file because DMF already has a copy of the data itself. This dramatically reduces the amount of space needed to back up a filesystem and it also reduces the time taken to complete the backup, thereby

minimizing the chances of it being inaccurate due to activity elsewhere in the system. An added advantage of using `-a` is that files that are actively being recalled will still be backed up correctly by `xfsdump` because it does not need to copy the file's data bytes to secondary storage.

You can also use `dmmigrate` to force data copies held only in a disk cache manager (DCM) MSP cache to be copied to tapes/MAID in the underlying volume groups (VGs). This removes the need to back up the cache filesystem.

Most installations periodically do a full (level 0) backup of filesystems. Incremental backups (levels 1 through 9) are done between full backups; these may happen once per day or several times per day. You can continue this practice after DMF is enabled. When a file is migrated (or recalled), the inode change time is updated. The inode change time ensures that the file gets backed up at the time of the next incremental backup.

To automatically manage backup media, DMF includes configurable administrative scripts called `run_full_dump.sh` and `run_partial_dump.sh`, which employ `xfsdump` to backup to tape or disk. The scripts perform the following actions:

- *(optional)* Migrates all eligible files to dual-state
- *(optional)* Copies all eligible DCM MSP files on a DCM MSP system to dual-residency state
- Performs a database snapshot using `dmsnap`
- Backs up the directory containing that snapshot
- Backs up other filesystems
- After a successful full backup, frees up old backup media and disk space for future reuse

DMF also supports a matching wrapper around `xfrestore` named `dmxfrestore` to be used when restoring files that were backed up by these scripts. See the `dmxfrestore(8)` man page for more information on running the command.

You can configure tasks in the `dump_tasks` object to automatically do full and incremental backups of the managed filesystems. See "taskgroup Object" on page 304 for more information.

For more information about parameters, see "Starting and Stopping the DMF Environment" on page 181.

Sites using OpenVault can add new backup media by using `dmov_makecarts` and/or `dmov_loadtapes` by providing the name of the task group as a parameter. Sites using TMF do not need any special steps to add new tapes, as TMF does not record details of which tapes are available to it.

Recycling old backup media is performed automatically after the successful completion of a full backup. In certain situations, such as running out of backup media, this pruning must be done manually by running `dmxfsprune`.

### Ensuring Accuracy with `xfsdump`

The `xfsdump` program is written such that it assumes backups will only be taken within filesystems that are not actively changing. `xfsdump` cannot detect that a file has changed while it is being backed up, so if a user should modify a file while it is being read by `xfsdump`, it is possible for the backup copy of the file to be inaccurate.

To ensure that all file backup copies are accurate, perform the following steps when using `xfsdump` to back up files within a DMF filesystem:

1. Make sure that there is no user activity within the filesystem.
2. Ensure that DMF is not actively migrating files within the filesystem.
3. Run `xfsdump`, preferably with the `-a` option.

### Backing Up and Restoring Files without the DMF Scripts

If you choose to back up and restore DMF filesystems without using the provided DMF scripts, there are several items that you must remember:

- The DMF scripts use `xfsdump` with the `-a` option to back up only data not backed up by DMF. You may also wish to consider using the `-a` option on `xfsdump` when backing up DMF filesystems manually.
- **Do not use the `-A` option** on either `xfsdump` or `xfrestore`. The `-A` option avoids backing up or restoring extended attribute information. DMF information is stored within files as extended attributes, so if you do use `-A`, migrated files restored from that backup media will not be recallable by DMF.
- When restoring migrated files using `xfrestore`, you must specify the `-D` option in order to guarantee that all information related to DMF is correctly restored.

## Filesystem Consistency with `xfstrestore`

When you restore files, you might be restoring some inodes containing BFIDs that were soft-deleted since the time the backup was taken. (For information about soft-deletes, see "Cleaning Up Obsolete Database Entries" on page 586.) `dmaudit(8)` will report this as an inconsistency between the filesystem and the daemon database, indicating that the database entry should not be soft-deleted.

Another form of inconsistency occurs if you happen to duplicate offline or dual-state files by restoring all or part of an existing directory into another directory. In this case, `dmaudit` will report as an inconsistency that two files share the same BFID. If one of the files is subsequently deleted causing the database entry to be soft-deleted, the `dmaudit`-reported inconsistency will change to the type described in the previous paragraph.

While these `dmaudit`-reported inconsistencies may seem serious, there is no risk of losing user data. The `dmhdelete(8)` program responsible for removing unused database entries always first scans all managed filesystems to make sure that there are no remaining files that reference the database entries it is about to remove. It is able to detect either of these inconsistencies and will not remove the database entries if inconsistencies are found.

Be aware that inconsistencies between a filesystem and the daemon database can occur as a result of restoring migrated files. It is good practice to run `dmaudit` after every restore to correct those inconsistencies.

## Recovery and Restoration of DMF Database

The basic strategy for recovering a lost or damaged DMF database is to recreate it by applying journal records to a backup copy of the database. For this reason it is essential that database backup copies and journal files reside on a different physical device from the production databases; it is also highly desirable that these devices have different controllers and channels. The following sections discuss the database recovery strategy in more detail:

- "Database Backups" on page 647
- "Database Recovery Procedure" on page 647
- "Database Restore Procedure for Integrated Backups" on page 650

## Database Backups

You can configure commands in the `run_copy_databases.sh` task (in the `dump_tasks` object) to automatically generate DMF database backups. See "taskgroup Object" on page 304, for more information.

You must back up the following files:

- The daemon database files and definition file in the `HOME_DIR/daemon_name` directory:

```
dbrec.dat
dbrec.keys
pathseg.dat
pathseg.keys
dmd_db.dbd
```

Each LS database has the following files in the `HOME_DIR/ls_name` directory:

- CAT records:

```
tpcrdm.dat
tpcrdm.key1.keys
tpcrdm.key2.keys
```

- VOL records:

```
tpvrdm.dat
tpvrdm.vsn.keys
```

- Database definition file: `libsrv_db.dbd`

## Database Recovery Procedure

---

**Note:** You can also recover the database from a dump available in the **Available Dumps (Integrated Method)** pane in the **Recovery** tab of DMF Manager. See "Restore a Filesystem Component (Integrated Backups)" on page 255.

---

The DMF daemon and LS write journal file records for every database transaction. These files contain binary records that cannot be edited by normal methods and that must be applied to an existing database with the `dmdbrecover(8)` command. The following procedure explains how to recover the daemon database.



---

**Warning:** If you are running on multiple LSs, always ensure that you have the correct journals restored in the correct directories. Recovering a database with incorrect journals can cause irrecoverable problems.

---

**Procedure 19-1** Recovering the Databases

If you lose a database through disk spindle failure or through some form of external corruption, use the following procedure to recover it:

1. Ensure that DMF is stopped. In a high-availability (HA) environment, see *High Availability Guide for SGI InfiniteStorage*. In a non-HA environment, execute the following:

```
# service dmf stop
```

2. Do one of the following depending upon your circumstances:
  - If you have configured the `run_copy_databases` task, restore the files from the directory with the most recent copy of the databases that were in `HOME_DIR` to `HOME_DIR/daemon` or `HOME_DIR/LS_NAME`.
  - If you have **not** configured the `run_copy_databases` task, reload an old version of the daemon or LS database. Typically, these will be from the most recent dumps of your filesystem.
3. Ensure that the default `JOURNAL_DIR/daemon_name` (or `JOURNAL_DIR/ls_name`) directory contains all of the time-ordered journal files since the last update of the older database.

For the daemon, the files are named `dmd_db.yyyymmdd[.hhmmss]`.

For the LS, the journal files are named `libsrv_db.yyyymmdd[.hhmmss]`.

4. Use `dmdbrecover` to update the old database with the journal entries from journal files identified in step 3. The following commands result in the recovery of the daemon and library server databases, assuming the backup copy of the databases and the journals exist as specified by `/etc/dmf/dmf.conf`:

```
# dmdbrecover -n daemon_name dmd_db
# dmdbrecover -n ls_name libsrv_db
```

---

**Note:** This process may take several hours to complete.

---

**Example 19-1** Database Recovery

Suppose that the filesystem containing *HOME\_DIR* was destroyed on February 1, 2004, and that your most recent backup copy of the daemon database and LS database is from January 28, 2004. To recover the databases, you would do the following:

1. Stop DMF (in a non-HA environment):

```
# service dmf stop
```

2. Ensure that *JOURNAL\_DIR/daemon\_name* (or *JOURNAL\_DIR/ls\_name*) contains the following journal files (one or more for each day):

*JOURNAL\_DIR/daemon\_name*

```
dmd_db.20040128.235959
dmd_db.20040129.235959
dmd_db.20040130.235959
dmd_db.20040131.235959
dmd_db.20040201
```

*JOURNAL\_DIR/ls\_name*

```
libsrv_db.20040128.235959
libsrv_db.20040129.235959
libsrv_db.20040130.235959
libsrv_db.20040131.235959
libsrv_db.20040201
```

3. Restore databases from January 28, to *HOME\_DIR/daemon\_name* and/or *HOME\_DIR/ls\_name*. The following files should be present:

*HOME\_DIR/daemon\_name*

```
dbrec.dat
dbrec.keys
pathseg.dat
pathseg.keys
```

*HOME\_DIR/ls\_name*

```
tpcrdm.dat
tpcrdm.key1.keys
tpcrdm.key2.keys
tpvrdm.dat
```

```
tpcrdm.vsn.keys
```

4. Update the database files created in the step 3 by using the following commands, assuming that the name of the daemon database is `daemon` and the name of the library server is `ls`, as defined in `/etc/dmf/dmf.conf`:

```
# dmdbrecover -n daemon dmd_db
# dmdbrecover -n ls libsrv_db
```

---

**Note:** This process may take several hours to complete.

---

## Database Restore Procedure for Integrated Backups

If you are using the integrated backup method, you can restore the DMF database from an online dump file. Select the most current dump file from the list under **Available Dumps (Integrated Method)** and select **Restore databases**. (You can also select an older database dump file and replay the journals.) For more information, see "Restore a Filesystem Component (Integrated Backups)" on page 255.

However, if no dump containing a good database is available, see "Disaster Recovery Procedures" on page 650.

## Backup Consistency Errors

If a full or incremental backup produces consistency errors, you can run the `run_full_dump.sh` script manually with the appropriate arguments to prune orphaned filesystem dumps and orphaned inventory entries. See "run\_full\_dump.sh" on page 142.

## Disaster Recovery Procedures

If the DMF database is lost or corrupt and the latest database backup file residing in the backup filesystem becomes inaccessible, you must first restore access to the backup filesystem and subsequently the DMF database to restore the server.

This section discusses the following:

- "Disaster Recovery for Basic DMF without HA" on page 651



- "Disaster Recovery for Parallel DMF" on page 655
- "Disaster Recovery for DMF with HA" on page 657

## Disaster Recovery for Basic DMF without HA

---

**Note:** If a good copy of the DMF database is available from a dump file, see "Database Restore Procedure for Integrated Backups" on page 650.

---

If you are using the integrated backup method and basic DMF in a non-HA environment, you can use DMF Manager to perform disaster recovery.

You can use the following menu in DMF Manager:

**Recovery**  
    > **Disaster Recovery**

The above menu opens the **Disaster Recovery** dialog shown in Figure 19-1.

## 19: Troubleshooting

The screenshot displays the sgi DMF™ Manager web interface. A modal window titled "Disaster Recovery" is open, showing the status of various components. Below this, a table titled "Status of restore processes" lists the progress of restoring 65 items.

**Disaster Recovery Configuration Components:**

| Recovery status | Component to Restore       | Current System State                         | All                                 |
|-----------------|----------------------------|----------------------------------------------|-------------------------------------|
|                 | /etc/fstab mount points    | Up to date                                   | <input type="checkbox"/>            |
|                 | Licenses                   | Up to date                                   | <input type="checkbox"/>            |
|                 | OpenVault configuration    | 2 LCPs and 16 DCPs configured                | <input type="checkbox"/>            |
|                 | DMF configuration          | Up to date                                   | <input type="checkbox"/>            |
|                 | OpenVault key file for DMF | Up to date                                   | <input type="checkbox"/>            |
|                 | Integrated dump records    | Backup state different from the system state | <input checked="" type="checkbox"/> |

**Status of restore processes (1 - 25 of 65 items):**

| Destination    | Status | Time Started        | Time Ended          |
|----------------|--------|---------------------|---------------------|
| /dmf_journals/ | ✓      | 2015-06-19T09:42:32 | 2015-06-19T09:42:35 |
| DMF database   | ✓      | 2015-06-19T09:38:01 | 2015-06-19T09:38:50 |
| DMF database   | ✓      | 2015-06-19T09:05:19 | 2015-06-19T09:06:11 |
| DMF database   | ✓      | 2015-06-19T08:14:44 | 2015-06-19T08:15:32 |
| DMF database   | ✓      | 2015-06-19T08:08:16 | 2015-06-19T08:09:04 |
| DMF database   | ✓      | 2015-06-19T07:28:35 | 2015-06-19T07:28:44 |
| DMF database   | ✓      | 2015-06-19T07:20:03 | 2015-06-19T07:20:56 |
| DMF database   | ✓      | 2015-06-19T07:18:53 | 2015-06-19T07:19:42 |
| DMF database   | ✓      | 2015-06-19T07:13:49 | 2015-06-19T07:14:16 |
| DMF database   | ✓      | 2015-06-19T07:06:16 | 2015-06-19T07:06:44 |
| DMF database   | ✓      | 2015-06-19T07:00:57 | 2015-06-19T07:01:26 |
| DMF database   | ✓      | 2015-06-19T07:00:13 | 2015-06-19T07:00:42 |
| DMF database   | ✓      | 2015-06-19T06:35:10 | 2015-06-19T06:35:26 |
| DMF database   | ✓      | 2015-06-19T06:31:30 | 2015-06-19T06:31:51 |
| DMF database   | ✓      | 2015-06-19T06:30:40 | 2015-06-19T06:30:56 |
| DMF database   | ✓      | 2015-06-19T06:27:38 | 2015-06-19T06:27:55 |

Figure 19-1 Disaster Recovery

Do the following:

1. Open the **Disaster Recovery** dialog and select **Confirm**.
2. Select the following:

**Backups**

> **Recovery**

> **Disaster Recovery..**

3. Specify the required information:
  - a. Specify the location of the DR bundle, such as  
`/hosts/nfsmirror/dmdrbundle-20150623_000000.tar.gz` or  
`root@remotehost:/drbundles/dmdrbundle-20150623_000000.tar.gz`.
  - b. Specify the location to store temporary files during the recovery process. The filesystem containing this directory should have enough space to hold the several components of the DR bundle, including the DR database (which is a collection of all metadata pertaining to the backup filesystem).
  - c. Click **Load**.
4. Choose the components that you want to recover:
  - Configuration components:
    - `/etc/fstab` mount points
    - Licenses in the `/etc/lk/keys.dat` file
    - OpenVault configuration
    - DMF configuration
    - OpenVault key file for DMF
  - Dump inventory records:
    - Integrated dump records containing status of all completed dumps in a database residing in `HOME_DIR/backups/dumps.db`, which is required for access to and operations on dumps through DMF Manager
    - XFS inventory, which has information on all filesystem dumps in the `xfsdump` inventory residing in `/var/lib/xfsdump/inventory`.

---

**Note:** SGI recommends that you create `/var/lib/xfsdump` as a symbolic link to `HOME_DIR/site-specific/xfsdump`.

---

- Backup filesystem components:



---

**Caution:** Restoring these components could potentially remove the current DMF database. Use with extreme caution.

---

- The backup filesystem defined by the `DUMP_DESTINATION` configuration parameter, such as `/dmf_dumps`
- Disaster recovery database containing the metadata of all files residing in the `DUMP_DESTINATION` filesystem

- DMF database components



---

**Caution:** Restoring these components could potentially remove the current DMF database. Use with extreme caution. The disaster-recovery process tries to find any transactions in the journal filesystems that should be replayed; therefore, before trying this operation, you must make sure that the journal filesystem (specified by the `JOURNAL_DIR` parameter) is either intact or already restored.

---

---

**Note:** You should take care to restore all relevant components:

- If you restored only the DR database, you would be left with an incomplete version of DMF. If you restore the DR database, you must restore the DMF databases also.
- If you restore the DMF databases, you must also apply any available journals in order to restore all of the transactions that occurred after the database snapshot.

- 
5. Click **Confirm** to accept the options and perform the disaster recovery.
- 

**Note:** The server will store the state of the DR process. If your browser session is closed during the process, you can reopen DMF Manager later continue the rest of the process.

---

6. After the DR process completes, go to the **Overview** panel and check the status of DMF and OpenVault and restart them if necessary.

## Disaster Recovery for Parallel DMF

If you are using the Parallel Data-Mover Option (Parallel DMF) in a non-HA environment, do the following for disaster recovery:

1. Install DMF software on the replacement DMF server (which is the same node as the OpenVault server, according to best practices for simplicity) and replacement parallel data-mover nodes, as directed in the *Release Note for ISSP*.
2. Run the `ov_makecert(8)` command on the DMF server:
 

```
dmfserver# ov_makecert
```
3. Set up the systems to enable distributed recovery across the cluster:
  - a. Copy the file `/opt/openvault/lib/cert.pem` from the DMF server to the passive DMF server and each parallel data-mover node.
  - b. Configure passwordless `ssh` from the DMF server to each parallel data-mover node.
4. On the DMF server, start the `dmdr_admin(8)` command:

```
dmfserver# dmdr_admin -l DR_bundle -d tmpdir
```

where:

|                  |                                                                                                                                                                                                                                                        |
|------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>DR_bundle</i> | Specifies the location of the disaster-recovery (DR) bundle, such as<br><code>/hosts/nfsmirror/dmdrbundle-20150623_000000.tar.gz</code> or<br><code>root@remotehost:/drbundles/dmdrbundle-20150623_000000.tar.gz</code>                                |
| <i>tmpdir</i>    | Specifies a temporary location on the DMF server to use during the disaster-recovery process. The filesystem containing this directory should have enough space to hold the several components of the DR bundle, including the DR database (which is a |

collection of all metadata pertaining to the backup filesystem).

For example:

```
dmfserver# dmdr_admin -l /hosts/nfsmirror/dmdrbundle-20150623_000000.tar.gz -d /tmp/dumtmp
```

5. At the DR > prompt in the interactive `dmdr_admin` session, do the following:

a. Restore the network configuration (that is, the `/etc/sysconfig/network-scripts/ifcfg-*` files on RHEL or the `/etc/sysconfig/network/ifcfg-*` files on SLES) on all nodes:

```
DR > restore config * network
```

b. Restore the `/etc/hosts` file on all nodes:

```
DR > restore config * host
```

c. Restore the license file on the DMF server:

```
DR > restore config servername licenses
```

where

*servername* Specifies the hostname of the DMF server

For example, if the hostname is `dmfserver`:

```
DR > restore config dmfserver licenses
```

d. Restore CXFS:

```
DR > restore cxfs
```

e. Exit the tool:

```
DR > quit
```

6. Reboot the DMF server.

7. Reboot each parallel data-mover node.

8. From the DMF server, restore OpenVault on each parallel data-mover node:

a. Restart the `dmdr_admin` command on the DMF server. For example:

```
dmfserver# dmdr_admin -l /hosts/nfsmirror/dmdrbundle-20150623_000000.tar.gz -d /tmp/dumtmp
```

- b. Restore the DMF configuration file on the DMF server and all parallel data-mover nodes:

```
DR > restore config * DMF
```

- c. Restore the OpenVault configuration for each parallel data-mover node:

```
DR > restore config movername OpenVault
```

where

*movername* Specifies the hostname of the parallel data-mover node

For example, for the node named *mover1*:

```
DR > restore config mover1 OpenVault
```

Repeat this command for each parallel data-mover node.

- d. After the OpenVault configuration is restored for each parallel data-mover node, remove the temporary files from the *tmpdir* location:

```
DR > unload
```

- e. Exit the tool:

```
DR > quit
```

9. Restore the following on the DMF server using the **Recovery** page of DMF Manager:

- `xfsdump inventory`
- Database for the dumps produced by the integrated backup processes (*HOME\_DIR/backups/dumps.db*)

10. If required, use the **Recovery** page to restore other components, such as */etc/fstab* mount entries and other filesystems from the dumps

For further assistance, call SGI Professional Services.

## Disaster Recovery for DMF with HA

If you are using DMF with HA, call SGI Professional Services for assistance with disaster recovery.

## Filesystem Errors

If the filesystems required for the DMF administrative directories are not mounted when you try to apply configuration changes using DMF Manager or when you use `dmcheck`, you will see errors such as the following:

```
ERROR: Directory for JOURNAL_DIR (/dmf_journals/journals) does not exist.
ERROR: MOVE_FS "/dmf/move" must be a filesystem root
ERROR: Filesystem "/dmi_fs" is not mounted.
ERROR: A DCM's STORE_DIRECTORY (/dmf/dcm_name_store) must be a filesystem root.
ERROR: Filesystem "/" is not a DMAPAPI filesystem
ERROR: No such directory /dmf_journals/database_copies.
ERROR: OpenVault server is not up or client is misconfigured.
```

For example, following is the complete output from `dmcheck`:

```
# dmcheck
```

```
Checking DMF installation.
```

```
Linux mynode 3.0.31-0.9-default #1 SMP Tue May 22 21:44:30 UTC 2012
```

```
(2dc3831) x86_64 x86_64 x86_64 GNU/Linux - mynode
```

```
SuSE-release: SUSE Linux Enterprise Server 11 (x86_64)
```

```
SuSE-release: VERSION = 11
```

```
SuSE-release: PATCHLEVEL = 2
```

```
sgi-issp-release: SGI InfiniteStorage Software Platform, version  
2.6, Build 706r75.sles11sp2-1207112009
```

```
lsb-release:
```

```
LSB_VERSION="core-2.0-noarch:core-3.2-noarch:core-4.0-noarch:core-2.0-x86_64:core-3.2-x86_64:core-4.0-x86_64"
```

```
DMF version 5.6.0 rpm dmf-5.6.0-sgi260r41.sles11sp2 installed.
```

```
Checking DMF config file
```

```
Scanning for non-comment lines outside define/endif pairs
```

```
Scanning for DMF parameters without values
```

```
Checking all objects for invalid names
```

```
Checking base
```

```
ERROR: Directory for JOURNAL_DIR (/dmf_journals/journals) does not exist.
```

```
Checking daemon
```

```
ERROR: MOVE_FS "/dmf/move" must be a filesystem root
```

```
Checking policy cache_policy
```

```
Checking policy space_policy
```

```
Checking policy chooser_policy
```



```
Checking policy optional_chooser_policy
Checking filesystem /dmi_fs
  ERROR: Filesystem "/dmi_fs" is not mounted.
  WARNING: Filesystem "/dmi_fs" inode size of 256 is inefficient for DMF.
Checking filesystem /dmi_fs2
Checking MSP msp
Checking MSP cache (DCM-mode)
  ERROR: A DCM's STORE_DIRECTORY (/dmf/dcm_name_store) must be a filesystem root.
  ERROR: Filesystem "/" is not a DMAPI filesystem
Checking MSP cachel (DCM-mode)
Checking Library Server ov_lib
Checking Resource Watcher rw
Checking Drive Group ov_drv
Checking Volume Group volume1
  WARNING: Please consider setting ZONE_SIZE to improve write performance.
  See the dmfc.conf(5) man page for more information.
Checking Volume Group volume2
Checking Resource Scheduler ov_drvrs
Checking Services dmfc_services
Checking Task Group vgtasks
Checking Task Group daemon_tasks
  ERROR: No such directory /dmf_journals/database_copies.
Checking Task Group dump_tasks
Checking Task Group library_tasks
Checking Task Group node_tasks
Checking for unreferenced objects
  WARNING: Unreferenced watcher rw.
Cross-checking LSSs and task groups for duplicate VSNS

Checking other daemons.
Checking OpenVault
  ERROR: OpenVault server is not up or client is misconfigured.
Checking chkconfig

7 errors found.
3 warnings found.
```

To resolve these problems, you must make and mount the filesystems required for the DMF administrative directories. See:

- "Configure Filesystems and Directories Appropriately for DMF" on page 94

- "Overview of the Installation and Configuration Steps" on page 165

## Unable to Use the `dmi` Mount Option

By default, DMAPI is turned off on SLES 10 systems. If you try to mount with the `dmi` mount option, you will see errors such as the following:

```
kernel: XFS: unknown mount option [dmi]
```

See "Linux CXFS Clients Cannot Mount Managed Filesystems" on page 670.

## EOT Error

A message of the following type means that there was no logical end-of-tape (EOT) mark written to the volume:

```
05:47:26-E 382537-dmatwc end_tape: NOTE: An EOT was not written to VSN 057751 prior to close
```

When DMF appends data to a volume, it positions to the EOT chunk in the EOT zone. Without a valid EOT chunk in the EOT zone, DMF might not be able to append to the volume; this may eventually cause the `HVFY` flag to be set. Set the `hsparse` flag on the volume to merge all the data off of it.

## Tape Drive Not Claimed by `ts`

If a tape drive is not claimed by `ts`, see the `/var/log/messages` file for an indication as to why `ts` did not attach to a device.

## Drive Entry Does Not Correspond to an Existing Drive (OpenVault)

If OpenVault starts before an HBA has discovered the devices, the devices will be unusable by OpenVault. In this case, you would see a message similar to the following:

```
Drive ltol_3 DCP ltol_3@boom config file scsi: entry does not correspond to an existing drive
```

You must add the HBA driver to the `/etc/sysconfig/kernel` file and restart OpenVault. See "Add HBA Drivers to the `initrd` Image" on page 107.

## Drive Does Not Exist (TMF)

If a drive is not visible to TMF, it may be because an HBA device was not properly discovered. In this case, there would be a message in `/var/spool/tmf/daemon.stderr` such as the following:

```
File /dev/pts/pci0002:00:01.1/fc/500104f000700269-500104f00070026a/lun0 does not exist
```

You must add the HBA driver to the `/etc/sysconfig/kernel` file and restart TMF. See "Add HBA Drivers to the `initrd` Image" on page 107.

## No Usable Drives

A variety of conditions can cause the drive group to report that no drives are available, such as shown in the following message:

```
DMF drive group dgc07 has had no usable drives in OpenVault drive group 'drives' for more than 0 seconds
```

To determine the source of the problem, check the following:

1. Is the OpenVault server is running? You can determine this by using the `ov_stat(8)` command. For example:

```
# ov_stat
```

```
The OV server 'node3' is UP.
```

If it is not running, use the `ov_start(8)` command.

2. Is the OpenVault library that contains the drives usable? Use the `ov_stat -L` option. For example, the following shows that OpenVault library `t200` is usable:

```
# ov_stat -L
```

```
LibraryName Usable Disabled
t120         false temporary
t200         true  false
```

3. Does the usable library have at least one usable drive? To determine this, do the following:

- a. Use the `ov_stat(8)` command to see which drives are unusable in group drives specified in the error message. For example, to see the status of all drives:

```
# ov_stat -d
DriveName Group Usable Access Disabled SoftState HardState Occupied PCL
t200d1 drives false true temporary ready unloaded false
t200d2 drives true true false ready unloaded false
t200d3 drives false true false ready unloaded false
```

The above output indicates that two drives (t200d1 and t200d3) are unusable. At least one reason for t200d1 not working is that it is temporarily disabled; you would use the following command to reenale it:

```
# ov_drive -E t200d1
```

You could then repeat the `ov_stat -d` command to see if t200d1 is usable.

There is no indication why t200d3 is unusable, so you must continue with the following step..

- b. Determine why an enabled drive (in this case t200d3) is unusable by examining its DCPs with the `ov_stat` command. For example, to display the DCP status (`-x`) for all drives:

```
# ov_stat -dx
DCPName DriveName Usable SoftState Disabled MsgLevel
t200d1@node1 t200d1 true disconnected false debug
t200d1@node2 t200d1 false inactive false debug
t200d1_2@node1 t200d1 true ready false debug
t200d1_2@node2 t200d1 false inactive false debug
t200d2@node1 t200d2 false disconnected temporary debug
t200d2@node2 t200d2 false inactive false debug
t200d2_2@node1 t200d2 true ready false debug
t200d2_2@node2 t200d2 false inactive false debug
t200d3@node1 t200d3 false disconnected permanent debug
t200d3@node2 t200d3 false inactive false debug
t200d3_2@node1 t200d3 false ready temporary debug
t200d3_2@node2 t200d3 false inactive false debug
```

The above output shows that none of the DCPs on node2 have been started, so they are not usable (because the `SoftState` value is `inactive`). All four DCPs for drive t200d3 are unusable, therefore drive t200d3 itself is unusable.

To fix the DCPs on node2, you would log on to host node2 and enter the following command to start those DCPs in a non-HA configuration:

```
# ov_start t200d1 t200d2 t200d3
```




---

**Caution:** If you are running in an HA configuration, do not start any DCPs or LCPs on the passive DMF server. In an HA environment, it is required that all DCPs and LCPs on the passive DMF server machine be in *inactive* state.

---

You could then repeat the above `ov_stat` command to verify the status of all DCPs:

```
# ov_stat -dx
DCPName      DriveName Usable SoftState   Disabled  MsgLevel
t200d1@node1 t200d1   true  disconnected false        debug
t200d1@node2 t200d1   true  disconnected false        debug
t200d1_2@node1 t200d1   true  ready        false        debug
t200d1_2@node2 t200d1   true  disconnected false        debug
t200d2@node1 t200d2   true  disconnected false        debug
t200d2@node2 t200d2   true  disconnected false        debug
t200d2_2@node1 t200d2   true  ready        false        debug
t200d2_2@node2 t200d2   true  disconnected false        debug
t200d3@node1 t200d3   false disconnected temporary  debug
t200d3@node2 t200d3   true  disconnected false        debug
t200d3_2@node1 t200d3   false ready        temporary  debug
t200d3_2@node2 t200d3   true  disconnected false        debug
```

According to the above output, all of the DCPs on node2 are now usable. However, there are still two DCPs on node1 that are unusable because they are disabled. The following `ov_dcp(8)` command enables all DCPs for all drives starting with the string `t200`:

```
# ov_dcp -E 't200.*' '.*'
```

---

**Note:** Although this may enable DCPs that are already enabled, that does not cause a problem.

---

You can then verify the status of all DCPs to determine if all DCPs on both nodes are usable:

```
# ov_stat -dx
DCPName      DriveName Usable SoftState Disabled MsgLevel
t120d1@node1 t120d1   true  ready      false  debug
t120d1@node2 t120d1   true  disconnected false  debug
t120d2@node1 t120d2   true  ready      false  debug
t120d2@node2 t120d2   true  disconnected false  debug
t120d3@node1 t120d3   true  ready      false  debug
t120d3@node2 t120d3   true  disconnected false  debug
t120d4@node1 t120d4   true  ready      false  debug
t120d4@node2 t120d4   true  disconnected false  debug
t120d5@node1 t120d5   true  disconnected false  debug
t120d5@node2 t120d5   true  disconnected false  debug
t120d5_2@node1 t120d5   true  ready      false  debug
t120d5_2@node2 t120d5   true  disconnected false  debug
t120d6@node1 t120d6   true  disconnected false  debug
t120d6@node2 t120d6   true  disconnected false  debug
t120d6_2@node1 t120d6   true  ready      false  debug
t120d6_2@node2 t120d6   true  disconnected false  debug
t120d6_3@node1 T120d6   true  disconnected false  debug
t120d6_3@node2 t120d6   true  disconnected false  debug
t120d6_4@node1 t120d6   true  disconnected false  debug
t120d6_4@node2 t120d6   true  disconnected false  debug
t200d1@node1 t200d1   true  disconnected false  debug
t200d1@node2 t200d1   true  disconnected false  debug
t200d1_2@node1 t200d1   true  ready      false  debug
t200d1_2@node2 t200d1   true  disconnected false  debug
t200d2@node1 t200d2   true  disconnected false  debug
t200d2@node2 t200d2   true  disconnected false  debug
t200d2_2@node1 t200d2   true  ready      false  debug
t200d2_2@node2 t200d2   true  disconnected false  debug
t200d3@node1 t200d3   true  disconnected false  debug
t200d3@node2 t200d3   true  disconnected false  debug
t200d3_2@node1 t200d3   true  ready      false  debug
t200d3_2@node2 t200d3   true  disconnected false  debug
```

Conversely, you could use the `-y` option to limit the output to only the unusable drives and DCPs:

```
# ov_stat -dy
DriveName Group Usable Access Disabled SoftState HardState Occupied PCL
#
# ov_stat -dxy
DCPName DriveName Usable SoftState Disabled MsgLevel
#
```

The lack of output for the above commands in this case confirms that there are no unusable drives or DCPs.

4. Are the LCPs for the library usable? For example:

```
# ov_stat -L t200 -x
LCPName      LibraryName Usable SoftState Disabled MsgLevel
t200@node3   t200        true  disconnected false  debug
t200_2@node3 t200        false ready      permanent debug
```

The above output indicates that `t200@node3` is usable but `t200_2@node3` has been disabled. To reenable `t200_2@node3`, enter the following:

```
# ov_lcp -E t200 t200_2@node3
```

To verify that all libraries and LCPs are usable, add the `-y` option to restrict the output to unusable components. For example:

```
# ov_stat -L t200 -y
LibraryName Usable Disabled

# ov_stat -L t200 -xy
LCPName LibraryName Usable SoftState Disabled MsgLevel
```

The lack of output for the above commands in this case confirms that there are no unusable libraries or LCPs.

5. Can DMF start movers on the machines with working drives? Use the `dmnode_admin(8)` command to verify that the nodes are active. For example,

```
# dmnode_admin -l
Node Name State Enabled Active Since Dropouts
node1 Inactive Yes - 0
node2 Disabled No - 0
node3 Active Yes 2014-Sep-03,15:23:53 0
```

The above output shows that `node3` is the only node that is both active and enabled. However, the previous steps show that all of the DCPs are defined for either `node1` or `node2`, but there are no drive connections to `node3`. Therefore no drives can be used until at least one of `node1` or `node2` is in `Active` state. See "Reenabling Parallel Data-Mover Nodes" on page 489.

For more information, see the `dmnode_admin(8)` man page and "Determining the State of Parallel Data-Mover Nodes" on page 488.

6. Can DMF communicate with OpenVault? To determine this, examine the following:
  - Output from the `dmcheck(8)` command
  - DMF library server log
  - OpenVault `OVSERVER` log
  - DMF Manager, as discussed in "Displaying Node Status" on page 252

## DMF Manager Errors

This section describes problems you may encounter when monitoring DMF with DMF Manager:

- "DMF Statistics are Unavailable Error Message" on page 666
- "DMF Statistics Graphs are Empty" on page 668
- "OpenVault Library Is Missing" on page 668

Also see "Filesystem Errors" on page 658.

### DMF Statistics are Unavailable Error Message

This screen requires statistics from DMF that are unavailable; check that DMF is running, including the `"pmdadm2"` process. Make sure the DMF `"EXPORT_METRICS"` configuration parameter is enabled.

If DMF statistics are unavailable, do the following:

1. Verify that the `EXPORT_METRICS` parameter in the base object of the `/etc/dmf/dmf.conf` file is set to `ON`.



If it is not, do the following:




---

**Caution:** Do not modify `EXPORT_METRICS` while DMF is running.

For instructions about starting and stopping DMF and the mounting service in an HA environment, see *High Availability Guide for SGI InfiniteStorage*.

---

- a. Run the following commands as `root` to stop DMF:

```
# service dmf stop
```

- b. Set `EXPORT_METRICS` to `ON` by editing the file or using DMF Manager.

- c. Validate the change by using the `dmcheck(8)` command or DMF Manager

- d. Start DMF:

```
# service dmf start
```

For more information, see:

- "Modifying an Object" on page 217
- "Validating Your Changes" on page 218
- "Displaying DMF Configuration File Parameters" on page 219
- "base Object" on page 277

2. Check that the data is passing through PCP by running the following command:

```
# pminfo -f dm2.config.dmversion
```

For example, the following indicates that all is well:

```
# pminfo -f dm2.config.dmversion
```

```
dm2.config.dmversion
value "6.0.0"
```

If no value is available, run the following commands as `root` to remove and reinstall the PCP performance metrics domain agents and restart DMF Manager:

```
# cd /var/lib/pcp/pmdas/dm2
# ./Remove
# ./Install
```

```
# service dmfsman restart
```

## DMF Statistics Graphs are Empty

If the DMF Manager graphs are empty but you do not see the error message in "DMF Statistics are Unavailable Error Message" on page 666, verify that the `gmgrd` process is running:

```
dmfserver# ps -A | grep gmgrd
```

If it is not, restart the `gmgrd` process by restarting the `pcp-storage` service:

```
dmfserver# service pcp-storage restart
```

## OpenVault Library Is Missing

No OpenVault-controlled library found.

This indicates that OpenVault is not running. Run the following command to verify that the `ov_stat` command is available:

```
# ls -lL /usr/bin/ov_stat
-rws--x--x 1 root sys 322304 Jul 22 2005 /usr/bin/ov_stat
```

If the file permissions are not `-rws--x--x` as shown above, run the following command to change the permissions:

```
# chmod 4711 /usr/bin/ov_stat
```

## Delay In Accessing Files in an SMB/CIFS Network Share

If there is a delay in accessing files in an SMB/CIFS network share, it may be because the files are in a fully or partially offline state. The Windows Explorer desktop can be enabled to display a small black clock on top of a migrated file's normal icon; the black clock symbol indicates that there may be a delay in accessing the contents of the file. (This feature is disabled by default.) For more information, see "Modify Settings If Providing File Access via Samba" on page 127.

## Operations Timeout or Abort on Windows

Operations such as `cp` can timeout on Windows systems or abort with the following message:

```
couldn't locate the origin file
```

This may occur if the `SessTimeout`, `ExtendedSessTimeout`, or `ServersWithExtendedSessTimeout` parameter is set to a value that is inappropriate for a DMF environment. See "Modify Settings If Providing File Access via Samba" on page 127.

## Windows Explorer Hangs

If Windows Explorer hangs and the `no response ...` message appears in the Windows main title, it may be because the `SessTimeout`, `ExtendedSessTimeout`, or `ServersWithExtendedSessTimeout` parameter is set to a value that is inappropriate for a DMF environment. See "Modify Settings If Providing File Access via Samba" on page 127.

## Poor Migration Performance

If you encounter poor migration performance, you can try to tune DMF's direct I/O size by modifying the `DIRECT_IO_SIZE` parameter for the `filesystem` object in the DMF configuration file (`/etc/dmf/dmf.conf`).

You can also try switching to buffered I/O migration by setting the `MIN_DIRECT_SIZE` parameter to a very large value.

See "filesystem Object" on page 350.

## Poor Recall Performance

If you notice performance problems when recalling files, you can consider adjusting the `POSIX_FADVISE_SIZE` parameter in the `filesystem` object. This may make an improvement, but will require testing multiple factors such as the following:

- Memory pressure, which impacts buffer cache and forces the kernel to flush pages
- User filesystem activity

- The setting of various `sysctl vm` parameters (see the `Documentation/sysctl/vm.txt` file in the Linux kernel source)

For more details about setting the `POSIX_FADVISE_SIZE` parameter in the DMF configuration file, see "filesystem Object Parameters" on page 351.

---

**Note:** Setting this parameter to a small, nonzero value may have an adverse affect on performance. See the `posix_fadvise(2)` man page for more information.

---

## Remote Connection Failures

If there are an insufficient number of `xinetd tcpmux` instances configured, you may see remote connection failures. If this condition occurs, you will see messages like the following in the `/var/log/xinetd.log` file:

```
10/3/2@13:41:09: FAIL: tcpmux service_limit from=128.162.246.75
```

To solve this problem, see "Set the `xinetd tcpmux` instances Parameter Appropriately" on page 108.

## yast2 Disk Space Warning

If you try to use `yast2` while RAID sets in the COPAN MAID are mounted by OpenVault, `yast2` displays a graphic that contains the following warning:

```
Warning: Disk space is running out!
```

However, the red disk usage shown for filesystems such as `/var/opt/openvault/clients/mounts/copan_C00d02` is expected; it indicates that the RAID sets are mounted by OpenVault. You can safely click the **OK** button at the bottom of the window.

## Linux CXFS Clients Cannot Mount Managed Filesystems

In order for CXFS client-only nodes that are not running DMF software to mount CXFS filesystems, you must make manual modifications in order to run DMAPI. See the information about enabling DMAPI for Linux client-only nodes in the *CXFS 7 Client-Only Guide for SGI InfiniteStorage*.

## Mount Errors for a Drive

If a drive is unable to mount a cartridge, it may be that the drive has firmware that is incompatible with the persistent reservation feature, which is on by default. In this case, you can disable persistent reservation on that drive by doing the following:

1. List the DCP paths for the problem drive. For example (output truncated):

```
# ov_dumptable -c DriveName,DCPHost,DCPControlPath DCP
C07d1      nodeA /dev/ts/pci0000:05:00.0/fc/2000001b3202a4dd-2100001b3202a4dd/lun1
C07d1      nodeB /dev/ts/pci0000:07:00.1/fc/2001001b3222a4dd-2101001b3222a4dd/lun1
...
```

2. On each host, execute the following command to turn off persistent reservation on the path for that host to the problem drive, where *PATH* is the DCPControlPath as listed above:

```
# tsset -p off -d PATH
```

For example, using the output above for C07d1, you would execute the following:

- On host nodeA:

```
nodeA# tsset -p off -d /dev/ts/pci0000:05:00.0/fc/2000001b3202a4dd-2100001b3202a4dd/lun1
```

- On host nodeB:

```
nodeB# tsset -p off -d /dev/ts/pci0000:07:00.1/fc/2001001b3222a4dd-2101001b3222a4dd/lun1
```

---

**Note:** Every path to a given drive used by OpenVault must be set the same way on every host (either all enabled or all disabled).

---

The drive will no longer experience the mount errors, but it will no longer have the data protection provided by the feature.

If in the future you install new firmware that supports persistent reservation, you can reenble the feature on the drive by doing the following on each host:

- Verify that the path has the persistent reservation feature disabled:

```
# tsmt -f PATH prsv
```

If the feature is disabled, the above command will return a Not Supported error.

- Reenable the feature by entering the following on each host:

```
# tsset -p on -d PATH
```

## Verifying the Integrity of Library Server Volumes

You can use the `dmatsnf(8)` command to verify the integrity of library server volumes. The command provides a number of options; see the man page for details.

The following example illustrates just a few `dmatsnf` options, in a series of steps in conjunction with the `dmcatadm(8)` command, that you can use to verify a volume (in this case, `C07IAI`) where some reads fail due to I/O errors. (To simplify the example, the volume was written with unrealistically small zones and no data was hard-deleted from this volume.)

1. List the chunks that are recorded in the database as being on the volume, using the `dmcatadm(8)` command:

```
# dmcatadm -m ls_maid -c 'list vsn=c07iai format zn,cn,vsn'
          ZONE CHUNK
          KEY   NUM   NUM VSN
-----
4d9dd5130000000000c6776b    1    1 C07IAI
4d9dd5130000000000c6776c    1    2 C07IAI
4d9dd5130000000000c6776d    1    3 C07IAI
4d9dd5130000000000c6776e    1    4 C07IAI
4d9dd5130000000000c6776f    2    6 C07IAI
4d9dd5130000000000c67770    2    7 C07IAI
```

2. Verify the volume:

```
# dmatsnf -v C07IAI -v vgc07
Processing vsn C07IAI
BOC: zn=1, cn=1, bfid=4d9dd5130000000000c6776b, file_offset=0, file_length=5000, expected_length=5000
BOC: zn=1, cn=2, bfid=4d9dd5130000000000c6776c, file_offset=0, file_length=5000000, expected_length=5000000
ERROR (C07IAI) at zn=1, cn=2, so=3139900: found block error, length=0: Input/output error

Skipped 51 bad blocks
ERROR (C07IAI): Too many consecutive block errors; will not try to read remainder of this zone. Consider increasing -
ERROR (C07IAI) at zn=1, cn=2, Database entry zn=1 cn=2 not read from tape due to preceding errors
ERROR (C07IAI) at zn=1, cn=2, Database entry zn=1 cn=3 not read from tape due to preceding errors
```

```

ERROR (C07IAI) at zn=1, cn=2, Database entry zn=1 cn=4 not read from tape due to preceding errors
BOC: zn=2, cn=6, bfid=4d9dd5130000000000c6776f, file_offset=0, file_length=1000000, expected_length=1000000
BOC: zn=2, cn=7, bfid=4d9dd5130000000000c67770, file_offset=0, file_length=27000000, expected_length=27000000
EOZ: zn=2, cn=8
--- TAPE MARK ---
EOI: zn=3, cn=9
7 errors found.

```

The above output shows that in the middle of chunk 2 (cn=2), dmatsnf saw 51 consecutive I/O errors. Because that exceeds the default maximum (for the `-e` option), dmatsnf quit reading data in zone 1 and positioned to zone 2 (zn=2), where it was able to successfully read the remainder of the volume.

To read all of zone 1, you must specify a maximum error count with `-e` that is equal to or greater than the number of blocks in the zone that have I/O errors; the easiest way to guarantee this is to use a value at least as large as the number of blocks in the volume, accomplished in the following steps.

### 3. Find the end-of-tape block ID value:

```

# dmvoladm -m ls_maid -c 'list vsn=c07iai format eb,ec,ez'

```

| VSN    | BLOCKID | CHUNK | ZONE |
|--------|---------|-------|------|
| C07IAI | d7      | 9     | 3    |

---

**Note:** The output is shown in hexadecimal.

---

### 4. Verify the volume again, but this time specify a maximum number of consecutive errors that is equal to the size of the volume by using the `-e` option with the decimal value of the end-of-tape block ID shown above (d7 has a decimal value of 215):

```

# dmatsnf -v C07IAI -V vgc07 -e 215
Processing vsn C07IAI
BOC: zn=1, cn=1, bfid=4d9dd5130000000000c6776b, file_offset=0, file_length=5000, expected_length=5000
BOC: zn=1, cn=2, bfid=4d9dd5130000000000c6776c, file_offset=0, file_length=5000000, expected_length=5000000
ERROR (C07IAI) at zn=1, cn=2, so=3139900: found block error, length=0: Input/output error

skipped 51 bad blocks
ERROR (C07IAI) at zn=1, cn=2, so=3139900: found cn=3, fo=24875824, DATA out of sequence
ERROR (C07IAI) at zn=1, cn=3, Database entry zn=1 cn=2 not found on tape

```

```
BOC: zn=1, cn=4, bfid=4d9dd513000000000c6776e, file_offset=0, file_length=17000000, expected_length=17000000
EOZ: zn=1, cn=5
--- TAPE MARK ---
BOC: zn=2, cn=6, bfid=4d9dd513000000000c6776f, file_offset=0, file_length=1000000, expected_length=1000000
BOC: zn=2, cn=7, bfid=4d9dd513000000000c67770, file_offset=0, file_length=27000000, expected_length=27000000
EOZ: zn=2, cn=8
--- TAPE MARK ---
EOI: zn=3, cn=9
4 errors found.
```

The above output shows that in the middle of chunk 2, I/O errors were encountered. The following line means that `dmatsnf` was able to successfully read part of chunk 3 (the first part of chunk 3 had I/O errors):

```
ERROR (C07IAI) at zn=1, cn=2, so=3139900: found cn=3, fo=24875824, DATA out of sequence
```

## **dmemptytape Process Did Not Complete**

An email message that contains wording similar to the following indicates that the `dmemptytape(8)` process was interrupted:

```
A dmemptytape process for vsn VSN did not complete.
```

The `dmemptytape` command uses a checkpoint feature so that you can restart it if it is interrupted, minimizing the chance that file copies will be lost. You should therefore reexecute the same `dmemptytape` command line in order to maintain all copies of all files. For details, see the `dmemptytape(8)` man page.



---

**Caution:** Do not manually remove any temporary files associated with `dmemptytape`. `dmemptytape` will automatically clean up the temporary directories after they are no longer needed.

---

## **DMF Database Server Startup Issues**

If there are problems starting the DMF database server, do the following:

- Ensure that the `ident` service is started, according to the instructions in "Overview of the Installation and Configuration Steps" on page 165
- Restart the `xinetd` service if you have changed arguments



- Examine the `/var/log/dmf/svclog` file for issues related to starting up the DMF database server

## Using SGI Knowledgebase

If you encounter problems and have an SGI support contract, you can log on to the SGI support website and access the **Search Knowledgebase** tool to help find answers.

See:

<https://support.sgi.com>

If you need further assistance, contact SGI Support.

## Reporting Problems to SGI

As soon as you suspect a problem with DMF, run the following commands as `root` to gather relevant information about your DMF environment that will help you and SGI analyze the problem:

- Run the following command on the DMF server and every parallel data-mover node in order to gather system configuration information:

```
# /usr/sbin/system_info_gather -A -o nodename.out
```

- Run the following command once on the DMF server to collect information for today and the specified number of additional days (*previous-days* must be a numerical value greater than or equal to 0):

```
# dmcollect previous-days
```

---

**Note:** Take care to enter the correct number of previous days from which to gather information, so that logs containing the first signs of trouble are included in the collection.

---

See the `dmcollect(8)` man page for additional information.

When you contact SGI Support, you will be provided with information on how and where to upload the collected information files for SGI analysis.



## Messages

This appendix discusses the following:

- "dmcatadm Message Interpretation" on page 677
- "dmvoladm Message Interpretation" on page 679

If you are uncertain about how to correct these errors, contact your customer service representative.

### dmcatadm Message Interpretation

The following lists the meaning of messages associated with the CAT records in the LS database:

*nnn* bytes duplicated in volume group name

Two or more chunks in the database, which belong to volume group (VG) name, contain data from the same region of the file.

for vsn DMF001 chunk 77 chunkoffset < 0

The `chunkoffset` value for chunk 77 on volume serial number (VSN) DMF001 is obviously bad because it is less than 0.

for vsn DMF001 chunk 77 chunklength < 0

The `chunklength` value for chunk 77 on VSN DMF001 is obviously bad because it is less than 0.

for vsn DMF001 chunk 77 chunknumber < 0

The `chunknumber` value for chunk 77 on VSN DMF001 is obviously bad because it is less than 0.

for vsn DMF001 chunk 77 filesize < 0

The `filesize` value for chunk 77 on DMF001 is obviously bad because it is less than 0.

for vsn DMF001 chunk 77 filesize < chunklength +  
chunkoffset

The value of `chunklength` plus `chunkoffset` should be less than or equal to the `filesize`. Therefore, one or more of these values is wrong.

for vsn DMF001 chunk 77 missing or improper vsn

The list of VSNs for the chunk is improperly constructed. The list should contain one or more six-character names separated by colons.

for vsn DMF001 chunk 77 zonenumbers < 0

The `zonenumbers` value for chunk 77 on DMF001 is obviously bad because it is less than 0.

for vsn DMF001 chunk 77 zonenumbers > chunknumber

Either the `zonenumbers` value or the `chunknumber` value for chunk 77 on DMF001 is wrong, because the `zonenumbers` is larger than the `chunknumber` value. (Each zone contains at least two chunks, because the end-of-zone header on the volume counts as a chunk.)

for vsn DMF001 chunk 77 filesize != file size in  
daemon entry (nnn)

The `filesize` value in the chunk entry is different from the file size in the daemon record. If no daemon record was provided, this message indicates that more than one chunk exists for the BFID and that the `filesize` value is not the same for all the chunks.

missing from cat db

No corresponding CAT record was found for an existing daemon record.

entry for volume group name missing from daemon db

No corresponding daemon record was found for an existing CAT record.

for volgrp name; no chunk for bytes nnn - nnn

There is no chunk that contains the specified bytes of the file.

## dmvoladm Message Interpretation

The following lists the meaning of messages associated with the VOL records in the LS database.

blocksize is bad

The `blocksize` field for the volume is less than or equal to 0.

eotpos < largest position in cat (3746)

The position for the end-of-volume (historically known as *EOT* for *end-of-tape*) descriptor on the volume is less than the largest position of all the chunk entries for the volume.

chunksleft != number of cat chunks (256)

The number of chunks referencing the volume in the CAT table does not equal the number of chunks left recorded in the VOL entry for the volume.

dataleft != sum of cat chunk lengths (4.562104mb)

The sum of the chunks length for chunks referencing the volume in the CAT table does not equal the `dataleft` value recorded in the VOL entry for the volume.

dataleft > datawritten

The entry shows that more data remains on the volume than was written.

eotchunk < chunksleft

The entry shows that more chunks remain on the volume than were written.

eotchunk < largest chunk in cat (443)

The chunk number of the end-of-volume EOT descriptor on the volume is less than the largest chunk number of all the chunk entries for the volume.

eotzone < largest zone in cat (77)

The zone number of the end-of-volume EOT descriptor on the volume is less than the largest zone number of all the chunk entries for the volume.

missing

The volume was found in a chunk entry from the CAT table but is not in the VOL table.

tapesize is bad

The `tapesize` field for the volume is an impossible number.

version is bad

The `version` field for the volume is not 1 or 3 (for a volume still containing data written by the old tape MSP) or 4 (for a volume written by this MSP).

volume is empty but hfull is on  
volume is empty but hsparse is on

When a volume is empty, the `hfull` and `hsparse` hold flags should be off.

volume is empty but datawritten != 0  
volume is empty but eotpos != 1/0  
volume is empty but eotchunk != 1

When the `hfree` hold flag is cleared, the `datawritten` field is set to 0, the `eotpos` field is set to 1/0, and the `eotchunk` is set to 1. The entry is inconsistent and should be checked.

volume is not empty but hfree is on

When a volume contains data, the `hfree` hold flag must be off.

volume is not empty and version is *n* but hfull is off

Tapes containing data with a version value of less than 4 must have `hfull` set, because the LS cannot append to the tape.

volume is not empty and version is *n* but eotpos != 2/0

Tapes imported from the old MSP only have one zone of data, so `eotpos` must be 2/0.

zonesize is too small

The `zonesize` field for the volume is an impossible number.

## DMF User Library `libdmfusr.so`

The subroutines that constitute the DMF user-command application program interface (API) are available to user-written programs by linking to the DMF user library, `libdmfusr.so`. Sites can design and write their own custom DMF user commands, which eliminates the need to use wrapper scripts around the DMF user commands.

This appendix discusses the following:

- "Overview of the Distributed Command Feature and `libdmfusr.so`" on page 681
- "Considerations for IRIX®" on page 684
- "`libdmfusr.so` Library Versioning" on page 684
- "`libdmfusr.so.2` Data Types" on page 686
- "User-Accessible API Subroutines for `libdmfusr.so.2`" on page 705

### Overview of the Distributed Command Feature and `libdmfusr.so`

The distributed command feature allows DMF commands to execute on a host other than the host on which the DMF daemon is running. (This feature was first made available with DMF 2.7.) A host that imports managed filesystems from the DMF daemon host machine can execute the DMF commands locally (see "DMF Manager Web Interface" on page 9). The distributed command feature requires `tcpmux` (RFC 1078).

The DMF user commands communicate with a process named `dmusrCmd`, which is executed as `setuid root`. `dmusrCmd` performs validity checks and communicates with the DMF daemon. (In releases prior to DMF 2.7, user commands communicated directly with the DMF daemon and were installed as `setuid root` processes.)

In order for the DMF user commands to communicate in an efficient and consistent manner with the `dmusrCmd` process, they must access the DMF user library, which is installed in the following location according to platform operating system and architecture:

| Platform   | DMF User Library Location   |
|------------|-----------------------------|
| irix-n32   | /usr/lib32/libdmfusr.so[.n] |
| irix-64    | /usr/lib64/libdmfusr.so[.n] |
| Linux ia64 | /usr/lib/libdmfusr.so[.n]   |

---

**Note:** The old version of `libdmfusr` is located in `/usr/lib/dmf/libdmfusr_v1` in order to prevent `ldconfig(8)` from updating the `/usr/lib/libdmfusr.so` symbolic link to point to the old library. Customers requiring the version 1 library can make use of it with the following steps:

```
# cd /usr/lib/dmf/libdmfusr_v1
# ln -s libdmfusr.so.1 libdmfusr.so
# export LD_LIBRARY_PATH=/usr/lib/dmf/libdmfusr_v1
```

---

|              |                                   |
|--------------|-----------------------------------|
| Linux x86_64 | /usr/lib64/libdmfusr.so[.n]       |
| Solaris      | /usr/lib/sparcv9/libdmfusr.so[.n] |
| Mac OS X     | /usr/lib/libdmfusr.[n].dylib      |

Each of the DMF user commands is linked to the library for its protocol-based communications. (The DMF user library became a versioned shared-object library in DMF 3.1. See "`libdmfusr.so` Library Versioning" on page 684 for more information on accessing the correct version of `libdmfusr.so`.)

The underlying design of the API calls for the user command to make contact with a `dmusrCmd` process by creating an opaque context object via a call to the API. This context is then used as a parameter on each function (`put`, `get`, `fullstat`, or `copy`). The context is used by each API subroutine to perform the requested operation and to correctly return the results of the operation to the command.

In addition to the library, the `libdmfusr.H`, `libdmfcom.H`, and `dmu_err.h` header files are provided. These files are required for sites to effectively create their own commands. All header files are installed in `/usr/include/dmf`. The `libdmf*` header files contain all of the object and function prototype definitions required by



the API subroutine calls. The `dmu_err.h` file contains all of the API error code definitions. Along with each error code definition is a text string that is associated with each of the error codes. This text string is the same message that is generated automatically when the error occurs as part of the `DmuErrInfo_t` object (see "DmuErrInfo\_t" on page 695). The text string is included in the file as informational only, and is not accessible by a program that includes `dmu_err.h`.

Each type of function request (`Put`, `Get`, `Fullstat`, or `Copy`) can be made via a synchronous or an asynchronous API subroutine call:

- Synchronous subroutine calls do not return to the caller until the request has completed, either successfully or unsuccessfully. These synchronous subroutines return an error object to the caller that can be processed to determine the success or failure of the call. If an application is making more than one call, these calls will usually perform less efficiently than their asynchronous counterparts because of the serial nature of their activity.
- Asynchronous subroutine calls return immediately to the caller. The return codes of these asynchronous subroutines indicate whether the request was successfully forwarded to `dmusrCmd` for processing. A successful return allows the calling program to continue its own processing in parallel with the processing being performed by `dmusrCmd` (or the DMF daemon) to complete the request. If the request was successfully forwarded, a request ID that is unique within the scope of the opaque context is returned to the caller. It is the responsibility of the caller to associate the request ID with the correct completion object (described in "DmuCompletion\_t" on page 692) to determine the eventual result of the original request.

There are several API subroutine calls for processing asynchronous request completion objects. The user can choose to do any of the following:

- Be notified when all requests have completed without processing the return status of each request.
- Process the return status of each request in the order in which they complete. See "DmuGetNextReply() Subroutine" on page 730.
- Wait synchronously on an individual asynchronous request's completion by specifying the request ID on which to wait. By using this method, each request return status can be processed in the order in which it was sent, known as *request ID order*.

The API includes well-defined protocols that it uses to communicate with the `dmusrCmd` process. Because these protocols make use of the `pthread(5)`

mechanism, any user application program making use of the API via `libdmfusr.so` must also link to the `libpthread.so` shared object library via one of the following:

- `lpthread` compiler option using `cc(1)` or `CC(1)`
- `lpthread` loader option using `ld(1)` or `rld(1)`

In many cases, the API subroutines pass the address of an object back to the caller by setting a `**` pointer accordingly. If errors occur and the subroutine is unable to complete its task, the address returned may be `NULL`. It is up to the caller to check the validity of an object's address before using it in order to avoid causing a `SIGSEGV` fault in the application program.

## Considerations for IRIX<sup>®</sup>

The DMF user library for each IRIX platform (`lib32` and `lib64`) was compiled using a MIPSpro<sup>™</sup> compiler. Compiling user applications that call DMF user library API subroutines with compilers other than MIPSpro compilers may result in incompatibilities causing load-time or run-time errors.

## `libdmfusr.so` Library Versioning



---

**Caution:** The old `libdmfusr.so.1` version of the DMF library described below will be removed in a future release. Customers should recompile their applications to use the new library.

---

DMF 3.1 introduced a new version of the DMF user library. This new version is not compatible with the previous library nor with applications that were written and linked with the previous library. To allow the use of older applications after installing the current version of DMF and to facilitate upgrading older applications, the current version of DMF provides both the old version and the new version and introduces a linking mechanism.

When an application is created and linked with a shared object, the name of the actual library that the application is ultimately linked with is stored in the executable file and used at execution time to find a library of the same name for dynamic linking. In previous releases, the library was named `libdmfusr.so`. Therefore, all existing DMF commands and site-developed applications that use the library contain the filename `libdmfusr.so` in the executable for linking with the library at execution time.

A common practice when creating a new version of a library is to add the suffix `.n` to the library name, where `n` is an ever-increasing integer that refers to the current version number.

Prior to DMF 3.1, the library named `libdmfusr.so` was an actual library, rather than a link to a library. The current version of DMF provides the old library (renamed `libdmfusr.so.1`) and the new library (named `libdmfusr.so.2`). All current DMF user commands (such as `dmput`) were created and linked with `libdmfusr.so.2` and their executables contain the filename `libdmfusr.so.2` for linking with the library.

The `libdmfusr.so.1` library is identical to the `libdmfusr.so` library shipped prior to DMF 3.1. The current DMF installation process will install a link named `libdmfusr.so` that will point to `libdmfusr.so.2`. If needed, you can change the link to point to `libdmfusr.so.1` in order to satisfy linking for executables built with a pre-DMF 3.1 `libdmfusr.so`.

The locations of the libraries and the link have not changed from previous releases (see "Overview of the Distributed Command Feature and `libdmfusr.so`" on page 681).

The new `libdmfusr.so` link provides the following advantages:

- You can use the default setting, which does not require any knowledge about the latest version of the library. When developing new site applications using the library, the non-version-specific `ld` option `-ldmfusr` will result in the loader following the link and using the new version of the library, `libdmfusr.so.2`. The resulting applications will contain the name `libdmfusr.so.2` in their executable files for dynamic loading.
- You can reset the link to point to `libdmfusr.so.1`, which allows existing site-developed applications to continue to work with the older version of the library. This will not affect any of the DMF user commands because they contain the name of the new library and make no use of the link at execution time. When an older application executes, if filename `libdmfusr.so` is encountered by the loader and the link points to `libdmfusr.so.1`, the application will continue to work exactly as it did before the current DMF installation.

The two uses of the link as described above are mutually exclusive of each other. Take care when using the link to enable older applications to run with the old library while at the same time developing new applications using the new library. If the link points to `libdmfusr.so.1` and `-ldmfusr` is used to create a new application, the older version of the library will be found and the resulting executable will contain the filename `libdmfusr.so.1` for use at execution time. If older applications are required to run correctly while new applications are being developed, you must use

specific loader command options to ensure that the new applications are linked with the latest library. This can be done by including the specific library name, such as `libdmfusr.so.2`, on the `ld` or `cc` command instead of the generic library specification `-ldmfusr`.

## `libdmfusr.so.2` Data Types

The data types described in this section are defined in `libdmfusr.H` or `libdmfcom.H`. For the most up-to-date definitions of each of these types, see the appropriate file. The following information is provided as a general description and overall usage outline.

All of the data types defined in this section are C++ objects, and all have constructors and destructors. Many have copy constructors and some have operator override functions defined. Please refer to the appropriate `.H` header file to see what C++ functions are defined for each object in addition to the member functions described in this section.

### `DmuAllErrors_t`

The `DmuAllErrors_t` object provides the caller with as much information regarding errors as is practical. The complex nature of the API and its communications allows for many types of errors and several locations (processes) in which they can occur. For example, a request might fail in the API, in the `dmusrcmd` process, or in the DMF daemon.

The public member fields and functions of this class are as follows:

|                            |                                                                                                                                           |
|----------------------------|-------------------------------------------------------------------------------------------------------------------------------------------|
| <code>entry</code>         | Specifies a read-only pointer allowing access to all <code>DmuErrInfo_t</code> entries in the <code>DmuAllErrors_t</code> internal array. |
| <code>numErrors()</code>   | Returns the number of <code>DmuErrInfo_t</code> entries in the <code>DmuAllErrors_t</code> internal array.                                |
| <code>resetErrors()</code> | Clears the <code>DmuAllErrors_t</code> internal array.                                                                                    |

Following is an example using a `DmuAllErrors_t` object.

---

**Note:** The following code is a guideline. It may refer to elements of a `DmuAllErrors_t` structure that are not defined in your installed version of `libdmfcom.H`.

---

```
report_errors(DmuAllErrors_t *errs)
{
    int          i;

    if (!errs) {
        return;
    }
    for(i = 0; i < errs->numErrors(); i++) {
        fprintf(stdout, "group '%s' errcode '%d' who '%s' "
            "severity '%s' position '%s' host '%s' message '%s'\n",
            errs->entry[i].group ? errs->entry[i].group : "NULL",
            errs->entry[i].errcode,
            DmuLogGetErrWhoImage(errs->entry[i].errwho),
            DmuLogGetSeverityImage(errs->entry[i].severity),
            errs->entry[i].position ? errs->entry[i].position : "NULL",
            errs->entry[i].host ? errs->entry[i].host : "NULL",
            errs->entry[i].message ? errs->entry[i].message : "NULL");
    }
}
```

### **DmuAttr\_t**

The `DmuAttr_t` object defines the DMF attribute for a managed file.

The public member fields and functions of this class are as follows:

|                      |                                                                                                                                                                                  |
|----------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>bfid</code>    | Specifies a <code>DmuBfid_t</code> object (defined in <code>libdmfcom.H</code> ) that defines the file's bitfile-ID ( <code>bfid</code> ).                                       |
| <code>dmflags</code> | Specifies an integer defining a file's DMAPI flags. Currently unused.                                                                                                            |
| <code>dmstate</code> | Specifies a <code>dmu_state_t</code> object that defines the file state. Valid states are:<br><div style="text-align: right;"><code>DMU_ST_ARCHIVING</code>      Archiving</div> |

|         |                                                                                                                                   |                      |
|---------|-----------------------------------------------------------------------------------------------------------------------------------|----------------------|
|         | DMU_ST_DUALSTATE                                                                                                                  | Dual-state           |
|         | DMU_ST_MIGRATING                                                                                                                  | Migrating            |
|         | DMU_ST_NOMIGR                                                                                                                     | No migration allowed |
|         | DMU_ST_OFFLINE                                                                                                                    | Offline              |
|         | DMU_ST_PARTIAL                                                                                                                    | Partial-state file   |
|         | DMU_ST_REGULAR                                                                                                                    | Regular              |
|         | DMU_ST_UNMIGRATING                                                                                                                | Unmigrating          |
| fsys    | Specifies a <code>DmuFileIoMethod_t</code> object (defined in <code>libdmfcom.H</code> ) that defines the file's filesystem type. |                      |
| regbuf  | Specifies a <code>DmuFullRegbuf_t</code> object that defines the file full region information. See "DmuFullRegbuf_t" on page 697. |                      |
| sitetag | Defines the file site tag value. See <code>dmtag(1)</code> .                                                                      |                      |
| version | Specifies a <code>DmuFileIoVersion_t</code> object (defined in <code>libdmfcom.H</code> ) that defines the filesystem version.    |                      |

### DmuByteRange\_t

The `DmuByteRange_t` object defines a range of bytes that are to be associated with a `Put` or `Get` request.

The public member fields and functions of this class are as follows:

|                        |                                                    |
|------------------------|----------------------------------------------------|
| <code>start_off</code> | Starting offset in bytes of the range in the file. |
| <code>end_off</code>   | Ending offset in bytes of the range in the file.   |

Nonnegative values for `start_off` or `end_off` indicate an offset from the beginning of the file. The first byte in the file has offset 0. Negative values may be used to indicate an offset from the end of the file. The value -1 indicates the last byte in the file, -2 is the next-to-last byte, and so on. The range is inclusive, so if `start_off` has a value of 2 and `end_off` has a value of 2, it indicates a range of one byte.

## DmuByteRanges\_t

The `DmuByteRanges_t` object defines a set of `DmuByteRange_t` objects that are to be associated with a Put or Get request.

The public member fields and functions of this class are as follows:

### `clearByteRange`

Clears the specified byte range in the `DmuByteRanges_t` object. The `clearByteRange()` routine is restricted in how it handles negative offsets, both in the `DmuByteRange_t` members of the `DmuByteRanges_t` class and in its parameters. The following items give the details of these restrictions. In the following items, *start* and *end* are the parameters to the `clearByteRange()` routine, using the following format:

`clearByteRange(start, end)`

- If *start* and *end* exactly match a `DmuByteRange_t` entry, then that entry will be cleared. This includes negative numbers.
- If *start* is 0 and *end* is -1, all `DmuByteRange_t` entries will be cleared. `resetByteRanges()` is the preferred method for clearing all ranges.
- If *start* is positive and *end* is -1, then:
  - All `DmuByteRange_t` entries that have a positive `start_off` value greater than or equal to *start* will be cleared
  - All `DmuByteRange_t` entries that have a positive `start_off` value that is less than *start* and an `end_off` value of -1 will be changed to have an `end_off` value of *start-1* (that is, *start* minus 1). For example, if `DmuByteRanges_t` has a single range, 3:-1, then `clearByteRange(4, -1)` will leave a single range, 3:3.
  - All `DmuByteRange_t` entries that have a positive `start_off` value that is less than *start* and an `end_off` value that is greater than *start* will be changed to have an `end_off` value of *start-1*. For example, if `DmuByteRanges_t` has a single range 3:9, then `clearByteRange(4, -1)` will leave a single range 3:3.

- If *start* and *end* are both positive and a `DmuByteRange_t` entry has positive *start\_off* and *end\_off* values, then the range specified by *start* and *end* is cleared from the `DmuByteRange_t`.
- If *start*, *end*, and the *start\_off* and *end\_off* values of a `DmuByteRange_t` are all negative, the range specified is cleared from `DmuByteRange_t`.

`entry`

Specifies a read-only pointer allowing access to all `DmuByteRange_t` entries in the `DmuByteRanges_t` internal array.

`fromByteRangesImage()`

Converts a string that represents a byte range and adds it to the `DmuByteRanges_t` object. Strings that represent byte ranges are described on the `dmput(1)` man page.

---

**Note:** In a string representing a byte range, `-0` represents the last byte in the file; in a `DmuByteRange_t` object, `-1` represents the last byte in the file.

For example, suppose `byteranges` is declared as the following:

```
DmuByteRanges_t byteranges;
```

Then each of the following statements will add the `DmuByteRange_t` object that covers the entire file:

```
byteranges.setByteRange(0, -1);  
byteranges.fromByteRangesImage("0:-0" , &errstr);
```

---

If the byte range overlaps or is adjacent to an existing range in the array, the items may be coalesced.

`numByteRanges()`

Returns the number of `DmuByteRange_t` objects contained in the entry array.

`resetByteRanges()`

Resets the number of `DmuByteRange_t` objects in the array to zero.



rounding

Specifies the rounding method to be used to validate range addresses. Only `DMU_RND_NONE` is valid.

`setByteRange()`

Adds a new range. If the range being added overlaps or is adjacent to an existing range in the array, the items may be coalesced. It is expected that the starting offset not be closer to the end-of-file than the ending offset. For example, a starting offset of 5 and an ending offset of 4 is invalid, and the `setByteRange()` function may not add it to the array. The `setByteRange()` function cannot determine the validity of some ranges, however, and may add ranges that the Put or Get request will later ignore.

You can create a valid `DmuByteRanges_t` object using the default constructor with or without the new operator, depending on the need. For example:

```
DmuByteRanges_t      ranges;

DmuByteRanges_t      *ranges = new DmuByteRanges_t;
```

The following example creates a `DmuByteRanges_t` named `byteranges`, adds a `DmuByteRange_t` to it, then prints the entry to `stdout`:

```
DmuByteRanges_t byteranges;
int             i;
byteranges.rounding = DMU_RND_NONE;
byteranges.setByteRange(0, 4095); /* specifies the first 4096 bytes in the file */
for (i = 0; i < byteranges.numByteRanges(); i++) {
    fprintf(stdout, "Starting offset %lld, ending offset %lld\n",
            byteranges.entry[i].start_off,
            byteranges.entry[i].end_off);
}
```

The output to `stdout` would be as follows:

```
starting offset 0, ending offset 4095
```

The following example creates a `DmuByteRanges_t` named `b`, adds a `DmuByteRange_t` to it, then clears a byte range:

```
DmuByteRanges_t b;
int i;
```

```
b.setByteRange(0,40960);  
b.clearByteRange(4096,8191);  
printf("Num byte ranges %d\n",b.numByteRanges());  
for (i = 0; i < b.numByteRanges(); i++)  
    printf("%lld %lld\n",b.entry[i].start_off, b.entry[i].end_off);
```

The output to stdout would be as follows:

```
Num byte ranges 2  
0 4095  
8192 40960
```

---

**Note:** The `toByteRangesImage()` member function is not yet supported.

---

## DmuCompletion\_t

The `DmuCompletion_t` object is returned by one of the API request completion subroutines (see "Request-Completion Subroutines" on page 727) with the results of an asynchronous request.

The public member fields and functions of this class are as follows:

|                           |                                                                                                                                                                                                                                                                                                                                                          |
|---------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>fhandle</code>      | Specifies the file handle of the file associated with the request.                                                                                                                                                                                                                                                                                       |
| <code>reply_code</code>   | Contains the overall success or failure status of the request. If this value is <code>DmuNoError</code> , the request was successful. If not, the output from the <code>errs</code> parameter from <code>DmuGetNextReply()</code> should be checked for the appropriate error information; see " <code>DmuGetNextReply()</code> Subroutine" on page 730. |
| <code>request_id</code>   | Associates the completion object with an asynchronous request that was previously issued. This value coincides with the request ID value that any of the asynchronous subroutines return to the user.                                                                                                                                                    |
| <code>request_type</code> | Specifies the type of the original request.                                                                                                                                                                                                                                                                                                              |
| <code>ureq_data</code>    | Specifies a pointer to user request-type specific data. For a <code>fullstat</code> user request, this will point to a                                                                                                                                                                                                                                   |

DmuFullstat\_t object. This field has no meaning for Put, Get, or Copy user requests.

### DmuCopyRange\_t

The DmuCopyRange\_t object defines a range of bytes that are to be associated with a Copy request.

The public member fields and functions of this class are as follows:

|            |                                                                                           |
|------------|-------------------------------------------------------------------------------------------|
| dst_offset | Specifies the starting offset in bytes in the destination file to which the copy is sent. |
| src_length | Specifies the length in bytes of the range to be copied.                                  |
| src_offset | Specifies the starting offset in bytes of the range in the source file to be copied.      |

### DmuCopyRanges\_t

The DmuCopyRanges\_t class defines an array of DmuCopyRange\_t objects that are to be associated with a Copy request.

The public member fields and functions of this class are as follows:

|                   |                                                                                                              |
|-------------------|--------------------------------------------------------------------------------------------------------------|
| entry             | Specifies a read-only pointer allowing access to all the DmuCopyRange_t entries in the array.                |
| numCopyRanges()   | Returns the number of DmuCopyRange_t objects contained in the entry array. Only a single range is supported. |
| resetCopyRanges() | Resets the number of DmuCopyRange_t objects in the array to zero.                                            |
| rounding          | Specifies the rounding method to be used to validate range addresses. Only DMU_RND_NONE is supported.        |

`setCopyRange`                      Adds a new `DmuCopyRange_t` object to the array.

**Example:** Create a `DmuCopyRanges_t`, add a `DmuCopyRange_t` to it, then print the entry to `stdout`:

```
DmuCopyRanges_t copyranges;
int              i;

copyranges.rounding = DMU_RND_NONE;
copyranges.setCopyRange(0, 4096, 0);

for (i = 0; i < copyranges.numCopyRanges(); i++) {
    fprintf(stdout, "source offset %llu, length %llu, "
        "destination offset %llu\n",
        copyranges.entry[i].src_offset,
        copyranges.entry[i].src_length,
        copyranges.entry[i].dst_offset);
}
```

## **DmuErrorHandler\_f**

The `DmuErrorHandler_f` object defines a user-specified error handling subroutine. Many of the API subroutines may result in the receipt of error information from the `dmusrcmd` process or the DMF daemon in the processing of the request. As these errors are received, they are formatted into a `DmuErrInfo_t` object (see "`DmuErrInfo_t`" on page 695) and are generally returned to the caller either via a calling parameter or as part of a `DmuCompletion_t` object.

In addition, however, if the error occurs in the course of processing internal protocol messages, the `DmuErrInfo_t` object can also be passed into the `DmuErrorHandler_f` that the caller defined when the opaque context was created.

As part of the `DmuCreateContext()` API subroutine call, the caller can specify a site-defined `DmuErrorHandler_f` subroutine or the caller can use one of the following API-supplied subroutines:

`DmuDefErrorHandler`                      Outputs the severity of error and the message associated with the error to `stderr`.

`DmuNullErrorHandler` Does nothing with the error.

## `DmuErrInfo_t`

The `DmuErrInfo_t` object contains the information about a single error occurrence.

The public member fields and functions of this class are as follows:

|                       |                                                                                                                                                                                                                                                                                                         |
|-----------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>errcode</code>  | Specifies an integer value generated by the originating routine. This code may have many different meanings for a single value, depending on who the originator is.                                                                                                                                     |
| <code>errwho</code>   | Specifies an integer value that describes in more detail the originator of the error. Use the <code>DmuLogGetErrWhoImage()</code> subroutine to access a character string corresponding to this value.                                                                                                  |
| <code>group</code>    | Defines the originator of the error:<br><br><code>sgi_dmf</code> (DMF routine)<br><code>sgi_dmf_site</code> (site-defined policy routine)                                                                                                                                                               |
| <code>host</code>     | Specifies a character pointer to a string that contains the hostname where the error originated.                                                                                                                                                                                                        |
| <code>message</code>  | Specifies a character pointer to a string that contains the body of the error message.                                                                                                                                                                                                                  |
| <code>position</code> | Specifies a character pointer to a string that contains the position of where the error was generated. For example, this could be a pointer to a character string generated using the <code>__FILE__</code> and <code>__LINE__</code> <code>cpp(1)</code> macros. This field may be <code>NULL</code> . |
| <code>severity</code> | Specifies an integer value that describes the severity of the error. Use the <code>DmuLogGetSeverityImage()</code> subroutine to access a character string corresponding to this value.                                                                                                                 |

## `DmuError_t`

The `DmuError_t` object is the type that most of the API subroutines pass as a return code. The definition `DmuNoError` is the general success return code.

### DmuEvents\_t

The `DmuEvents_t` object defines the various event mask settings that a file may contain.

Valid settings are defined as the logical OR of any of the following:

|                                 |                                                                              |
|---------------------------------|------------------------------------------------------------------------------|
| <code>DMF_EVENT_DESTROY</code>  | Generates a kernel event for each <code>Destroy</code> request on the file.  |
| <code>DMF_EVENT_READ</code>     | Generates a kernel event for each <code>Read</code> request on the file.     |
| <code>DMF_EVENT_TRUNCATE</code> | Generates a kernel event for each <code>Truncate</code> request on the file. |
| <code>DMF_EVENT_WRITE</code>    | Generates a kernel event for each <code>Write</code> request on the file.    |

### DmuFhandle\_t

The `DmuFhandle_t` object contains the ASCII representation of the file `fhandle` as it is known on the host on which the file's filesystem is native.

The public member fields and functions of this class are as follows:

|                                 |                                                                                 |
|---------------------------------|---------------------------------------------------------------------------------|
| <code>fromFhandleImage()</code> | Copies an ASCII file handle image string into the <code>hanp</code> field.      |
| <code>hanp</code>               | Specifies a character array containing the file handle.                         |
| <code>is_valid()</code>         | Verifies the validity of the <code>hanp</code> field.                           |
| <code>toFhandleImage()</code>   | Copies the <code>hanp</code> field into a <code>DmuStringImage_t</code> object. |

### DmuFsysInfo\_t

The `DmuFsysInfo_t` object contains the subset of DMF filesystem configuration information that may be relevant to a user command.

The public member functions of this class are as follows:

|                                                        |                                                                                                                                                                                                                          |
|--------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>bool supports (DmuOperandType_t op_type);</code> | Returns <code>true</code> if files within the filesystem may be used as operands to a function of <code>op_type</code> . For example, if <code>supports(DmuPutOp)</code> returns <code>true</code> , then it is legal to |
|--------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                      |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
|--------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                                      | perform a Put File request (for example, <code>DmuPutByPathSync()</code> ) for files in the filesystem; however, individual requests may still fail, depending on configuration parameters. See "DmuOperandType_t" on page 700.                                                                                                                                                                                                                                                                                                            |
| <code>is_configured()</code>         | Returns true if the filesystem is defined in the DMF configuration file, either as a managed filesystem or an archive filesystem.                                                                                                                                                                                                                                                                                                                                                                                                          |
| <code>is_managed()</code>            | Returns true if the filesystem is defined in the DMF configuration file and has a <code>MIGRATION_LEVEL</code> value other than <code>archive</code> . Files in managed filesystems can be used for all <code>libdmfusr.so</code> file request subroutines (such as <code>put</code> or <code>get</code> ), with the exception that they cannot be the source file of an archive request ( <code>DmuArchiveAsync/DmuArchiveSync</code> ).                                                                                                  |
| <code>is_unmanaged()</code>          | Returns true if the filesystem is defined in the DMF configuration file and has a <code>MIGRATION_LEVEL</code> value of <code>archive</code> . Files in archive filesystems can be used as the source of an archive request ( <code>DmuArchiveAsync/DmuArchiveSync</code> ) or the destination of a copy request ( <code>DmuCopyAsync_2/DmuCopySync_2</code> ). (However, see <code>min_archive_file_size()</code> .) Archive filesystems do not support Put, Get, or Settag requests, and cannot be used as the source of a Copy request. |
| <code>min_archive_file_size()</code> | Specifies the smallest file size that should be submitted in an archive request for this filesystem, or a copy request when this filesystem is the destination of the copy request. This only applies to filesystems for which <code>is_unmanaged()</code> is true.                                                                                                                                                                                                                                                                        |

### DmuFullRegbuf\_t

The `DmuFullRegbuf_t` object defines the DMF fullregion buffer information for a file.

The public member fields and functions of this class are as follows:

`arrcnt` Specifies the number of regions in the `regions` array.

|         |                                                                                                  |
|---------|--------------------------------------------------------------------------------------------------|
| regcnt  | Specifies the number of regions in the regions array that are valid. Only 0 and 1 are supported. |
| regions | Specifies a DmuFullRegion_t array. See "DmuFullRegion_t" on page 698.                            |

### DmuFullRegion\_t

The DmuFullRegion\_t object defines a file region from address *A* (rg\_offset) to address *B* (rg\_offset + rg\_size) that has a different event mask (described by rg\_flags below) from the regions adjacent to it. The object also defines state. When there is more than one region, the file is partial state.

The public member fields and functions of this class are as follows:

|           |                                                                               |
|-----------|-------------------------------------------------------------------------------|
| rg_fbits  | (Reserved for future use.)                                                    |
| rg_flags  | Defines the region event flag bitmask. See "DmuEvents_t" on page 696.         |
| rg_offset | Defines the region starting offset in bytes. The start of the file is byte 0. |
| rg_size   | Defines the region size in bytes.                                             |
| rg_state  | Defines the region file state. Valid states are:                              |
|           | DMU_ST_ARCHIVING      Archiving                                               |
|           | DMU_ST_DUALSTATE      Dual-state                                              |
|           | DMU_ST_MIGRATING      Migrating                                               |
|           | DMU_ST_NOMIGR      No migration allowed                                       |
|           | DMU_ST_OFFLINE      Offline                                                   |
|           | DMU_ST_REGULAR      Regular                                                   |
|           | DMU_ST_UNMIGRATING      Unmigrating                                           |

### DmuFullstat\_t

The DmuFullstat\_t object is a user-accessible version of the internal DMF fullstat object. It contains all of the basic stat(2) information regarding the file, as well as all of the DMAPI-related fields.



The public member fields and functions of this class are as follows:

|                           |                                                                                                                                                                          |
|---------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>attr</code>         | Specifies a <code>DmuAttr_t</code> object that defines the DMF attribute of the file. See "DmuAttr_t" on page 687.                                                       |
| <code>evmask</code>       | Specifies a <code>DmuEvents_t</code> object that defines the event mask for the file. See "DmuEvents_t" on page 696.                                                     |
| <code>host</code>         | Specifies the hostname where the file is native.                                                                                                                         |
| <code>inconsistent</code> | Indicates that the <code>DmuFullstat_t</code> object has inconsistencies in the fields.                                                                                  |
| <code>is_valid()</code>   | Returns 1 if the <code>DmuFullstat_t</code> is valid.                                                                                                                    |
| <code>mntpt</code>        | Specifies a <code>DmuOpaque_t</code> object (defined in <code>libdmfcom.H</code> ) defining the mount point of the filesystem containing the file on <code>host</code> . |
| <code>regbuf</code>       | Specifies a <code>DmuRegionbuf_t</code> object that defines the regions of the file. See "DmuRegionbuf_t" on page 701.                                                   |
| <code>relpath</code>      | Specifies the relative path of the file in <code>mntpt</code> on <code>host</code> .                                                                                     |
| <code>stat</code>         | Specifies a <code>DmuStat_t</code> object that contains the fields representing those in the <code>stat(5)</code> structure. See the <code>stat(2)</code> system call.   |

### **DmuFullstat\_2\_t**

The `DmuFullstat_2_t` object is a user-accessible version of the internal DMF `fullstat` object. It contains all of the basic `stat(2)` information regarding the file, as well as all of the DMAPI-related fields.

The public member fields and functions of this class are as follows:

|                           |                                                                                                                                                                          |
|---------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>attr</code>         | Specifies a <code>DmuAttr_t</code> object that defines the DMF attribute of the file. See "DmuAttr_t" on page 687.                                                       |
| <code>evmask</code>       | Specifies a <code>DmuEvents_t</code> object that defines the event mask for the file. See "DmuEvents_t" on page 696.                                                     |
| <code>host</code>         | Specifies the hostname where the file is native.                                                                                                                         |
| <code>inconsistent</code> | Indicates that the <code>DmuFullstat_2_t</code> object has inconsistencies in the fields.                                                                                |
| <code>is_valid()</code>   | Returns 1 if the <code>DmuFullstat_2_t</code> is valid.                                                                                                                  |
| <code>mntpt</code>        | Specifies a <code>DmuOpaque_t</code> object (defined in <code>libdmfcom.H</code> ) defining the mount point of the filesystem containing the file on <code>host</code> . |
| <code>regbuf</code>       | Specifies a <code>DmuRegionbuf_t</code> object that defines the regions of the file. See "DmuRegionbuf_t" on page 701.                                                   |
| <code>relpath</code>      | Specifies the relative path of the file in <code>mntpt</code> on <code>host</code> .                                                                                     |
| <code>stat</code>         | Specifies a <code>DmuStat_2_t</code> object that contains the fields representing those in the <code>stat(5)</code> structure. See the <code>stat(2)</code> system call. |

### **DmuOperandType\_t**

The `DmuOperandType_t` object is an enum data type that is defined in `libdmfcom.H` and it is used as an operand to `DmuFsysInfo_t::supports()`. Its values are:

`DmuPutOp`  
`DmuGetOp`  
`DmuCopySrcOp`  
`DmuCopyDstOp`  
`DmuFstatOp`  
`DmuSettagOp`  
`DmuArchiveSrcOp`  
`DmuArchiveDstOp`  
`DmuSetProjidOp`

## DmuPriority\_t

The `DmuPriority_t` object defines the priority of the request.

Valid settings are defined as follows:

|                               |                                                                                                                                                                                                                                                                                                                                                  |
|-------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>DMU_DEF_PRIORITY</code> | Defines the default priority of the request. You should use <code>DMU_DEF_PRIORITY</code> in any function calls with a deferred priority parameter to guarantee forward compatibility. DMF translates <code>DMU_DEF_PRIORITY</code> to a default value that is within the range <code>DMU_MIN_PRIORITY</code> to <code>DMU_MAX_PRIORITY</code> . |
| <code>DMU_MIN_PRIORITY</code> | Defines the minimum priority.                                                                                                                                                                                                                                                                                                                    |
| <code>DMU_MAX_PRIORITY</code> | Defines the maximum priority.                                                                                                                                                                                                                                                                                                                    |

## DmuRegion\_t

The `DmuRegion_t` object defines a file region from address *A* (`rg_offset`) to address *B* (`rg_offset + rg_size`) that has a different event mask (described by `rg_flags` below) from the regions adjacent to it. When there is more than one region, the file is partial state.

The public member fields and functions of this class are as follows:

|                        |                                                                                      |
|------------------------|--------------------------------------------------------------------------------------|
| <code>rg_flags</code>  | Defines the region event flag bitmask. See " <code>DmuEvents_t</code> " on page 696. |
| <code>rg_offset</code> | Defines the region starting offset in bytes. The start of the file is byte 0.        |
| <code>rg_size</code>   | Defines the region size in bytes.                                                    |

## DmuRegionbuf\_t

The `DmuRegionbuf_t` object defines the file region buffer information for a file.

The public member fields and functions of this class are as follows:

|                     |                                                                                   |
|---------------------|-----------------------------------------------------------------------------------|
| <code>arrcnt</code> | Specifies the number of regions in the <code>regions</code> array.                |
| <code>regcnt</code> | Specifies the number of regions in the <code>regions</code> array that are valid. |

`regions` Specifies the `DmuRegion_t` array. See the `DmuRegion_t` description.

### **DmuReplyOrder\_t**

The `DmuReplyOrder_t` object selects the order in which asynchronous replies are to be returned by the API reply processing subroutines.

Valid settings are defined as follows:

|                          |                                                        |
|--------------------------|--------------------------------------------------------|
| <code>DmuAnyOrder</code> | Returns replies in the order the replies are received. |
| <code>DmuReqOrder</code> | Returns replies in the order the requests were issued. |

### **DmuReplyType\_t**

The `DmuReplyType_t` object is used to select the type of reply that an API can receive after sending a request. All requests will receive a final reply when the `dmusrCmd` process has completed processing the request, whether it was successful or not.

Valid settings are defined as follows:

|                          |                                                                                                                                                                                                                                                                                                                                                                          |
|--------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>DmuIntermed</code> | Specifies an intermediate reply, an informational message to alert the caller that the request is being processed and may not complete for some time. An example of this is the intermediate reply that is sent when a <code>put</code> request has been forwarded to an MSP or LS for processing and the completion reply is deferred until that operation is complete. |
| <code>DmuFinal</code>    | Specifies the final reply for the request.                                                                                                                                                                                                                                                                                                                               |

This definition is used to specify the types of replies that some of the reply processing subroutines defined below are to consider.

### **DmuSeverity\_t**

The `DmuSeverity_t` object specifies the level of message reporting.

Valid settings are defined as follows:

|                           |                                   |
|---------------------------|-----------------------------------|
| <code>DmuSevDebug4</code> | Highest level of debug reporting. |
|---------------------------|-----------------------------------|

|                            |                                          |
|----------------------------|------------------------------------------|
| <code>DmuSevDebug3</code>  | Second-highest level of debug reporting. |
| <code>DmuSevDebug2</code>  | Third-highest level of debug reporting.  |
| <code>DmuSevDebug1</code>  | Lowest level of debug reporting.         |
| <code>DmuSevVerbose</code> | Verbose message reporting.               |
| <code>DmuSevInform</code>  | Informative message reporting.           |
| <code>DmuSevWarn</code>    | Warning message reporting.               |
| <code>DmuSevFatal</code>   | Error message reporting.                 |

### **DmuVolGroup\_t**

The `DmuVolGroup_t` object defines a volume group (VG) name. As an entry in a `DmuVolGroups_t` array, it is used to specify one of the VGs to be used for a DMF put request. For more information about VGs, see "How DMF Software Works" on page 14.

The public member field and function of this class is as follows:

|                    |                                                                              |
|--------------------|------------------------------------------------------------------------------|
| <code>vname</code> | Specifies a character pointer to a string containing the name of a valid VG. |
|--------------------|------------------------------------------------------------------------------|

### **DmuVolGroups\_t**

The `DmuVolGroups_t` object defines an array of `DmuVolGroup_t` objects. This object is used to specify the list of VGs to which a caller would like a file to be written in a DMF put request.

The public member fields and functions of this class are as follows:

|                                   |                                                                                                                          |
|-----------------------------------|--------------------------------------------------------------------------------------------------------------------------|
| <code>clearVolGroup()</code>      | Removes a <code>DmuVolGroup_t</code> object from the internal <code>DmuVolGroup_t</code> array.                          |
| <code>fromVolGroupsImage()</code> | Converts a string image of the following format to a <code>DmuVolGroups_t</code> object:<br><br><i>vname1 vname2 ...</i> |

The delimiter between multiple `vname` values may be a space, a tab, or a comma.

|                                 |                                                                                                                                                                                                                                                                                           |
|---------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>numVolGroups()</code>     | <b>Returns the number of <code>DmuVolGroup_t</code> objects in the internal <code>DmuVolGroup_t</code> array.</b>                                                                                                                                                                         |
| <code>resetVolGroups()</code>   | <b>Clears the internal <code>DmuVolGroup_t</code> array.</b>                                                                                                                                                                                                                              |
| <code>setVolGroup()</code>      | <b>Adds a <code>DmuVolGroup_t</code> object to the internal <code>DmuVolGroup_t</code> array.</b>                                                                                                                                                                                         |
| <code>toVolGroupsImage()</code> | <b>Converts a <code>DmuVolGroups_t</code> object to a <code>DmuStringImage_t</code> (defined in <code>libdmfcom.H</code>) in the following format:</b><br><br><i>vname1 vname2 ...</i><br><br>The delimiter between multiple <code>vname</code> values may be a space, a tab, or a comma. |

## User-Accessible API Subroutines for `libdmfusr.so.2`

This section describes the following types of user-accessible API subroutines:

- "Context-Manipulation Subroutines" on page 705
- "Filesystem-Information Subroutine" on page 708
- "DMF File-Request Subroutines" on page 709
- "Request-Completion Subroutines" on page 727

### Context-Manipulation Subroutines

The `DmuContext_t` object manipulated by the `DmuCreateContext()`, `DmuDestroyContext()`, and `DmuChangedDirectory()` subroutines is designed to be completely opaque to the application. The context is used on all API subroutine calls so that the API can successfully manage user request and reply processing, but its internal contents are of no interest or use to the application.

You can use multiple `DmuContext_t` objects within the same process if desired.

#### `DmuCreateContext()` Subroutine

The `DmuCreateContext()` subroutine creates an opaque context for the API to use to correctly communicate with the `dmusrcmd` process. This subroutine should be the first API subroutine called by a DMF user command. Not only is the context created, but the communication channel to the `dmusrcmd` process is initialized.

Normally, a context would be used for multiple requests and only destroyed when no more requests are to be made. Creating and destroying a context for each request is likely to be inefficient if done frequently.

The prototype is as follows:

```
extern DmuError_t
DmuCreateContext(
    const char          *prog_name,
    DmuCreateFlags_t   create_flags,
    DmuSeverity_t       severity,
    DmuErrHandler_f    err_handler,
    DmuContext_t       *dmuctxt,
    pid_t               *child_pid,
```

DmuAllErrors\_t \*errs)

The parameters are as follows:

|              |                                                                                                                                                                                                                                                                                           |
|--------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| child_pid    | Specifies the process ID (PID) of the child that is forked and executed to create the dmusrcmd process. This value is returned to the caller so that the caller is free to handle the termination of child signals as desired.                                                            |
| create_flags | Specifies a DmuCreateFlags_t object (defined in libdmfusr.H) that specifies create options. The only valid create_flags option is:<br><br>CREATE_CHDIR<br><br>Allows change-directory requests via the DmuChangedDirectory() routine. See "DmuChangedDirectory() Subroutine" on page 707. |
| dmuctxt      | Specifies a DmuContext_t object (defined in libdmfusr.H) that is returned with the address of the newly created API to be used on all subsequent subroutine calls that require the program's API context.                                                                                 |
| err_handler  | Specifies a user-defined error handling subroutine. The DmuErrHandler_f object is defined in libdmfusr.H. If the err_handler parameter is NULL, the default error handler DmuDefErrHandler is used. For more information, see "DmuErrHandler_f" on page 694.                              |
| errs         | Specifies a pointer to a DmuAllErrors_t object. This value may be NULL. If it is not NULL, the subroutine will use it to return errors. See "DmuAllErrors_t" on page 686.                                                                                                                 |
| prog_name    | Contains the name of the program. This field can be the full pathname of the program or some other representation.                                                                                                                                                                        |
| severity     | Specifies a DmuSeverity_t object that specifies the level of error reporting. See "DmuSeverity_t" on page 702.                                                                                                                                                                            |

If the DmuCreateContext call completes successfully, it returns DmuNoError.



**DmuChangedDirectory() Subroutine**

The `DmuChangedDirectory` subroutine changes the current directory of the context. This subroutine is useful to a process that will be making multiple API file requests using relative pathnames while the process might also be making `chdir(3)` subroutine calls.

When a process makes a `chdir` call, if the `DmuChangedDirectory()` subroutine is called before the next API file request that references a relative pathname is made, the file reference will be successfully made by the process.

The prototype is as follows:

```
extern DmuError_t
DmuChangedDirectory(
    const DmuContext_t    dmuctxt,
    const char            *new_directory,
    DmuAllErrors_t    *errs);
```

|                            |                                                                                                                                                                                                                    |
|----------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>dmuctxt</code>       | Specifies a <code>DmuContext_t</code> object that was previously created by <code>DmuCreateContext()</code> .                                                                                                      |
| <code>errs</code>          | Specifies a pointer to a <code>DmuAllErrors_t</code> object. This value may be <code>NULL</code> . If it is not <code>NULL</code> , the subroutine will use it to return errors. See "DmuAllErrors_t" on page 686. |
| <code>new_directory</code> | Specifies a read-only character pointer to the string containing the directory path that was passed on the last <code>chdir(3)</code> subroutine call.                                                             |

**DmuDestroyContext() Subroutine**

The `DmuDestroyContext()` subroutine destroys the API context `dmuctxt`. The memory that had been allocated for its use is freed.

The prototype is as follows:

```
extern DmuError_t
DmuDestroyContext(
    DmuContext_t    dmuctxt,
    DmuAllErrors_t    *errs)
```

The parameters are as follows:

|                      |                                                                                                                                                                                                                                   |
|----------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>dmuctxt</code> | Specifies a <code>DmuContext_t</code> object that was previously created by <code>DmuCreateContext()</code> .                                                                                                                     |
| <code>errs</code>    | Specifies a pointer to a <code>DmuAllErrors_t</code> object. This value may be <code>NULL</code> . If it is not <code>NULL</code> , the subroutine will use it to return errors. See " <code>DmuAllErrors_t</code> " on page 686. |

### Filesystem-Information Subroutine

The `DmuFilesysInfo()` routine returns DMF configuration information about a filesystem. The `dmarchive(1)` command uses this routine to determine whether it can issue an archive or copy request to the DMF daemon when copying data between a source and target.

The `DmuFilesysInfo()` subroutine does not return until the request has either completed successfully or been aborted due to an error condition.

Upon success, a `DmuFsysInfo_t` object is transferred to the caller.

The prototype is as follows:

```
DmuError_t
DmuFilesysInfo(
    const DmuContext_t  dmuctxt,
    const char          *dmf_path,
    const char          *fsys_path,
    int                 flags,
    DmuFsysInfo_t      *fsys_info,
    DmuAllErrors_t      *errs);
```

The parameters are as follows:

|                       |                                                                                                                                                    |
|-----------------------|----------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>dmf_path</code> | Specifies a path on a managed filesystem, used only for the purposes of locating the DMF server.                                                   |
| <code>dmuctxt</code>  | Specifies a <code>DmuContext_t</code> object that was previously created by <code>DmuCreateContext()</code> .                                      |
| <code>errs</code>     | Specifies a pointer to a <code>DmuAllErrors_t</code> object. This value may be <code>NULL</code> . If it is not <code>NULL</code> , the subroutine |

|           |                                                                                                                                                                        |
|-----------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|           | will use it to return errors. See "DmuAllErrors_t" on page 686.                                                                                                        |
| flags     | Specifies one of the flags found in /usr/lib/dmf/libdmfcom.H as FS_INFO*.                                                                                              |
| fsys_info | Specifies the pointer that will be returned with the DmuFsysInfo_t object.                                                                                             |
| fsys_path | Specifies a path on the filesystem for which you want configuration information. It does not need to be on a managed filesystem, nor does it need to be a mount point. |

If the routine succeeds, it returns `DmuNoError`.

## DMF File-Request Subroutines

Each of the following subroutines makes a DMF file request:

- "Copy File Requests" on page 710
- "Archive File Requests" on page 712
- "Fullstat Requests" on page 714
- "Put File Requests" on page 717
- "Get File Requests" on page 720
- "Setprojid File Requests" on page 723
- "Settag File Requests" on page 725

The context parameter that is included in each of these subroutines must have been already initialized via `DmuCreateContext`.

## Copy File Requests

The `DmuCopyAsync_2()` and `DmuCopySync_2()` subroutines perform copy requests in the manner of the `dmcopy(1)` command. The `dmarchive(1)` command also issues copy requests when copying from files that are in a migrated state in a managed filesystem.

The `DmuCopyAsync_2()` subroutine returns immediately after the copy request has been forwarded to the `dmusrcmd` process. If a reply is desired, the caller must process the reply to this request. See "Request-Completion Subroutines" on page 727.

The `DmuCopySync_2()` subroutine does not return until the requested copy has either completed successfully or been aborted due to an error condition.

The prototypes are as follows:

```
extern DmuError_t
DmuCopyAsync_2(
    const DmuContext_t    dmuctxt,
    const char            *srcfile_path,
    const char            *dstfile_path,
    const char            *pref_vgmg,
    DmuCopyFlags_t       copy_flags,
    const DmuCopyRanges_t *copyranges,
    DmuPriority_t         priority,
    DmuReqid_t           *request_id,
    DmuAllErrors_t       *errs)

extern DmuError_t
DmuCopySync_2(
    const DmuContext_t    dmuctxt,
    const char            *srcfile_path,
    const char            *dstfile_path,
    const char            *pref_vgmg,
    DmuCopyFlags_t       copy_flags,
    const DmuCopyRanges_t *copyranges,
    DmuPriority_t         priority,
    DmuAllErrors_t       *errs)
```

The parameters are as follows:

|                         |                                                                                                         |
|-------------------------|---------------------------------------------------------------------------------------------------------|
| <code>copy_flags</code> | Specifies the OR'd value of the following copy operation flags as defined in <code>libdmfcom.H</code> : |
|-------------------------|---------------------------------------------------------------------------------------------------------|

- `COPY_CANCEL` — Cancel matching request
- `COPY_ADDR_ALIGN` — Allow an address in the destination file that is greater than the size of the file
- `COPY_NONE` — No flags specified
- `COPY_NOWAIT` — Return immediately if the daemon is not available to process the request (do not wait)
- `COPY_PRESV_DFILE` — Do not truncate the destination file before the `copy` operation
- `COPY_REPRI` — Reprioritize matching request

---

**Note:** The following flags may only be set by the `root` user on the DMF server or on a `VALID_ROOT_HOSTS` server:

`COPY_CANCEL`  
`COPY_REPRI`

See "base Object Parameters" on page 278.

---

|                           |                                                                                                                                                                                                                                                                                                                  |
|---------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>copyranges</code>   | Specifies a pointer to a <code>DmuCopyRanges_t</code> object, as defined in " <code>DmuCopyRanges_t</code> " on page 693 and in <code>libdmfcom.H</code> . This object can have only one <code>DmuCopyRange_t</code> as defined in " <code>DmuCopyRange_t</code> " on page 693 and in <code>libdmfcom.H</code> . |
| <code>dmuctxt</code>      | Specifies a <code>DmuContext_t</code> object that was previously created by <code>DmuCreateContext()</code> .                                                                                                                                                                                                    |
| <code>dstfile_path</code> | Specifies the pathname of the destination (output) file for the <code>copy</code> operation. This path must point to a file that exists or can be created on a filesystem visible from the DMF server and any parallel data-mover nodes. See also "DMF Direct Archiving Requirements" on page 50.                |
| <code>errs</code>         | Specifies a pointer to a <code>DmuAllErrors_t</code> object. This value may be <code>NULL</code> . If it is not <code>NULL</code> , the subroutine will use it to return errors. See " <code>DmuAllErrors_t</code> " on page 686.                                                                                |

|              |                                                                                                                                                                                                                                                                                                                                                                                         |
|--------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| pref_vgmg    | Specifies a list of MSP, volume group, or migrate group names from which the file should be copied if possible. If the file has a copy in one of the elements in the list, the DMF daemon will attempt to copy the file first using that copy, overriding the default copy order as defined in the DMF configuration file. This option is only available to the <code>root</code> user. |
| priority     | Specifies a <code>DmuPriority_t</code> object (defined in <code>libdmfcom.H</code> ) that defines the request priority.                                                                                                                                                                                                                                                                 |
| request_id   | Specifies a pointer to a <code>DmuReqid_t</code> object (defined in <code>libdmfcom.H</code> ) parameter that will be returned with the unique request ID of the asynchronous request. This value can be used when processing <code>DmuCompletion_t</code> objects (see "Request-Completion Subroutines" on page 727).                                                                  |
| srcfile_path | Specifies the pathname of the source (input) file for the copy operation. It must be an offline or dual-state DMF file.                                                                                                                                                                                                                                                                 |

If the subroutine succeeds, it returns `DmuNoError`.

### Archive File Requests

The `DmuArchiveAsync()` and `DmuArchiveSync()` subroutines perform archive requests in the manner of the `dmarchive(1)` command, when `dmarchive` is operating in the mode of copying files from an archive filesystem to a managed filesystem.

The `DmuArchiveAsync()` subroutine returns immediately after the archive request has been forwarded to the `dmusrcmd` process. If a reply is desired, the caller must process the reply to this request. See "Request-Completion Subroutines" on page 727.

The `DmuArchiveSync()` subroutine does not return until the requested archive has either completed successfully or been aborted due to an error condition.

The prototypes are as follows:

```
extern DmuError_t
DmuArchiveAsync(
    const DmuContext_t  dmuctxt,
    const char          *src_path,
```

```

        const char          *dst_path,
        const DmuVolGroups_t *volgroups,
        int                 arch_flags,
        DmuPriority_t       priority,
        DmuReqid_t         *request_id,
        DmuAllErrors_t     *errs);

extern DmuError_t
DmuArchiveSync(
    const DmuContext_t  dmuctxt,
    const char          *src_path,
    const char          *dst_path,
    const DmuVolGroups_t *volgroups,
    int                 arch_flags,
    DmuPriority_t       priority,
    DmuAllErrors_t     *errs);

```

The parameters are as follows:

|                         |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
|-------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>arch_flags</code> | <p>Specifies the OR'd value of the following archive operation flags as defined in <code>libdmfcom.H</code>:</p> <ul style="list-style-type: none"> <li>• <code>ARCH_CANCEL</code> — Cancel matching request</li> <li>• <code>ARCH_NONE</code> — No flags specified</li> <li>• <code>ARCH_NOWAIT</code> — Return immediately if the daemon is not available to process the request (do not wait)</li> </ul> <hr/> <p><b>Note:</b> The <code>ARCH_CANCEL</code> flag may only be set by the root user on the DMF server or on a <code>VALID_ROOT_HOSTS</code> server. See "base Object Parameters" on page 278.</p> <hr/> |
| <code>dmuctxt</code>    | <p>Specifies a <code>DmuContext_t</code> object that was previously created by <code>DmuCreateContext()</code>.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| <code>dst_path</code>   | <p>Specifies the pathname of the destination (output) file for the archive operation. This path must refer to a file on a managed filesystem that either does not currently exist or exists and is zero-length.</p>                                                                                                                                                                                                                                                                                                                                                                                                      |

|                         |                                                                                                                                                                                                                                                                                                                        |
|-------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>errs</code>       | Specifies a pointer to a <code>DmuAllErrors_t</code> object. This value may be <code>NULL</code> . If it is not <code>NULL</code> , the subroutine will use it to return errors. See "DmuAllErrors_t" on page 686.                                                                                                     |
| <code>priority</code>   | Specifies a <code>DmuPriority_t</code> object (defined in <code>libdmfcom.H</code> ) that defines the request priority. (Deferred implementation.)                                                                                                                                                                     |
| <code>request_id</code> | Specifies a pointer to a <code>DmuReqid_t</code> object (defined in <code>libdmfcom.H</code> ) parameter that will be returned with the unique request ID of the asynchronous request. This value can be used when processing <code>DmuCompletion_t</code> objects (see "Request-Completion Subroutines" on page 727). |
| <code>src_path</code>   | Specifies the pathname of the source (input) file for the archive operation. It must be a file in a non-DMF managed filesystem. See "DMF Direct Archiving Requirements" on page 50.                                                                                                                                    |
| <code>volgroups</code>  | Specifies a pointer to a <code>DmuVolGroups_t</code> object. See "DmuVolGroups_t" on page 703.                                                                                                                                                                                                                         |

If the subroutine succeeds, it returns `DmuNoError`.

### Fullstat Requests

The following subroutines send a `fullstat` request to the `dmusrcmd` process:

- Current subroutines (as of DMF 6.2)
  - `DmuFullstatByFhandleAsync_2()`
  - `DmuFullstatByFhandleSync_2()`
  - `DmuFullstatByPathAsync_2()`
  - `DmuFullstatByPathSync_2()`
- Legacy subroutines (prior to DMF 6.2):
  - `DmuFullstatByFhandleAsync()`
  - `DmuFullstatByFhandleSync()`
  - `DmuFullstatByPathAsync()`
  - `DmuFullstatByPathSync()`



---

**Note:** If your program must work on versions of DMF prior to DMF 6.2, you should use the legacy versions of the routines. However, the project id field is only available in the new (Dmu\*\_2) versions of the routines.

---

These subroutines have the following things in common:

- The 'Sync' versions of these subroutines do not return until the `DmuFullstat_t` has been received or the request has been aborted due to errors.
- The 'Async' versions of these subroutines return immediately after successfully forwarding the `fullstat` request to the `dmusrcmd` process. If a reply is desired, the caller must process the reply to this request. See "Request-Completion Subroutines" on page 727. That is the only way to actually receive the `DmuFullstat_t` object for an 'Async' `fullstat` request, however. The `DmuFullstatCompletion()` subroutine has been supplied to extract the `fullstat` information from a `fullstat` completion object.
- The 'ByPath' versions of these subroutines allow the target file to be defined by its pathname.
- The 'ByFhandle' versions of these subroutines allow the target file to be defined by its filesystem handle, the `fhandle`. These subroutines are valid only when the command making the call is on the DMF server machine, and they are valid only when a user has sufficient (`root`) privileges.

These subroutines can return a successful completion (`DmuNoError`), but might not return valid `DmuFullstat_t` information. The subroutines are designed to return the normal `stat` type information regardless of whether a DMAPI `fullstat` could be successfully completed. Upon return from these subroutines, the caller can use the `DmuFullstat_t is_valid()` member function to verify the validity of the DMAPI information in the `DmuFullstat_t` block.

The ultimate result of this request is the transfer of a `DmuFullstat_t` object to the caller.

The prototypes are as follows:

```
extern DmuError_t
DmuFullstatByFhandleAsync(
    const DmuContext_t  dmuctxt,
    const DmuFhandle_t  *client_fhandle,
    DmuReqid_t          *request_id,
    DmuAllErrors_t      *errs)

extern DmuError_t
DmuFullstatByFhandleSync(
    const DmuContext_t  dmuctxt,
    const DmuFhandle_t  *client_fhandle,
    DmuFullstat_t       *dmufullstat,
    DmuAllErrors_t      *errs)

extern DmuError_t
DmuFullstatByPathAsync(
    const DmuContext_t  dmuctxt,
    const char           *path,
    DmuReqid_t          *request_id,
    DmuAllErrors_t      *errs)

extern DmuError_t
DmuFullstatByPathSync(
    const DmuContext_t  dmuctxt,
    const char           *path,
    DmuFullstat_t       *dmufullstat,
    DmuFhandle_t        *fhandle,
    DmuAllErrors_t      *errs)
```

The parameters are as follows:

- dmuctxt                      Specifies a `DmuContext_t` object that was previously created by `DmuCreateContext()`.
- dmufullstat                Specifies the pointer that will be returned with the `DmuFullstat_t` object.
- client\_fhandle             Specifies the DMF filesystem `fhandle` of the target file. Valid for use only by a privileged (`root`) user on the DMF server machine.

|                         |                                                                                                                                                                                                                                                                                                                        |
|-------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>errs</code>       | Specifies a pointer to a <code>DmuAllErrors_t</code> object. This value may be <code>NULL</code> . If it is not <code>NULL</code> , the subroutine will use it to return errors. See "DmuAllErrors_t" on page 686.                                                                                                     |
| <code>fhandle</code>    | Specifies the pointer that will be returned with the <code>DmuFhandle_t</code> value.                                                                                                                                                                                                                                  |
| <code>path</code>       | Specifies the relative or absolute pathname of the target file.                                                                                                                                                                                                                                                        |
| <code>request_id</code> | Specifies a pointer to a <code>DmuReqid_t</code> object (defined in <code>libdmfcom.H</code> ) parameter that will be returned with the unique request ID of the asynchronous request. This value can be used when processing <code>DmuCompletion_t</code> objects (see "Request-Completion Subroutines" on page 727). |

If the subroutine succeeds, it returns `DmuNoError`.

## Put File Requests

The following subroutines perform the `put` DMF request:

```
DmuPutByFhandleAsync ( )
DmuPutByFhandleSync ( )
DmuPutByPathAsync ( )
DmuPutByPathSync ( )
```

These subroutines have the following things in common:

- The 'Sync' versions do not return until the `put` request has either completed successfully, or been aborted due to errors.
- The 'Async' versions return immediately after successfully forwarding the `put` request to the `dmusrcmd` process. If a reply is desired, the caller must process the reply to this request. See "Request-Completion Subroutines" on page 727.
- The 'ByPath' versions allow the target file to be defined by its pathname.
- The 'ByFhandle' versions allow the target file to be defined by its filesystem handle, the `fhandle`. These subroutines are valid only when the command making the call is on the DMF server machine, and they are valid only when a user has sufficient (`root`) privileges.

The prototypes are as follows:

```
extern DmuError_t
DmuPutByFhandleAsync(
    const DmuContext_t    dmuctxt,
    const DmuFhandle_t    *client_fhandle,
    DmuMigFlags_t         mig_flags,
    const DmuByteRanges_t *byteranges,
    const DmuVolGroups_t  *volgroups,
    DmuPriority_t          priority,
    DmuReqid_t             *request_id,
    DmuAllErrors_t        *errs)
```

```
extern DmuError_t
DmuPutByFhandleSync(
    const DmuContext_t    dmuctxt,
    const DmuFhandle_t    *client_fhandle,
    DmuMigFlags_t         mig_flags,
    const DmuByteRanges_t *byteranges,
    const DmuVolGroups_t  *volgroups,
    DmuPriority_t          priority,
    DmuAllErrors_t        *errs)
```

```
extern DmuError_t
DmuPutByPathAsync(
    const DmuContext_t    dmuctxt,
    const char             *path,
    DmuMigFlags_t         mig_flags,
    const DmuByteRanges_t *byteranges,
    const DmuVolGroups_t  *volgroups,
    DmuPriority_t          priority,
    DmuReqid_t             *request_id,
    DmuAllErrors_t        *errs)
```

```
extern DmuError_t
DmuPutByPathSync(
    const DmuContext_t    dmuctxt,
    const char             *path,
    DmuMigFlags_t         mig_flags,
    const DmuByteRanges_t *byteranges,
    const DmuVolGroups_t  *volgroups,
```

```
DmuPriority_t    priority,
DmuAllErrors_t  *errs)
```

The parameters are as follows:

|                             |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
|-----------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>byteranges</code>     | Specifies a pointer to a <code>DmuByteRanges_t</code> object. See "DmuByteRanges_t" on page 689.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| <code>client_fhandle</code> | Specifies the DMF filesystem <code>fhandle</code> of the target file. Valid for use only by a privileged ( <code>root</code> ) user on the DMF server machine.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| <code>dmuctxt</code>        | Specifies a <code>DmuContext_t</code> object that was previously created by <code>DmuCreateContext()</code> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
| <code>errs</code>           | Specifies a pointer to a <code>DmuAllErrors_t</code> object. This value may be <code>NULL</code> . If it is not <code>NULL</code> , the subroutine will use it to return errors. See "DmuAllErrors_t" on page 686.                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
| <code>mig_flags</code>      | Specifies the following migration flags as defined in <code>libdmfcom.H</code> : <ul style="list-style-type: none"> <li>• <code>MIG_CANCEL</code> — Cancel matching request</li> <li>• <code>MIG_FREE</code> — Free the space associated with the file</li> <li>• <code>MIG_NONE</code> — No flags specified</li> <li>• <code>MIG_NOWAIT</code> — Return immediately if the daemon is not available to process the request (do not wait)</li> </ul> <hr/> <p><b>Note:</b> The <code>MIG_CANCEL</code> flag may only be set by the <code>root</code> user on the DMF server or on a <code>VALID_ROOT_HOSTS</code> server. See "base Object Parameters" on page 278.</p> <hr/> |
| <code>path</code>           | Specifies the relative or full pathname of the target file.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
| <code>priority</code>       | Specifies a <code>DmuPriority_t</code> object (defined in <code>libdmfcom.H</code> ) that defines the request priority. (Deferred implementation.)                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
| <code>request_id</code>     | Specifies a pointer to a <code>DmuReqid_t</code> object (defined in <code>libdmfcom.H</code> ) parameter that will be returned with                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |

the unique request ID of the asynchronous request. This value can be used when processing `DmuCompletion_t` objects (see "Request-Completion Subroutines" on page 727).

`volgroups` Specifies a pointer to a `DmuVolGroups_t` object. See "DmuVolGroups\_t" on page 703.

If the subroutine succeeds, it returns `DmuNoError`.

### Get File Requests

The following subroutines perform the `get` DMF request:

```
DmuGetByFhandleAsync_2()  
DmuGetByFhandleSync_2()  
DmuGetByPathAsync_2()  
DmuGetByPathSync_2()
```

These subroutines have the following things in common:

- The 'Sync' versions do not return until the `get` request has either completed successfully or has been aborted due to errors.
- The 'Async' versions return immediately after successfully forwarding the `get` request to the `dmusrcmd` process. If a reply is desired, the caller must process the reply to this request. See "Request-Completion Subroutines" on page 727.
- The 'ByPath' versions of these calls allow the target file to be defined by its pathname.
- The 'ByFhandle' versions allow the target file to be defined by its filesystem handle, the `fhandle`. These subroutines are valid only when the command making the call is on the DMF server machine, and they are valid only when a user has sufficient (`root`) privileges.

The prototypes are as follows:

```
extern DmuError_t  
DmuGetByFhandleAsync_2(  
    const DmuContext_t    dmuctxt,  
    const DmuFhandle_t    *client_fhandle,  
    int                   recall_flags,  
    const DmuByteRanges_t *byteranges,          /* may be NULL */
```

```

        const char          *pref_vgmg,          /* may be NULL */
        DmuPriority_t       priority,
        DmuReqid_t          *request_id,
        DmuAllErrors_t      *errs);

extern DmuError_t
DmuGetByFhandleSync_2(
    const DmuContext_t      dmuctxt,
    const DmuFhandle_t      *client_fhandle,
    int                     recall_flags,
    const DmuByteRanges_t   *byteranges,       /* may be NULL */
    const char              *pref_vgmg,       /* may be NULL */
    DmuPriority_t           priority,
    DmuAllErrors_t          *errs);

extern DmuError_t
DmuGetByPathAsync_2(
    const DmuContext_t      dmuctxt,
    const char              *path,
    int                     recall_flags,
    const DmuByteRanges_t   *byteranges,       /* may be NULL */
    const char              *pref_vgmg,       /* may be NULL */
    DmuPriority_t           priority,
    DmuReqid_t              *request_id,
    DmuAllErrors_t          *errs);

extern DmuError_t
DmuGetByPathSync_2(
    const DmuContext_t      dmuctxt,
    const char              *path,
    int                     recall_flags,
    const DmuByteRanges_t   *byteranges,       /* may be NULL */
    const char              *pref_vgmg,       /* may be NULL */
    DmuPriority_t           priority,
    DmuAllErrors_t          *errs);

```

The parameters are as follows:

**byteranges** Specifies a pointer to a `DmuByteRanges_t` object. See "DmuByteRanges\_t" on page 689.

|                |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
|----------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| client_fhandle | Specifies the DMF filesystem fhandle of the target file. Valid for use only by a privileged (root) user on the DMF server machine.                                                                                                                                                                                                                                                                                                                                                                                                       |
| dmuctxt        | Specifies a DmuContext_t object that was previously created by DmuCreateContext().                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| errs           | Specifies a pointer to a DmuAllErrors_t object. This value may be NULL. If it is not NULL, the subroutine will use it to return errors. See "DmuAllErrors_t" on page 686.                                                                                                                                                                                                                                                                                                                                                                |
| path           | Specifies the relative or full pathname of the target file.                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| pref_vgmg      | Specifies a list of MSP, volume group, or migrate group names from which the files should be recalled if possible. If a file has a copy in one of the elements in the list, the DMF daemon will attempt to recall the file first using that copy, overriding the default recall order as defined in the DMF configuration file. This option is only available to the root user.                                                                                                                                                          |
| priority       | Specifies a DmuPriority_t object (defined in libdmfcom.H) that defines the request priority.                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| recall_flags   | <p>Specifies the following recall flags as defined in libdmfcom.H:</p> <ul style="list-style-type: none"> <li>• RECALL_ETIME — Update the access time of the file. This parameter is only valid with DmuGetByPathAsync_2() and DmuGetByPathSync_2().</li> <li>• RECALL_CANCEL — Cancel matching request</li> <li>• RECALL_NONE — No flags specified</li> <li>• RECALL_NOWAIT — Return immediately if the daemon is not available to process the request (do not wait)</li> <li>• RECALL_REPRI — Reprioritize matching request</li> </ul> |



---

**Note:** The following flags may only be set by the `root` user on the DMF server or on a `VALID_ROOT_HOSTS` server:

`RECALL_CANCEL`  
`RECALL_REPRI`

See "base Object Parameters" on page 278.

---

`request_id` Specifies a pointer to a `DmuReqid_t` (defined in `libdmfcom.H`) parameter that will be returned with the unique request ID of the asynchronous request. This value can be used when processing `DmuCompletion_t` objects (see "Request-Completion Subroutines" on page 727).

If the subroutine succeeds, it returns `DmuNoError`.

### setprojid File Requests

The `Setprojid` request performs the same functional task as the `dmprojid(1)` command. The following subroutines perform the `Setprojid` DMF request:

`DmuSetprojidByPathAsync()`  
`DmuSetprojidByPathSync()`

Note the following:

- The 'Sync' version does not return until the `Setprojid` request has either completed successfully or has been aborted due to errors.
- The 'Async' version returns immediately after successfully forwarding the `Setprojid` request to the `dmusrCmd` process. If a reply is desired, the caller must process the reply to this request. See "Request-Completion Subroutines" on page 727.
- They allow the target file to be defined by its pathname.

The prototypes are as follows:

```
extern DmuError_t
DmuSetprojidByPathAsync(
    const DmuContext_t  dmuctxt,
```

```

        const char      *path,
        int             setprojid_flags,
        uint32_t        projid,
        DmuPriority_t    priority,           /* deferred */
        DmuReqid_t       *request_id,
        DmuAllErrors_t   *errs);          /* may be NULL */

extern DmuError_t
DmuSetprojidByPathSync(
    const DmuContext_t  dmuctxt,
    const char          *path,
    int                 setprojid_flags,
    uint32_t            projid,
    DmuPriority_t        priority,         /* deferred */
    DmuAllErrors_t      *errs);          /* may be NULL */

```

The parameters are as follows:

- dmuctxt                    Specifies a DmuContext\_t object that was previously created by DmuCreateContext().
- errs                     Specifies a pointer to a DmuAllErrors\_t object. This value may be NULL. If it is not NULL, the subroutine will use it to return errors. See "DmuAllErrors\_t" on page 686.
- path                     Specifies the relative or full pathname of the target file.
- priority                 Specifies a DmuPriority\_t object (defined in libdmfcom.H) that defines the request priority. (Deferred implementation.)
- projid                    Specifies the file project ID value. See the dmprojid(8) man page.
- request\_id                Specifies a pointer to a DmuReqid\_t (defined in libdmfcom.H) parameter that will be returned with the unique request ID of the asynchronous request. This value can be used when processing DmuCompletion\_t objects (see "Request-Completion Subroutines" on page 727).
- setprojid\_flags         Specifies the following flags:

- PROJID\_CLEARINHERIT — Clear the project ID inheritance bit on directories
- PROJID\_NONE — No flags specified
- PROJID\_NOWAIT — Do not wait if the DMF daemon is unavailable
- PROJID\_SETINHERIT — Set the project ID inheritance bit on directories

---

**Note:** These flags may only be set by the `root` user on the DMF server or on a `VALID_ROOT_HOSTS` server (see "base Object Parameters" on page 278).

---

If the subroutine succeeds, it returns `DmuNoError`.

## settag File Requests

The `Settag` request performs the same functional task as the `dmtag(1)` command. The following subroutines perform the `Settag` DMF request:

```
DmuSettagByFhandleAsync()  
DmuSettagByFhandleSync()  
DmuSettagByPathAsync()  
DmuSettagByPathSync()
```

These subroutines have the following things in common:

- The 'Sync' versions do not return until the `Settag` request has either completed successfully or has been aborted due to errors.
- The 'Async' versions return immediately after successfully forwarding the `Settag` request to the `dmusrcmd` process. If a reply is desired, the caller must process the reply to this request. See "Request-Completion Subroutines" on page 727.
- The 'ByPath' versions allow the target file to be defined by its pathname.
- The 'ByFhandle' versions allow the target file to be defined by its filesystem handle, the `fhandle`. These subroutines are valid only when the command making the call is on the DMF server machine and when a user has sufficient (`root`) privileges.

The prototypes are as follows:

```
extern DmuError_t
DmuSettagByFhandleAsync(
    const DmuContext_t    dmuctxt,
    const DmuFhandle_t    *client_fhandle,
    DmuSettagFlags_t     settag_flags,
    DmuSitetag_t         sitetag,
    DmuPriority_t         priority,
    DmuReqid_t           *request_id,
    DmuAllErrors_t       *errs)
```

```
extern DmuError_t
DmuSettagByFhandleSync(
    const DmuContext_t    dmuctxt,
    const DmuFhandle_t    *client_fhandle,
    DmuSettagFlags_t     settag_flags,
    DmuSitetag_t         sitetag,
    DmuPriority_t         priority,
    DmuAllErrors_t       *errs)
```

```
extern DmuError_t
DmuSettagByPathAsync(
    const DmuContext_t    dmuctxt,
    const char             *path,
    DmuSettagFlags_t     settag_flags,
    DmuSitetag_t         sitetag,
    DmuPriority_t         priority,
    DmuReqid_t           *request_id,
    DmuAllErrors_t       *errs)
```

```
extern DmuError_t
DmuSettagByPathSync(
    const DmuContext_t    dmuctxt,
    const char             *path,
    DmuSettagFlags_t     settag_flags,
    DmuSitetag_t         sitetag,
    DmuPriority_t         priority,
    DmuAllErrors_t       *errs)
```

The parameters are as follows:

|                             |                                                                                                                                                                                                                                                                                                                 |
|-----------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>client_fhandle</code> | Specifies the DMF filesystem <code>fhandle</code> of the target file. Valid for use only by a privileged ( <code>root</code> ) user on the DMF server machine.                                                                                                                                                  |
| <code>dmuctxt</code>        | Specifies a <code>DmuContext_t</code> object that was previously created by <code>DmuCreateContext()</code> .                                                                                                                                                                                                   |
| <code>errs</code>           | Specifies a pointer to a <code>DmuAllErrors_t</code> object. This value may be <code>NULL</code> . If it is not <code>NULL</code> , the subroutine will use it to return errors. See "DmuAllErrors_t" on page 686.                                                                                              |
| <code>path</code>           | Specifies the relative or full pathname of the target file.                                                                                                                                                                                                                                                     |
| <code>priority</code>       | Specifies a <code>DmuPriority_t</code> object (defined in <code>libdmfcom.H</code> ) that defines the request priority. (Deferred implementation.)                                                                                                                                                              |
| <code>request_id</code>     | Specifies a pointer to a <code>DmuReqid_t</code> (defined in <code>libdmfcom.H</code> ) parameter that will be returned with the unique request ID of the asynchronous request. This value can be used when processing <code>DmuCompletion_t</code> objects (see "Request-Completion Subroutines" on page 727). |
| <code>settag_flags</code>   | Specifies the following flags as defined in <code>libdmfcom.H</code> : <ul style="list-style-type: none"> <li>• <code>SETTAG_NONE</code> — No flags specified</li> <li>• <code>SETTAG_NOWAIT</code> — Return immediately if the daemon is not available to process the request (do not wait)</li> </ul>         |
| <code>sitetag</code>        | Defines the file site tag value. See <code>dmtag(1)</code> .                                                                                                                                                                                                                                                    |

If the subroutine succeeds, it returns `DmuNoError`.

## Request-Completion Subroutines

The request completion subroutines are provided so that the application can process the completion events of any asynchronous requests it might have issued. The caller can choose to process each request's completion object (`DmuCompletion_t`) or to be notified when each request has responded with either an intermediate or final (completion) reply.

The asynchronous requests described previously along with the following completion subroutines allow the user to achieve maximum parallelization of the processing of all requests.

### **DmuAwaitReplies() Subroutine**

The `DmuAwaitReplies()` subroutine performs a synchronous wait until the number of outstanding request replies of the type specified is less than or equal to `max_outstanding`. This subroutine is called by a user who does not want to perform individual processing of each outstanding request, but wants to know when a reply (intermediate or final) has been received for each request that has been sent to this point.

The prototype is as follows:

```
extern DmuError_t
DmuAwaitReplies(
    const DmuContext_t  dmuctxt,
    DmuReplyType_t     type,
    int                 max_outstanding,
    DmuAllErrors_t     *errs)
```

The parameters are as follows:

|                              |                                                                                                                                                                                                                                                            |
|------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>dmuctxt</code>         | Specifies a <code>DmuContext_t</code> object that was previously created by <code>DmuCreateContext()</code> .                                                                                                                                              |
| <code>errs</code>            | Specifies a pointer to a <code>DmuAllErrors_t</code> object. This value may be <code>NULL</code> . If it is not <code>NULL</code> , the subroutine will use it to return errors. See "DmuAllErrors_t" on page 686.                                         |
| <code>max_outstanding</code> | Specifies the number of outstanding requests allowed for which the <code>type</code> reply has not been received before the subroutine returns. If this parameter is 0, all <code>type</code> replies will have been received when the subroutine returns. |
| <code>type</code>            | Defines the type of reply to be received. The caller can wait for an intermediate or final reply for the outstanding requests.                                                                                                                             |

See the definition of `DmuReplyType_t` in "DmuReplyType\_t" on page 702 or in `libdmfcom.H`.

If no errors occurred getting the next reply, this subroutine returns `DmuNoError`.

### **DmuFullstatCompletion() Subroutine**

The `DmuFullstatCompletion()` subroutine can be called when asynchronous fullstat replies are being processed by `DmuGetNextReply()` or `DmuGetThisReply()`. When the reply is received, the `DmuCompletion_t` object that is part of the reply can be used as an input parameter to this routine, which will then extract the `DmuFullstat_t` object and the `DmuFhandle_t` objects that are contained in the `DmuCompletion_t` object's `ureq_data` field.

The prototype is as follows:

```
extern DmuError_t
DmuFullstatCompletion(
    DmuCompletion_t *comp;
    DmuFullstat_t *dmufullstat,
    DmuFhandle_t *fhandle,
    DmuAllErrors_t *errs)
```

The parameters are as follows:

|                          |                                                                                                                                                                                                                                                           |
|--------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>comp</code>        | Specifies the <code>DmuCompletion_t</code> object from an asynchronous Fullstat request.                                                                                                                                                                  |
| <code>dmufullstat</code> | Specifies a pointer to an existing <code>DmuFullstat_t</code> object. If <code>comp</code> references a successful Fullstat request, <code>dmufullstat</code> will be set to be equal to the <code>DmuFullstat_t</code> that was returned with the reply. |
| <code>errs</code>        | Specifies a pointer to a <code>DmuAllErrors_t</code> object. This value may be NULL. If it is not NULL, the subroutine will use it to return errors. See "DmuAllErrors_t" on page 686.                                                                    |
| <code>fhandle</code>     | Specifies a pointer to an existing <code>DmuFhandle_t</code> object. If <code>comp</code> references a successful Fullstat request,                                                                                                                       |

`fhandle` will be set to be equal to the `DmuFhandle_t` that was returned with the reply.

### **DmuGetNextReply() Subroutine**

The `DmuGetNextReply()` subroutine returns the completion object of the next reply based on the order specified on the call. This subroutine performs a synchronous wait until a request reply of the type specified on the call is received. At the time of the call, any reply that has already been received and is queued for processing is returned immediately.

The prototype is as follows:

```
extern DmuError_t
DmuGetNextReply(
    const DmuContext_t    dmuctxt,
    DmuReplyOrder_t order,
    DmuReplyType_t type,
    DmuCompletion_t *comp,
    DmuAllErrors_t *errs)
```

The parameters are as follows:

|                      |                                                                                                                                                                                                                                                                                                                                   |
|----------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>comp</code>    | Specifies a pointer to an existing <code>DmuCompletion_t</code> object. If a reply was available for processing according to the parameters on the calling subroutine, the <code>DmuCompletion_t</code> object pointed to by <code>comp</code> will be set with all of the appropriate values. See "DmuCompletion_t" on page 692. |
| <code>dmuctxt</code> | Specifies a <code>DmuContext_t</code> object that was previously created by <code>DmuCreateContext()</code> .                                                                                                                                                                                                                     |
| <code>errs</code>    | Specifies a pointer to a <code>DmuAllErrors_t</code> object. This value may be <code>NULL</code> . If it is not <code>NULL</code> , the subroutine will use it to return errors. See "DmuAllErrors_t" on page 686.                                                                                                                |

---

**Note:** This object will return errors that occurred while waiting for or receiving this reply. It does not refer to the errors that might have occurred during the request processing that resulted in the reply. Those errors are available in the `comp` object.

---



|       |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
|-------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| order | <p>Defines the order in which the request replies should be returned. The caller can process the replies in the order the replies are received (<code>DmuAnyOrder</code>) or in the order the requests were issued (<code>DmuReqOrder</code>).</p> <p>See the definition of <code>DmuReplyOrder_t</code> in "DmuReplyOrder_t" on page 702 or in <code>libdmfcom.H</code>.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| type  | <p>Defines the type of reply to be received, which is one of the following:</p> <ul style="list-style-type: none"> <li>• <code>DmuIntermed</code> returns both intermediate messages (which indicate that the DMF daemon has received a valid request) and the final message (which indicates that the request is complete, either with a successful execution or with errors).</li> </ul> <p>The <code>comp.ureq_data</code> field will always be <code>NULL</code> for an intermediate reply and for failed final replies. For successful replies, there are various possible structures returned via <code>ureq_data</code>, or <code>NULL</code>.</p> <ul style="list-style-type: none"> <li>• <code>DmuFinal</code> returns only the final message (intermediate messages are silently discarded)</li> </ul> |

For example:

```
rc = DmuGetNextReply(ctxp, DmuAnyOrder, DmuIntermed, &comp, &errs);
if (rc != DmuNoError) {
    /* The request could not be sent, this request is complete. */
} else if (comp.reply_code == /* intermediate-reply */ 1) {
    /* This is an intermediate reply, the request is accepted, a final reply will come later. */
} else if (comp.reply_code != DmuNoError) {
    /* This is a failed final reply, DMF could not complete your request. */
} else {
    /* This is a successful final reply, the request is complete. */
}
```

The value of `comp.ureq_data` in a successful final reply depends upon which request type was sent (a few request types return data):

- A pointer to a `DmuFullstat_t` structure will be returned for the following request types:

```
DmuFullstatByFhandleAsync
DmuFullstatByFhandleSync
DmuFullstatByPathAsync
DmuFullstatByPathSync
```

- A pointer to a `DmuFullstat_2_t` structure will be returned for the following request types:

```
DmuFullstatByFhandleAsync_2
DmuFullstatByFhandleSync_2
DmuFullstatByPathAsync_2
DmuFullstatByPathSync_2
```

- A pointer to a `DmuFsysInfo_t` structure will be returned for the following request type:

```
DmuFilesysInfo
```

- All other request types return a value of `NULL`.

If no errors occurred getting the next reply, this subroutine returns `DmuNoError`. If there are no outstanding requests pending, a return code of `DME_DMU_QUEUEEMPTY` is returned. You can use a check for `DME_DMU_QUEUEEMPTY` to terminate a `while` loop based on this subroutine. Any other error return code indicates an error, and the `errs` parameter can be processed for the error information.

### **DmuGetThisReply() Subroutine**

The `DmuGetThisReply()` subroutine returns the completion object of the specified request. This subroutine performs a synchronous wait until a request reply specified on the call is received.

The prototype is as follows:

```
extern DmuError_t
DmuGetThisReply(
    const DmuContext_t    dmuctxt,
          DmuReqid_t      request_id,
          DmuCompletion_t *comp,
          DmuAllErrors_t  *errs)
```

The parameters are as follows:

|                         |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|-------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>comp</code>       | <p>Specifies a pointer to an existing <code>DmuCompletion_t</code> object. If a reply was available for processing according to the parameters on the calling subroutine, the <code>DmuCompletion_t</code> object pointed to by <code>comp</code> will be set with all of the appropriate values. See "<code>DmuCompletion_t</code>" on page 692.</p> <p>The <code>reply_code</code> field of the <code>comp</code> parameter is the ultimate status of the request. A successful <code>comp</code> has a <code>reply_code</code> of <code>DmuNoError</code>. If the <code>reply_code</code> of <code>comp</code> is not <code>DmNoError</code>, the <code>comp-&gt;allerrors</code> object will contain the error information needed to determine the cause of the error.</p> <hr/> <p><b>Note:</b> The <code>errs</code> parameter on the subroutine call does not contain the error information for the failed request.</p> <hr/> |
| <code>dmuctxt</code>    | <p>Specifies a <code>DmuContext_t</code> object that was previously created by <code>DmuCreateContext()</code>.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
| <code>errs</code>       | <p>Specifies a pointer to a <code>DmuAllErrors_t</code> object. This value may be <code>NULL</code>. If it is not <code>NULL</code>, the subroutine will use it to return errors. See "<code>DmuAllErrors_t</code>" on page 686.</p> <hr/> <p><b>Note:</b> This object will return errors that occurred while waiting for or receiving this reply. It does not refer to the errors that might have occurred during the request processing that resulted in the reply. Those errors are available in the <code>comp</code> object.</p> <hr/>                                                                                                                                                                                                                                                                                                                                                                                          |
| <code>request_id</code> | <p>Specifies the unique request ID of the request for which the caller wants to wait.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |

If no errors occurred getting the next reply, this subroutine returns `DmuNoError`. Any other error return code indicates an error, and the `errs` parameter can be processed for the error information.



## Site-Defined Policy Subroutines and the `sitelib.so` Library

This appendix provides an overview of the site-defined policy feature and a summary of the policy subroutines sites may write:

- "Overview of Site-Defined Policy Subroutines" on page 735
- "Getting Started with Custom Subroutines" on page 736
- "Considerations for Writing Custom Subroutines" on page 738
- "`sitelib.so` Data Types" on page 739
- "Site-Defined Policy Subroutines" on page 743
- "Helper Subroutines for `sitelib.so`" on page 752

### Overview of Site-Defined Policy Subroutines

Site-defined policy subroutines are loaded dynamically by DMF to provide custom decision-making at key points in its processing. Several DMF processes, including `dmfdaemon`, can call subroutines within `sitelib.so`.

You do not need to use this feature, in which case DMF will function as documented in the manuals and man pages. But if you wish, you can implement one or more of these subroutines in order to override DMF's default behavior.

If you use the site-defined policy feature, you must communicate the policy changes to your user community; otherwise, they will not be able to predict how the user commands will work. The man page for any command with a site-defined policy will state something like the following:

If your site is using the site-defined policy feature, the default behavior may be overridden. Please check with your administrator for any behavior differences due to site-defined policies.

You should also consider adding `ERROR`, `WARN`, and `INFO` messages into the reply stream for commands you customize so that you can routinely return messages to the user that explain what was changed in their request. Doing so will allow the users to understand why the behavior was different from what they expected.

The subroutines are written in C++ according to the subroutine prototypes in `/usr/include/dmf/libdmfadm.H`. They are placed in a shared-object library called `/usr/lib/dmf/sitelib.so`.

The parameters and return values of the subroutines and the name of the `sitelib.so` library are fixed and cannot be altered by the site. In general, the parameters provide all of the information DMF has that is relevant to the purpose of the subroutine, which is described in the comments preceding each subroutine.

The code within the subroutines performs whatever processing the site wishes. To assist in several common operations, such as extracting information from the DMF configuration file, optional helper subroutines are provided in `/usr/include/dmf/libdmfadm.H`.

## Getting Started with Custom Subroutines

The `/usr/share/doc/dmf-*/info/sample` directory contains the following files to demonstrate generating the `sitelib.so` library:

- `sample_sitelib.C` contains source code of basic sample subroutines
- `sample_sitelib.mk` is the associated makefile

---

**Note:** If you use these files as a base for implementing subroutines of your own, be sure to keep them in a different directory and/or rename them to avoid any conflict when DMF is upgraded and new sample files are installed. For example, you could rename the files `sitelib.c` and `sitelib.mk`.

---

For example, to use the basic subroutine example `sample_sitelib.C`, do the following:

1. Copy `sample_sitelib.C` and its associated makefile `sample_sitelib.mk` from `/usr/share/doc/dmf-*/info/sample` to a directory of your own with names of your own choice.

For example, if you wanted to work in the `/tmp/testdmf` directory:

```
$ cp /usr/share/doc/dmf-*/info/sample/sample_sitelib.C /tmp/testdmf/sitelib.C
$ cp /usr/share/doc/dmf-*/info/sample/sample_sitelib.mk /tmp/testdmf/sitelib.mk
```

2. In the makefile, specify the stem from which the library filename and source code filename will be derived by editing the value for the `SITELIB` parameter. For example, to use a stem of `sitelib` (that is, `sitelib.so` for the library and `sitelib.c` for the source code file):

```
SITELIB=sitelib
```

---

**Note:** Although you can set the `SITELIB` value to something other than `sitelib` for testing purposes, when you actually want to run with DMF, it must be `sitelib`.

---

3. Read the comments at the start of each subroutine and alter the supplied code to suit your requirements. As supplied, each subroutine is disabled. To enable one or more subroutines, modify the `SiteFncMap` variable at the bottom of the source file (in our example, `sitelib.C`).

---

**Note:** The name of the `SiteFncMap` variable is fixed and cannot be altered. However, you can change the names of the site-defined subroutines such as `SiteCreateContext()`.

---

4. Build the `sitelib.so` library by using the `make(1)` command:

```
$ make -f sitelib.mk
```

5. Print a list of the subroutines that have been enabled and visually verify that it is what you expect:

```
$ make -f sitelib.mk verbose
```

6. Install the library on a DMF server, which requires you to be the `root` user:

```
$ su
# make -f sitelib.mk install
```

---

**Note:** You do not need to install `sitelib.so` on a machine that functions only as a DMF client.

---

For subroutines that affect the operation of the DMF daemon, library server, or MSP, you must wait for a minute or so for the new `sitelib.so` library to be noticed. You will see a message in the relevant log file when this happens.

7. Test your new library by monitoring the relevant log file with `tail -f` while you present test cases to DMF. You may also find it useful to have a Resource Watcher configured and running or to use `dmstat`.

## Considerations for Writing Custom Subroutines

As you write your own custom subroutines, be aware of the following:

- The `sitelib.so` file must be owned by `root` and must not be writable by anyone else, for security reasons. If these conditions are not met, DMF will ignore `sitelib.so` and use the default behavior.
- The `sitelib.so` library should not use the `stdin`, `stdout`, or `stderr` files as this could cause problems for DMF, possibly endangering data. For information about sending messages to users or to log files, see "`DmaSendLogFmtMessage()`" on page 763 and "`DmaSendUserFmtMessage()`" on page 764.
- If you overwrite the `sitelib.so` file while it is in use (for example by copying a new version of your file over the top of the old one), DMF processes may abort or run improperly. The DMF daemon may or may not be able to restart them properly.

To update the file, you should do one of the following:

- Use the `mv(1)` command to move the new file over the top of the old one, so that any existing DMF processes will continue to use the previous version of the file, which is now unlinked pending removal. The `install` target in the supplied makefile is also a safe way to update the file.



- Delete the old file with `rm(1)` before installing the new one using `cp`, `mv`, or `make install`.
- Shut down DMF while the update takes place.

This warning also applies to changes to the DMF configuration file.

- Site-defined policy subroutines should not call subroutines in `libdmfusr.so`, such as `DmuSettagByPathSync()`. They are free to call member functions of classes defined in `libdmfcom.H`, such as `DmuVolGroups_t::numVolGroups()`.
- At times, the site-defined subroutines may be called many times in rapid succession. They should therefore be as efficient as possible, avoiding any unnecessary processing, especially of system calls.

For example, when `dmfsfree` is invoked to prevent a filesystem from filling, site-defined subroutines may be called one or more times for every file in the filesystem as `dmfsfree` prepares its list of candidates prior to migrating and/or freeing some of them. If the functions are slow, DMF may not be able to react to the situation in time to prevent the filesystem from filling.

## sitelib.so Data Types

The data types described in this section are defined in `libdmfadm.H`. The information in this section is provided as a general description and overall usage outline. Other data types that are referenced in this file are defined in `libdmfcom.H`; see Appendix B, "DMF User Library `libdmfusr.so`" on page 681.

---

**Note:** For the most current definitions of these types, see the `libdmfadm.H` file.

---

### `DmaContext_t`

The `DmaContext_t` object stores information for DMF in order to provide continuity from one subroutine call to the next. It is an opaque object that is created when a DMF process first loads `sitelib.so` and it exists until that process unloads it. This context is provided as a parameter for each of the site-defined policy subroutines.

Site-defined subroutines cannot directly access the information held in the context, but they can obtain information from it by using the following subroutines:

- "DmaGetContextFlags()" on page 759
- "DmaGetProgramIdentity()" on page 762
- "DmaGetUserIdentity()" on page 762

Site-defined subroutines can also store their own information in the context and retrieve it on subsequent calls by using the following subroutines:

- "DmaSetCookie()" on page 765
- "DmaGetCookie()" on page 759

### **DmaFrom\_t**

The `DmaFrom_t` object specifies the type of policy statement being evaluated.

There are the following possible values:

|                                 |                                                                                                         |
|---------------------------------|---------------------------------------------------------------------------------------------------------|
| <code>DmaFromAgeWeight</code>   | Indicates that an <code>AGE_WEIGHT</code> policy statement is being evaluated.                          |
| <code>DmaFromSpaceWeight</code> | Indicates that a <code>SPACE_WEIGHT</code> policy statement is being evaluated.                         |
| <code>DmaFromVgSelect</code>    | Indicates that a <code>SELECT_MSP</code> or <code>SELECT_VG</code> policy statement is being evaluated. |

### **DmaIdentity\_t**

The `DmaIdentity_t` object provides information, if known, about the program calling the site-defined subroutine and the user whose request generated the call.

The public member fields and functions of this class are as follows:

`realm_type`

Specifies the environment in which the type of data that is contained in the `realm_data` field is meaningful.

The following settings are defined:

- `DMF_REALM_UNIX` means that the `unix_1` member of `realm_data` contains valid information
- `DMF_REALM_UNKNOWN` means that `realm_data` is not reliable

`realm_data`

Specifies user identity information that is specific to the environment defined by `realm_type`. Only the `unix_1` member of the union is defined for the `realm_type` of `DMF_REALM_UNIX`.

If the UID and/or GID values are `0xffffffff`, the values are not reliable.

`logical_name`

Specifies a character string containing the program name of the process. This may be an absolute or relative pathname. If the value is unknown, the program name was unavailable.

`product_name_and_revision`

Specifies a character string containing the product name and revision (for example, `DMF_3.1.0.0`).

`locale_1`

Specifies a character string containing the locale value. See the `locale(1)` man page.

`host`

Specifies a character string containing the host on which the `DmaIdentity_t` originated.

`pid`

Specifies the process ID where the `DmaIdentity_t` originated.

`instance_id`

Specifies a further refinement of the PID field. Because a process may create more than one `DmaIdentity_t`, this value is incremented by one for each new `DmaIdentity_t`.

`os_type`

Specifies a character string containing a description of the operating system where the `DmaIdentity_t` originated.

`os_version`

Specifies a character string containing a description of the operating system version where the `DmaIdentity_t` originated.

`cpu_type`

Specifies a character string containing a description of the CPU type where the `DmaIdentity_t` originated.

---

**Note:** Any of the descriptive character strings may be set to unknown if the field's true value cannot be determined.

---

### **`DmaLogLevel_t`**

The `DmaLogLevel_t` object specifies the level of a message. The administrator may select a log level in the DMF configuration file; messages with a less severe level than what is specified in the configuration file will not appear in the log.

### **`DmaRealm_t`**

The `DmaRealm_t` object specifies the realm. Only the UNIX realm is supported.

### **`DmaRecallType_t`**

The `DmaRecallType_t` object specifies the type of kernel recall being performed.

## SiteFncMap\_t

The `SiteFncMap_t` object specifies the site subroutine map. The various DMF processes that can call subroutines in `sitelib.so` look for a variable named `SiteFncMap`, of type `SiteFncMap_t`, in the `sitelib.so` library. It then uses the addresses provided in this variable to find the site-defined subroutines. If the variable is not found, DMF will not make any calls to subroutines in `sitelib.so`.

## Site-Defined Policy Subroutines

DMF looks for the variable named `SiteFncMap`, of type `SiteFncMap_t`, in the `sitelib.so` library. It then uses the addresses provided in this variable to find site-defined subroutines listed in this section. You can provide any number of these subroutines in the `sitelib.so` library.

## SiteArchiveFile()

The `SiteArchiveFile()` subroutine allows sites some control over the DMF archive requests. It is invoked when a `dmarchive(1)` command is issued to copy data directly to secondary storage or when one of the following `libdmfusr.so` subroutines is called:

```
DmuArchiveAsync()
DmuArchiveSync()
```

This subroutine is not called when automated space management migrates a file.



**Caution:** If `SiteArchiveFile()` is implemented, it takes precedence over any when clause being used to control MSP, volume group (VG), or migrate group (MG) selection, whether or not `SiteWhen()` has been implemented.

If this subroutine returns a value other than `DmuNoError`, the archive request will be rejected. The subroutine may not issue log messages, but it can issue messages to the user.

The prototype is as follows:

```
typedef DmuError_t (*SiteArchiveFile_f) (
    const DmaContext_t      dmacontext,
    const DmuFullstat_2_t  *fstat,
```

```

const char      *src_path,
const char      *dst_path,
const DmuFhandle_t *dst_fhandle,
const int       flags,
const DmuVolGroups_t *policy_volgrps,

const DmuPriority_t user_priority,
const int          user_flags,
const DmuVolGroups_t *user_volgrps,

DmuPriority_t     *operative_priority,
int              *operative_flags,
DmuVolGroups_t   *operative_volgrps);

```

The parameters are as follows:

|                          |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
|--------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>dmacontext</code>  | Refers to the context established when <code>sitelib.so</code> was loaded.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| <code>fstat</code>       | Specifies the <code>DmuFullstat_2_t</code> information of the target file for the archive request.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| <code>src_path</code>    | Specifies the pathname of the source file for the archive request.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| <code>dst_path</code>    | Specifies the pathname of the destination file for the archive request.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
| <code>dst_fhandle</code> | Specifies the <code>DmuFhandle_t</code> of the destination file for the archive request.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
| <code>flags</code>       | Specifies whether the <code>SiteArchiveFile()</code> subroutine is called for the first time (0) or is replayed (nonzero). <code>SiteArchiveFile()</code> can be called multiple times for the same request. For example, if <code>dmfdaemon</code> is not running, a <code>dmarchive</code> request will periodically try to establish a connection with it, and <code>SiteArchiveFile()</code> may be called. If <code>flags</code> is 0, this is the first time that <code>SiteArchiveFile()</code> has been called for a particular request. When a request is replayed, DMF reevaluates the parameters to <code>SiteArchiveFile()</code> before calling it. |

|                                                                                                   |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
|---------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>policy_volgrps</code>                                                                       | Specifies an input parameter that contains the MSPs, VGs, and MGs that have been selected by the policy statements in the DMF configuration file.                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| <code>user_priority</code><br><code>user_flags</code><br><code>user_volgrps</code>                | Contains information entered by the user as a <code>dmarchive</code> parameter (where supported) or as a parameter to one of the following <code>libdmfusr.so</code> subroutines:<br><br><code>DmuArchiveAsync()</code><br><code>DmuArchiveSync()</code>                                                                                                                                                                                                                                                                                                                                      |
| <code>operative_priority</code><br><code>operative_flags</code><br><code>operative_volgrps</code> | Contains the information that will be used when the request is made to <code>dmfdaemon</code> . These are all both input and output parameters. You can alter the <code>operative_flags</code> and <code>operative_volgrps</code> values. (Currently, <code>operative_priority</code> is ignored. For compatibility with future releases of DMF, it is recommended that you do not alter the value of this parameter.) If you alter <code>operative_volgrps</code> , take care that it expands to a non-overlapping set of MSPs and VGs when all the group members of the MGs are considered. |

### **SiteCreateContext()**

The `SiteCreateContext()` subroutine provides the opportunity to create a site-specific setup. It is called when `sitelib.so` is loaded. If no such setup is required, it need not be implemented. If this subroutine returns anything other than `DmuNoError`, no other subroutines in `sitelib.so`, including `SiteDestroyContext()`, will be called by the current process, unless `sitelib.so` is changed and therefore reloaded.

This subroutine may not issue messages to the user because the user details are unknown at the time it is invoked. If it is invoked by a program with a log file, such

as `dmfdaemon`, it can issue log messages by calling `DmaSendLogFmtMessage()`. You can call `DmaGetContextFlags()` to determine if it can issue log messages.

The prototype is as follows:

```
typedef DmuError_t (*SiteCreateContext_f)(
    const DmaContext_t dmacontext);
```

The parameter is as follows:

|                         |                                                                            |
|-------------------------|----------------------------------------------------------------------------|
| <code>dmacontext</code> | Refers to the context established when <code>sitelib.so</code> was loaded. |
|-------------------------|----------------------------------------------------------------------------|

### **SiteDestroyContext()**

The `SiteDestroyContext()` subroutine provides the opportunity for site-specific cleanup. It is called when `sitelib.so` is unloaded. If no such cleanup is required, it need not be implemented. This subroutine may not issue messages to the user because the user details are no longer valid at the time it is invoked. If it is invoked by a program with a log file, such as `dmfdaemon`, it can issue log messages by calling `DmaSendLogFmtMessage()`. You can call `DmaGetContextFlags()` to determine if it can issue log messages.

The prototype is as follows:

```
typedef void (*SiteDestroyContext_f)(
    const DmaContext_t dmacontext);
```

The parameter is as follows:

|                         |                                                                            |
|-------------------------|----------------------------------------------------------------------------|
| <code>dmacontext</code> | Refers to the context established when <code>sitelib.so</code> was loaded. |
|-------------------------|----------------------------------------------------------------------------|

### **SiteKernRecall()**

The `SiteKernRecall()` subroutine allows sites some control over kernel requests to recall a file. It is invoked when DMF receives a kernel request to recall a file. For example, a `read()` system call for a file that is currently in OFL state would result in `SiteKernRecall()` being called. The `dmget` command or the equivalent `libdmfusr.so` library call would not result in a call to `SiteKernRecall()`.



This subroutine may accept or reject the request or change its priority; no other changes are possible. If the subroutine returns a value other than `DmuNoError`, the request will be rejected.

---

**Note:** `offset` and `length` pertain to the range of the file that the user's I/O request referenced, not the byte range that `dmfdaemon` will actually recall.

---

The subroutine may not issue messages to the user, but it can issue messages to the DMF daemon log.

The prototype is as follows:

```
typedef DmuError_t (*SiteKernRecall_f) (
    DmaContext_t      dmacontext,
    const DmuFullstat_2_t *fullstat,
    const DmuFhandle_t *fhandle,
    uint64_t          offset,
    uint64_t          length,
    DmaRecallType_t  recall_type,
    DmuPriority_t     *operative_priority);
```

The parameters are as follows:

|                                 |                                                                                                                                                                                                                                                                          |
|---------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>dmacontext</code>         | Refers to the context established when <code>sitelib.so</code> was loaded.                                                                                                                                                                                               |
| <code>fullstat</code>           | Specifies the <code>DmuFullstat_2_t</code> of the file being recalled.                                                                                                                                                                                                   |
| <code>fhandle</code>            | Specifies the <code>DmuFhandle_t</code> of the file being recalled.                                                                                                                                                                                                      |
| <code>offset</code>             | Pertains to the range of the file that the user's I/O request referenced.                                                                                                                                                                                                |
| <code>length</code>             | Pertains to the length of the file that the user's I/O request referenced.                                                                                                                                                                                               |
| <code>recall_type</code>        | Specifies the type of recall.                                                                                                                                                                                                                                            |
| <code>operative_priority</code> | Specifies the priority of the operation. <code>operative_priority</code> is both an input and an output parameter and you can alter the value. Valid values are in the range <code>DMU_MIN_PRIORITY</code> to <code>DMU_MAX_PRIORITY</code> . Higher values imply higher |

priority. Only volume groups use priority; disk, DCM, and FTP MSPs ignore it.

## SitePutFile()

The `SitePutFile()` subroutine allows sites some control over the DMF put requests. It is invoked when a `dmput` command is issued or when one of the following `libdmfusr.so` subroutines is called:

```
DmuPutByPathAsync()
DmuPutByPathSync()
DmuPutByFhandleAsync()
DmuPutByFhandleSync()
```

This subroutine is not called when automated space management migrates a file.



---

**Caution:** If `SitePutFile()` is implemented, it takes precedence over any when clause being used to control MSP, VG, or MG selection, whether or not `SiteWhen()` has been implemented.

---

If this subroutine returns a value other than `DmuNoError`, the put request will be rejected. The subroutine may not issue log messages, but it can issue messages to the user.

The prototype is as follows:

```
typedef DmuError_t (*SitePutFile_f) (
    const DmaContext_t    dmacontext,
    const DmuFullstat_2_t *fstat,
    const char            *path,
    const DmuFhandle_t    *fhandle,
    const int             flags,
    const DmuVolGroups_t  *policy_volgrps,

    const DmuPriority_t    user_priority,
    const int             user_flags,
    const DmuByteRanges_t *user_byteranges,
    const DmuVolGroups_t  *user_volgrps,

    DmuPriority_t         *operative_priority,
```

```

int          *operative_flags,
DmuByteRanges_t *operative_byteranges,
DmuVolGroups_t *operative_volgrps);

```

The parameters are as follows:

|                                                                                                                    |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
|--------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>dmacontext</code>                                                                                            | Refers to the context established when <code>sitelib.so</code> was loaded.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| <code>fstat</code>                                                                                                 | Specifies the <code>DmuFullstat_2_t</code> information of the target file for the <code>put</code> request.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| <code>path</code>                                                                                                  | Specifies the pathname of the target file for the <code>put</code> request (if known) or <code>NULL</code> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| <code>fhandle</code>                                                                                               | Specifies the <code>DmuFhandle_t</code> of the target file for the <code>put</code> request.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| <code>flags</code>                                                                                                 | Specifies whether the <code>SitePutFile()</code> subroutine is called for the first time (0) or is replayed (nonzero). <code>SitePutFile()</code> can be called multiple times for the same request. For example, if <code>dmfdaemon</code> is not running, a <code>dmput</code> request will periodically try to establish a connection with it, and <code>SitePutFile()</code> may be called. If <code>flags</code> is 0, this is the first time that <code>SitePutFile()</code> has been called for a particular request. When a request is replayed, DMF reevaluates the parameters to <code>SitePutFile()</code> before calling it. |
| <code>policy_volgrps</code>                                                                                        | Specifies an input parameter that contains the MSPs, VGs, and MGs that have been selected by the policy statements in the DMF configuration file.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
| <code>user_priority</code><br><code>user_flags</code><br><code>user_byteranges</code><br><code>user_volgrps</code> | Contains information entered by the user as a <code>dmput</code> parameter (where supported) or as a parameter to one of the following <code>libdmfusr.so</code> subroutines:<br><br><pre> DmuPutByPathAsync() DmuPutByPathSync() DmuPutByFhandleAsync() DmuPutByFhandleSync() </pre>                                                                                                                                                                                                                                                                                                                                                    |

```
operative_priority
operative_flags
operative_byteranges
operative_volgrps
```

Contains the information that will be used when the request is made to `dmfdaemon`. These are all both input and output parameters. You can alter the `operative_flags`, `operative_byteranges`, and `operative_volgrps` values. (Currently, `operative_priority` is ignored. For compatibility with future releases of DMF, it is recommended that you do not alter the value of this parameter.) If you alter `operative_volgrps`, take care that it expands to a non-overlapping set of MSPs and VGs when all the group members of the MGs are considered.

### **SiteWhen()**

The `SiteWhen()` subroutine provides the opportunity to supply the value for the `sitefn` variable in `when` clauses in the following parameters:

```
AGE_WEIGHT
SPACE_WEIGHT
SELECT_MSP
SELECT_VG
```

This subroutine and the `sitefn` variable in `when` clauses are not supported for the `SELECT_LOWER_VG` parameter.



**Caution:** If `SitePutFile()` or `SiteArchiveFile()` is implemented, it takes precedence over any `when` clause being used to control MSP, VG, or MG selection, whether or not `SiteWhen()` has been implemented.

---

For example,

```
SELECT_VG          tp9840  when uid = archive or sitefn = 6
```

If this subroutine is unavailable, either because it was not implemented or because the `sitelib.so` library is not accessible, the expression using `sitelfn` is evaluated as being false. Therefore, the example above would be treated as if it were the following:

```
SELECT_VG      tp9840  when uid = archive or false
```

Or:

```
SELECT_VG      tp9840  when uid = archive
```

If a policy stanza contains multiple references to `sitelfn`, it is possible that the subroutine is only called once and the value returned by that call may be used for several substitutions of `sitelfn`. Therefore, a policy that contains the following will not necessarily call the subroutine three times:

```
AGE_WEIGHT     -1     0          when sitelfn < 10
AGE_WEIGHT     1     .1
SPACE_WEIGHT   1     1e-6       when sitelfn != 11
SPACE_WEIGHT   2     1e-9       when sitelfn > 19
SPACE_WEIGHT   3.14  1e-12
```

The subroutine can issue log messages in some circumstances and user messages in others. You can call `DmaGetContextFlags()` to determine what kind of messages are possible.

The prototype is as follows:

```
typedef int (*SiteWhen_f) (
    const DmaContext_t    dmacontext,
    const DmuFullstat_2_t *fstat,
    const DmuFhandle_t    *fhandle,
    DmaFrom_t             fromtyp);
```

The parameters are as follows:

|                         |                                                                            |
|-------------------------|----------------------------------------------------------------------------|
| <code>dmacontext</code> | Refers to the context established when <code>sitelib.so</code> was loaded. |
| <code>fstat</code>      | Specifies the <code>DmuFullstat_2_t</code> of the file being evaluated.    |
| <code>fhandle</code>    | Specifies the <code>DmuFhandle_t</code> of the file being evaluated.       |
| <code>fromtyp</code>    | Indicates what kind of policy is being evaluated.                          |

## Helper Subroutines for `sitelib.so`

This section describes optional subroutines that may be called from `sitelib.so` and are present in the processes that load `sitelib.so`.

### `DmaConfigStanzaExists()`

The `DmaConfigStanzaExists()` subroutine checks whether a specified stanza exists in the DMF configuration file.

---

**Note:** Values in the configuration file may change while DMF is running.

---

The prototype is as follows:

```
DmaBool_t  
DmaConfigStanzaExists(  
    const DmaContext_t    dmacontext,  
    const char            *type,  
    const char            *stanza);
```

The parameters are as follows:

|                         |                                                                                                                                                |
|-------------------------|------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>dmacontext</code> | Specifies the <code>DmaContext_t</code> parameter passed as input to all site-defined policy subroutines, such as <code>SitePutFile()</code> . |
| <code>type</code>       | Specifies the type of the stanza being checked.                                                                                                |
| <code>stanza</code>     | Specifies the name of the stanza being checked.                                                                                                |

For example, if the DMF configuration file contained the following:

```
define /dmf1  
    TYPE            filesystem  
    POLICIES        space_policy vg_policy  
enddef
```

Then the following call would return true:

```
DmaConfigStanzaExists(dmacontext, "filesystem", "/dmf1");
```

### **DmaGetConfigBool()**

The `DmaGetConfigBool()` subroutine extracts parameter values of type `DmaBool_t` from the specified stanza in the DMF configuration file. If there is no such parameter definition or if it exists but with a missing or improper value, then the default is used.

---

**Note:** Values in the configuration file may change while DMF is running.

---

The prototype is as follows:

```
DmaBool_t
DmaGetConfigBool(
    const DmaContext_t dmacontext,
    const char *stanza,
    const char *param,
    DmaBool_t default_val);
```

The parameters are as follows:

|                          |                                                                                                                                                |
|--------------------------|------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>dmacontext</code>  | Specifies the <code>DmaContext_t</code> parameter passed as input to all site-defined policy subroutines, such as <code>SitePutFile()</code> . |
| <code>stanza</code>      | Specifies the name of the stanza being searched.                                                                                               |
| <code>param</code>       | Specifies the name of the parameter for which <code>DmaGetConfigBool()</code> is searching.                                                    |
| <code>default_val</code> | Specifies the value to use if <code>param</code> is not found in <code>stanza</code> or if <code>param</code> has a missing or invalid value.  |

### **DmaGetConfigFloat()**

The `DmaGetConfigFloat()` subroutine extracts parameter values of type `float` from the specified stanza in the DMF configuration file. If there is no such parameter definition or if it exists but with a missing or invalid value, the default is used.

---

**Note:** Values in the configuration file may change while DMF is running.

---

The prototype is as follows:

```
float
DmaGetConfigFloat(
    const DmaContext_t dmacontext,
    const char *stanza,
    const char *param,
    float default_val,
    float min,
    float max);
```



The parameters are as follows:

|                          |                                                                                                                                                |
|--------------------------|------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>dmacontext</code>  | Specifies the <code>DmaContext_t</code> parameter passed as input to all site-defined policy subroutines, such as <code>SitePutFile()</code> . |
| <code>stanza</code>      | Specifies the name of the stanza being searched.                                                                                               |
| <code>param</code>       | Specifies the name of the parameter for which <code>DmaGetConfigFloat()</code> is searching.                                                   |
| <code>default_val</code> | Specifies the value to use if <code>param</code> is not found in stanza or if <code>param</code> has a missing or invalid value.               |
| <code>min</code>         | Defines the minimum valid value.                                                                                                               |
| <code>max</code>         | Defines the maximum valid value.                                                                                                               |

### `DmaGetConfigInt()`

The `DmaGetConfigInt()` subroutine extracts parameter values of type `int64_t` from the specified stanza in the DMF configuration file. If there is no such parameter definition or if it exists but with a missing or invalid value, then a default value is used.

---

**Note:** Values in the configuration file may change while DMF is running.

---

The prototype is as follows:

```
int64_t
DmaGetConfigInt(
    const DmaContext_t  dmacontext,
    const char          *stanza,
    const char          *param,
    int64_t             default_val,
    int64_t             min,
    int64_t             max);
```

The parameters are as follows:

|                         |                                                                                                                                                |
|-------------------------|------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>dmacontext</code> | Specifies the <code>DmaContext_t</code> parameter passed as input to all site-defined policy subroutines, such as <code>SitePutFile()</code> . |
|-------------------------|------------------------------------------------------------------------------------------------------------------------------------------------|

|                          |                                                                                                                                               |
|--------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------|
| <code>stanza</code>      | Specifies the name of the stanza being searched.                                                                                              |
| <code>param</code>       | Specifies the name of the parameter for which <code>DmaGetConfigInt()</code> is searching.                                                    |
| <code>default_val</code> | Specifies the value to use if <code>param</code> is not found in <code>stanza</code> or if <code>param</code> has a missing or invalid value. |
| <code>min</code>         | Defines the minimum valid value.                                                                                                              |
| <code>max</code>         | Defines the maximum valid value.                                                                                                              |

### `DmaGetConfigList()`

The `DmaGetConfigList()` subroutine returns a pointer to an array of words found in the parameter in the specified stanza. The `items` value points to a block of memory containing an array of string pointers as well as the strings themselves; the end of the array is marked by a `NULL` pointer. The block of memory has been allocated by the `malloc()` subroutine and can be released with the `free()` subroutine if desired. The caller is responsible for releasing this memory.

---

**Note:** Values in the configuration file may change while DMF is running.

---

The prototype is as follows:

```
DmaBool_t
DmaGetConfigList(
    const DmaContext_t dmacontext,
    const char *stanza,
    const char *param,
    char *** items);
```

The parameters are as follows:

|                         |                                                                                                                                                |
|-------------------------|------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>dmacontext</code> | Specifies the <code>DmaContext_t</code> parameter passed as input to all site-defined policy subroutines, such as <code>SitePutFile()</code> . |
| <code>stanza</code>     | Specifies the name of the stanza being searched.                                                                                               |
| <code>param</code>      | The name of the parameter for which <code>DmaGetConfigList()</code> is searching.                                                              |

`items` Specifies an output value that points to a block of memory containing an array of string pointers as well as the strings themselves; the end of the array is marked by a `NULL` pointer.

### **DmaGetConfigStanza()**

The `DmaGetConfigStanza()` subroutine return a pointer to an array of parameters and values for the specified stanza in the DMF configuration file. (That is, it provides the entire stanza, after comments have been removed.) The `items` value points to a block of memory containing an array of structures with string pointers as well as the strings themselves; the end of the array is marked by a `NULL` pointer. The block of memory has been allocated by the `malloc()` subroutine and can be released with the `free()` subroutine if desired. The caller is responsible for releasing this memory.

---

**Note:** Values in the configuration file may change while DMF is running.

---

The prototype is as follows:

```
DmaBool_t
DmaGetConfigStanza(
    const DmaContext_t dmacontext,
    const char *stanza,
    DmaConfigData_t **items);
}
```

The parameters are as follows:

`dmacontext` Specifies the `DmaContext_t` parameter passed as input to all site-defined policy subroutines, such as `SitePutFile()`.

`stanza` Specifies the name of the stanza being searched.

`items` Specifies an output value that points to a block of memory containing an array of structures with string

pointers as well as the strings themselves; the end of the array is marked by a `NULL` pointer.

### **DmaGetConfigString()**

Extracts a string from the specified stanza in the DMF configuration file and returns it. If there is no such parameter definition, the default is used. If the parameter exists but with a missing value, the null string (which is a valid value) is returned.

---

**Note:** Values in the configuration file may change while DMF is running.

---

The prototype is as follows:

```
void
DmaGetConfigString(
    const DmaContext_t dmacontext,
    const char *stanza,
    const char *param,
    const char *default_val,
    DmuStringImage_t &result);
```

The parameters are as follows:

|                          |                                                                                                                                                                                                    |
|--------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>dmacontext</code>  | Specifies the <code>DmaContext_t</code> parameter passed as input to all site-defined policy subroutines, such as <code>SitePutFile()</code> .                                                     |
| <code>stanza</code>      | Specifies the name of the stanza being searched.                                                                                                                                                   |
| <code>param</code>       | Specifies the name of the parameter for which <code>DmaGetConfigString()</code> is searching.                                                                                                      |
| <code>default_val</code> | Specifies the value to use if <code>param</code> is not found in <code>stanza</code> . If <code>param</code> is found in <code>stanza</code> but has a missing value, the null string is returned. |
| <code>result</code>      | Specifies an output parameter, containing the result.                                                                                                                                              |

## DmaGetContextFlags()

The `DmaGetContextFlags()` subroutine determines if a given subroutine can issue log messages or issue user messages.

---

**Note:** If `DmaFlagContextValid()` is not set in the return value, no use should be made of any other bits.

---

`DmaGetContextFlags()` can return the following values, which may be OR'd together:

|                                  |                                                                  |
|----------------------------------|------------------------------------------------------------------|
| <code>DmaFlagContextValid</code> | Indicates that the context is valid.                             |
| <code>DmaFlagLogAvail</code>     | Indicates that <code>DmaSendLogFmtMessage</code> may be called.  |
| <code>DmaFlagMsgAvail</code>     | Indicates that <code>DmaSendUserFmtMessage</code> may be called. |

The prototype is as follows:

```
uint64_t
DmaGetContextFlags(
    const DmaContext_t dmacontext);
```

The parameter is as follows:

|                         |                                                                                                                                                |
|-------------------------|------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>dmacontext</code> | Specifies the <code>DmaContext_t</code> parameter passed as input to all site-defined policy subroutines, such as <code>SitePutFile()</code> . |
|-------------------------|------------------------------------------------------------------------------------------------------------------------------------------------|

## DmaGetCookie()

The `DmaGetCookie()` subroutine returns the cookie that was stored in `dmacontext` by a call to `DmaSetCookie()`. If a NULL value is returned, either the context is invalid or the cookie was not set.

The prototype is as follows:

```
void *
DmaGetCookie(
    const DmaContext_t dmacontext);
```

The parameter is as follows:

|                         |                                                                                                                                                |
|-------------------------|------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>dmacontext</code> | Specifies the <code>DmaContext_t</code> parameter passed as input to all site-defined policy subroutines, such as <code>SitePutFile()</code> . |
|-------------------------|------------------------------------------------------------------------------------------------------------------------------------------------|

### **DmaGetDaemonMigGroups()**

The `DmaGetDaemonMigGroups` subroutine returns the list of configured migrate groups.

The prototype is as follows:

```
const DmuVolGroups_t *  
DmaGetDaemonMigGroups(  
    const DmaContext_t dmacontext)
```

The parameter is as follows:

|                         |                                                                                                                                                |
|-------------------------|------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>dmacontext</code> | Specifies the <code>DmaContext_t</code> parameter passed as input to all site-defined policy subroutines, such as <code>SitePutFile()</code> . |
|-------------------------|------------------------------------------------------------------------------------------------------------------------------------------------|

### **DmaGetDaemonVolAndMigGroups()**

The `DmaGetDaemonVolAndMigGroups()` subroutine returns the MSPs, VGs, and MGs that `dmfdaemon` is currently configured to use.

---

**Note:** Values in the configuration file may change while DMF is running.

---

The prototype is as follows:

```
const DmuVolGroups_t *  
DmaGetDaemonVolAndMigGroups(  
    const DmaContext_t dmacontext);
```

The parameter is as follows:

`dmacontext` Specifies the `DmaContext_t` parameter passed as input to all site-defined policy subroutines, such as `SitePutFile()`.

### **DmaGetDaemonVolGroups()**

The `DmaGetDaemonVolGroups()` subroutine returns the MSPs and VGs that `dmfdaemon` is currently configured to use.

---

**Note:** Values in the configuration file may change while DMF is running.

---

The prototype is as follows:

```
const DmuVolGroups_t *
DmaGetDaemonVolGroups(
    const DmaContext_t dmacontext);
```

The parameter is as follows:

`dmacontext` Specifies the `DmaContext_t` parameter passed as input to all site-defined policy subroutines, such as `SitePutFile()`.

### **DmaGetMigGroupMembers()**

The `DmaGetMigGroupMembers` subroutine returns group members of the given migrate group. The return value must be explicitly released by the caller using the `free()` subroutine.

```
char **
DmaGetMigGroupMembers(
    const DmaContext_t dmacontext,
    const char *mg_name)
```

The parameters are as follows:

`dmacontext` Specifies the `DmaContext_t` parameter passed as input to all site-defined policy subroutines, such as `SitePutFile()`.





same context from another site-defined policy subroutine. In most cases, the user identity is determined after the call to `SiteCreateContext()`.

Under certain circumstances, some elements of the `DmaIdentity_t` structure may be unknown. For example, if a site-defined subroutine is called as a result of a command entered on a client machine running a release prior to DMF 3.1, some elements of the user identity may be unknown.

The prototype is as follows:

```
const DmaIdentity_t *
DmaGetUserIdentity(
    const DmaContext_t dmacontext);
```

The parameter is as follows:

|                         |                                                                                                                                                |
|-------------------------|------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>dmacontext</code> | Specifies the <code>DmaContext_t</code> parameter passed as input to all site-defined policy subroutines, such as <code>SitePutFile()</code> . |
|-------------------------|------------------------------------------------------------------------------------------------------------------------------------------------|

### **DmaSendLogFmtMessage()**

The `DmaSendLogFmtMessage()` subroutine formats and issues log messages, if log messages are possible. The messages will potentially appear in the calling program's log depending upon the `DmaLogLevel_t` of the message and the log level selected by the administrator in the DMF configuration file. If log messages are not possible, `DmaSendLogFmtMessage()` silently discards the message.

The prototype is as follows:

```
void
DmaSendLogFmtMessage(
    const DmaContext_t dmacontext,
    DmaLogLevel_t log_level,
    const char *name,
    const char *format,
    ...);
```

The parameters are as follows:

|                         |                                                                                                                                                |
|-------------------------|------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>dmacontext</code> | Specifies the <code>DmaContext_t</code> parameter passed as input to all site-defined policy subroutines, such as <code>SitePutFile()</code> . |
|-------------------------|------------------------------------------------------------------------------------------------------------------------------------------------|

|                        |                                                                                                                                                                                                                                                                                               |
|------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>log_level</code> | Specifies the level of the message.                                                                                                                                                                                                                                                           |
| <code>name</code>      | Specifies a string that is included as part of the log message.                                                                                                                                                                                                                               |
| <code>format</code>    | Specifies the format for the message that will be printed in the log. It looks like a <code>printf(3S)</code> format. Do not include <code>\n</code> as part of the message. If you want to print more than one line to the log, make multiple calls to <code>DmaSendLogFmtMessage()</code> . |

For example, the following will issue an error message to the calling program's log:

```
DmaSendLogFmtMessage (dmacontext, DmaLogErr,
                     "SiteCreateContext", "sitelib.so problem errno %d",
                     errno);
```

### **DmaSendUserFmtMessage()**

The `DmaSendUserFmtMessage()` subroutine formats and sends messages to the user, if user messages are possible. The messages will potentially appear as output from commands such as `dmput` and `dmget`, depending upon the severity of the message and the level of message verbosity selected by the user. If user messages are not possible, `DmaSendUserFmtMessage()` silently discards the message.

The prototype is as follows:

```
void
DmaSendUserFmtMessage(
    const   DmaContext_t   dmacontext,
           DmuSeverity_t   severity,
    const   char           *position,
           int             err_no,
    const   char           *format,
           ...);
```

The parameters are as follows:

|                         |                                                                                                                                                |
|-------------------------|------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>dmacontext</code> | Specifies the <code>DmaContext_t</code> parameter passed as input to all site-defined policy subroutines, such as <code>SitePutFile()</code> . |
| <code>severity</code>   | Specifies the severity of the message.                                                                                                         |

|                       |                                                                                                                                                                                           |
|-----------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>position</code> | Specifies a string that can be included in the message. This string may be set to <code>NULL</code> .                                                                                     |
| <code>err_no</code>   | Specifies that if <code>err_no</code> is non-zero, the results of <code>strerror(err_no)</code> will be included in the message.                                                          |
| <code>format</code>   | Specifies the format for the message that will be sent to the user. It looks like a <code>printf(3S)</code> format. It is not necessary to put <code>\n</code> at the end of the message. |

### **DmaSetCookie()**

The `DmaSetCookie()` subroutine stores a pointer to site-defined subroutine information in `dmacontext`. This pointer may be retrieved by a call to `DmaGetCookie()`. The site-defined subroutines are responsible for memory management of the space pointed to by the `cookie` parameter.

The prototype is as follows:

```
void
DmaSetCookie(
    const DmaContext_t dmacontext,
    void *cookie);
```

The parameters are as follows:

|                         |                                                                                                                                                        |
|-------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>dmacontext</code> | Specifies the <code>DmaContext_t</code> parameter that is passed as input to all site-defined policy subroutines, such as <code>SitePutFile()</code> . |
| <code>cookie</code>     | Specifies a pointer to information that <code>sitelib.so</code> subroutines want to retain while the <code>dmacontext</code> is valid.                 |



## Third-Party Backup Package Configuration

This appendix discusses the following:

- "Using Third-Party Backup Packages" on page 767
- "ASG-Time Navigator" on page 769
- "taskgroup Object Example for Third-Party Backups" on page 770

### Using Third-Party Backup Packages

This section discusses the following:

- "Overview of Using Third-Party Backup Packages" on page 767
- "do\_predump.sh Script" on page 768
- "DUMP\_DATABASE\_COPY Configuration File Parameter in the taskgroup Object" on page 768
- "Hard Deletes and Third-Party Backup" on page 769
- "Unprivileged Users" on page 769
- "Procedure to Use a Third-Party Backup Package" on page 769

### Overview of Using Third-Party Backup Packages

Many backup and recovery software packages make backup copies of files by opening and reading them using the standard UNIX or Linux system calls. In a filesystem managed by DMF, this causes files that are offline to be recalled back to disk before they can be backed up. If you have a managed filesystem in which a high percentage of the files are offline, you may see a large amount of media or other activity caused by the backup package when it initially does its backups. You should take this behavior into account when deciding whether or not to use such backup packages with filesystems managed by DMF.

Some third-party backup packages can use a DMF library to perform backups in a manner that is aware of DMF. When the feature that is aware of DMF is enabled, these packages will not cause offline (OFL) files to be recalled during a backup.

Dual-state (DUL) files will be backed up as if they were offline, which will reduce the time and space needed for a backup.

### **do\_predump.sh Script**

DMF provides a script called `do_predump.sh` that is meant to be run just prior to a backup of the DMF filesystems using a third-party backup package. The `do_predump.sh` script does the following:

- *(Optional)* Migrates all eligible files to dual-state
- *(Optional on a DCM MSP system)* Copies all eligible DCM MSP files to dual-residency state
- *(Optional)* Performs a snapshot of the databases by using `dmsnap`

To use `do_predump.sh`, do the following:

1. Configure the backup package to run `do_predump.sh` as the pre-backup command. For details, see the application-specific information in Appendix D, "Third-Party Backup Package Configuration" on page 767.
2. Define a task group in the `dmf.conf` file that is referred to by the `dmdaemon` object. In the supplied configurations, this task group is called `dump_tasks`.

The parameters `do_predump.sh` uses are as follows:

- `DUMP_DATABASE_COPY`
- `DUMP_FLUSH_DCM_FIRST`
- `DUMP_FILE_SYSTEMS`
- `DUMP_MIGRATE_FIRST`

For more information, see "taskgroup Object Parameters" on page 312.

### **DUMP\_DATABASE\_COPY Configuration File Parameter in the taskgroup Object**

The `taskgroup` object also supports the `DUMP_DATABASE_COPY` for third-party backup only. It specifies the path to a directory where a snapshot of the DMF databases will be placed when `do_predump.sh` is run. The third-party backup application should be configured to back up this directory. By default, a snapshot will not be taken.

## Hard Deletes and Third-Party Backup

Because hard-deletions normally use the same expiry time as backups, `run_hard_deletes.sh` is normally run from the same task group. The `DUMP_RETENTION` parameter should match the retention policy of the backup package. For an example stanza, see Example D-1 on page 770.

## Unprivileged Users

Backups and restores must be run from the DMF server.

Only `root` can perform backups and restores. Although some third-party backup packages normally allow unprivileged users to restore their own files, unprivileged users cannot restore their own files from a DMF filesystem because doing so requires `root` privilege to set the DMF attribute.

Files backed up from a DMF filesystem should only be restored to a DMF filesystem. Otherwise, files that are offline (or treated as such) will not be recallable.

## Procedure to Use a Third-Party Backup Package

To use a third-party backup package to back up DMF filesystems, do the following:

1. Configure the backup package to include the DMF filesystems in the backups.
2. Enable the feature that is aware of DMF on those filesystems.

## ASG-Time Navigator

---

**Note:** SGI Support does not cover ASG-Time Navigator. For more information about ASG-Time Navigator, see [www.asg.com](http://www.asg.com) and the ASG-Time Navigator manuals.

---

ASG-Time Navigator is high-performance backup and recovery software designed with intuitive graphical user interfaces (GUIs) to manage data in heterogeneous environments.

ASG-Time Navigator is aware of DMF and supports a broad range of servers and client operating systems. It also supports a wide range of SAN hardware and tape

libraries. ASG-Time Navigator by default uses a proprietary protocol for all data transfers.

To make ASG-Time Navigator aware of a managed filesystem, add lines resembling the following to the *full-TimeNavigator-installation-path/Conf/parameters* file, where */dmfusr1* and */dmfusr2* are the managed filesystems:

```
<parameter name="bapi_fs">
<value>/dmfusr1</value>
<value>/dmfusr2</value>
</parameter>
```

Using the ASG-Time Navigator GUI, you can define **backup classes** to select which directories you want to back up. You can also vary the granularity for backup and restore, such as file, directory, or class level.

To use DMF's *do\_predump.sh* script with ASG-Time Navigator, set up ASG-Time Navigator to use a precommand as follows:

- In the **Advanced** tab of the backup strategy, specify the following as the preprocessing command:

```
/usr/lib/dmf/do_predump.sh daemon dump_tasks
```

where:

*daemon*        Name of the *dmdaemon* object in the DMF configuration file

*dump\_tasks*   Name of the task group specifying the parameters related to backups

- Ensure that DMF's *DUMP\_RETENTION* parameter matches the retention value of the cartridge pool associated with backing up the DMF filesystem.

## taskgroup Object Example for Third-Party Backups

### Example D-1 taskgroup Object for Third-Party Backups

```
define dump_tasks
    TYPE                taskgroup
    RUN_TASK             $ADMINDIR/run_hard_deletes.sh at 23:00
    DUMP_RETENTION      4w

    DUMP_MIGRATE_FIRST  yes
    DUMP_FLUSH_DCM_FIRST  yes
```



```
        DUMP_DATABASE_COPY      /path/to/db_snapshot
enddef
```

The above example is similar to Example 7-10, page 333, and Example 7-11, page 335, but has the following differences:

- The backups are not managed via the dump scripts
- There is a DCM MSP, so the `dmmigrate` command should be run before the backups are done
- A snapshot of the DMF databases will be placed in `/path/to/db_snapshot` when `do_predump.sh` is run



## Converting from IRIX DMF to Linux<sup>®</sup> DMF

---

**Note:** This procedure must take place during a planned outage of the systems and filesystems managed by DMF. It is assumed that sites converting DMF from IRIX to Linux will obtain the help of SGI customer support. The following documentation is offered to familiarize you with the necessary steps.

---

This appendix describes the necessary steps to convert an IRIX DMF system to a Linux DMF system and provides an example using a single library server (LS).

You cannot copy DMF databases from an IRIX system to a Linux system because of binary incompatibility. Instead, you must dump the IRIX DMF databases to text on the IRIX system and load the resulting text file into the databases on the Linux system. However, you can move managed filesystems (that is, filesystems containing user files that DMF has migrated) from an IRIX system to a Linux system.

### **Procedure E-1** Converting from IRIX DMF to Linux DMF

1. Discontinue all user activity for the duration of the IRIX to Linux conversion process.
2. If you have a tape MSP, you must convert it to a volume group (VG) in an LS **while still on IRIX** using `dmmstols`.

---

**Note:** The tape MSP is not available in the Linux DMF release.

---

For more information, see the DMF 3.0 version of the *DMF Administrator's Guide for SGI InfiniteStorage* (007-3681-008).

3. Prepare the DMF databases on the IRIX system:
  - a. Change the filesystem migration levels in the `dmf.conf` file to `none`.
  - b. Run `dmdidle` and wait for activity to cease.
  - c. Use `dmsnap` to back up the DMF databases.

Alternatively, if time or disk space considerations are critical, it is acceptable to use the snapshot of the DMF databases that is generated in the

*dmaudit\_working\_dir* as part of step 4 below as the database backup copy, allowing you to skip this *dmsnap* step.

4. Audit the DMF databases to ensure that they are valid:



---

**Caution:** Do not proceed until you have obtained clean results for each step in turn.

---

- a. Run `dmaudit snapshot` and resolve all errors before moving on to step 4.b.
- b. Run `dmatvfy dmaudit_working_dir` and resolve all errors before moving on to step 4.c.
- c. Run `dmdskvfy` against all DCM and disk MSPs and resolve all errors before moving on to step 5.

For more information, see the `dmaudit(8)` man page and *DMF Filesystem Audit Guide for SGI InfiniteStorage*.

5. Stop DMF on the IRIX system.



---

**Caution:** If DMF is started again on the IRIX system during or after this procedure, the databases captured during step 7 might not reflect reality, and loss of data might result if you use them.

---

6. Use `dmdbcheck` to verify the consistency of the DMF databases.
7. Dump all of the DMF databases to text from the snapshot taken in step 3c above. This should include the daemon database and the CAT and VOL tables for each LS database. For more information, see the `dmdump(8)` man page.
8. Sort the daemon and CAT text database records for better overall performance of the text-record load process. (The time to sort and load will be less than the time to load unsorted text records when the number of records is in the millions.) Do the following:

- To sort the daemon text record file, use a command similar to the following, where *tmpdir* is a directory in a filesystem with sufficient free space for `sort` to complete the sort:

```
# /bin/sort -t"|" -y -T tmpdir -k 1,1 -o sorted_daemontext daemontext
```

- To sort the CAT text record file, use a command similar to the following, where *tmpdir* is a directory in a filesystem with sufficient free space for `sort` to complete the sort:

```
# /bin/sort -t"|" -y -T tmpdir -k 2,2 -o sorted_cattext cattext
```

For more information, see the `sort(1)` man page.

9. Set up the `/etc/dmf/dmf.conf` file on the Linux system. The conversion will be simpler if you name all of the FTP MSPs, disk MSPs, tape VGs, and LSs with the same names used on IRIX. This assumes that you do not already have MSPs, LSs, or VGs with these names on your Linux system.

If you do change the name of an MSP or VG, you must convert the daemon database. For more information on how to perform this conversion, see the documentation in the `dmconvertdaemon` script.

10. Use `dmcheck` to ensure that your new `/etc/dmf/dmf.conf` file is valid on the Linux system.
11. Copy the text versions of the databases (which you created in step 7 and sorted in step 8) to the Linux system.
12. Load the database files from the text files on the Linux system. Use the following commands:

---

**Note:** If you are loading the text records into an empty database, use the `-j` option on the `dmdadm(8)` and `dmcatadm(8)` commands to eliminate the unnecessary overhead of database journal records. If you are loading the records into a nonempty database, SGI recommends that you make a copy of the database before running the `dmdadm` and `dmcatadm` commands and that you do not use `-j` option.

---

- `dmdadm` to load the daemon database file
  - `dmcatadm` to load the CAT records for each of the LS databases
  - `dmvoladm` to load the VOL records for each of the LS databases
13. Use `dmdbcheck` to check the consistency of databases on the Linux system.
  14. Move all of the managed filesystems and DCM MSP filesystems from the IRIX system to the Linux system:

- If reusing the existing disks and the IRIX filesystem blocksize is supported by Linux (512, 1024, 2048, 4096, 8192, or 16384), you can simply move the disks from the IRIX system to the Linux system.
- If there is a disk resource upgrade or if the IRIX block size greater than what is supported in Linux, there will be new filesystems built under Linux. The old data must then be restored to these new filesystems. For information, see "Restoring Files from Backups" on page 643.

15. Start DMF on the Linux system.

16. Run `dmaudit` to verify the filesystems.

#### **Example E-1** IRIX to Linux Conversion (Single LS)

In the following example, the IRIX system has a single LS named `ls1`. The example assumes that the `/tmp/dmf_databases` directory has been created, is initially empty, and contains enough space to accommodate the text versions of the databases. The example also assumes that the `HOME_DIR` configuration parameter is set to `/dmf/home` on both systems. After completing steps 2 through 6 of Procedure E-1 on page 773, the daemon database and the CAT and VOL tables of the LS database are dumped to text, as follows:

```
$ dmdump -c /dmf/home/daemon > /tmp/dmf_databases/daemon_txt
$ dmdump /dmf/home/ls1/tpcrdm.dat > /tmp/dmf_databases/ls1_cat_txt
$ dmdump /dmf/home/ls1/tpvrmdm.dat > /tmp/dmf_databases/ls1_vol_txt
```

Next, the files in `/tmp/dmf_databases` on the IRIX system are copied to `/tmp/dmf_txtdb` on the Linux system. After creating the DMF configuration file on the Linux system, the databases are loaded on the Linux system, as follows:

```
$ dmdadm -u -c "load /tmp/dmf_txtdb/daemon_txt"
$ dmcataadm -m ls1 -u -c "load /tmp/dmf_txtdb/ls1_cat_txt"
$ dmvoidadm -m ls1 -u -c "load /tmp/dmf_txtdb/ls1_vol_txt"
```

Now `dmdbcheck` is run to verify the consistency of the databases, as follows:

```
$ cd /dmf/home/daemon; dmdbcheck -a dmd_db
$ cd /dmf/home/ls1; dmdbcheck -a libsrv_db
```

## Converting from TMF to OpenVault

The following provides an overview of the steps to convert from TMF to OpenVault. For assistance, contact SGI Professional Services.

Do the following:

1. Stop DMF.
2. Stop TMF.
3. Configure OpenVault. Ensure that the OpenVault library control program (LCP) uses the same ACSLS ID as TMF. For more information see:
  - "OpenVault Configuration Tasks" on page 491
  - *OpenVault Administrator Guide for SGI InfiniteStorage*
  - `ov_admin(8)` man page
4. Import the media into OpenVault using the `dmov_makecarts(8)` command, which adds the appropriate information so that tapes can be mounted via OpenVault and assigns the tapes to the OpenVault `dmf` application.

For each cartridge type at your site, enter one of the following commands

```
# dmov_makecarts -g cartgroup -t carttype lname

# dmov_makecarts -g cartgroup -t carttype -v vg1,vg2 lname

# dmov_makecarts -g cartgroup -t carttype taskgroup
```

where:

<i>cartgroup</i>	Specifies the cartridge group
<i>carttype</i>	Specifies the cartridge type
<i>lname</i>	Specifies the library server
<i>taskgroupname</i>	Specifies the name of the <code>taskgroup</code> object

*vg1,vg2*

Specifies the volume groups

---

**Note:** In some situations, such as STK T100000A and T100000B tapes, the above procedure does not apply because you must use the `ov_import(8)` command with the `-b` option to set the `PartitionBitFormat` field when you load the tapes. For more information, contact SGI Professional Services.

---

5. Edit the DMF configuration file to set the `MOUNT_SERVICE` parameter to `openvault` (or delete the parameter). See:
  - "device Object Parameters" on page 348
  - "drivegroup Object Parameters" on page 397



## Considerations for Partial-State Files

This section discusses the following:

- "Performance Cost Due to Lack of Linux Kernel Support" on page 779
- "Inability to Fulfill Exact Byte Range Requests" on page 780

### Performance Cost Due to Lack of Linux Kernel Support

The Linux kernel does not provide underlying support for partial-state files. A partial-state file looks exactly like an offline file to the filesystem, and so all read requests for a partial-state file generate a DMF daemon read event, whether the byte range being read is actually already online or not. The DMF daemon will write an attribute to a partial-state file that includes the number and boundaries of each region so that any read event whose byte range is completely contained in an online region will return immediately to the kernel with no intervening recall. A read event whose byte range is not completely contained in an online region will result in the entire file being recalled.

Because there is no underlying support in the Linux kernel, the DMF partial-state file feature has a performance cost. The kernel cannot detect when a read request could be satisfied without a read event being generated to the DMF daemon, resulting in pseudo read events that cannot be absorbed by the system and therefore impact the system's performance. A performance degradation will be noticed if thousands of pseudo read events are being generated in a short period of time.

For example, if a very large file has a very large online region followed by a very small offline region and a process is doing a sequential read through the file using a small buffer size, each of the reads for the online region will result in a pseudo read event until finally a read for the offline region will cause the rest of the file to be brought back online. A single process doing this kind of operation might not impact the system, but tens or hundreds of simultaneous similar processes may. In this situation, it might be better to manually recall the file before doing the read.

Additionally, the pseudo read events will result in DMF daemon log-file entries for each read, and so the DMF `SPOOL_DIR` directory may experience a very significant increase in the amount of disk space that is consumed each day. If this is the case, the `SPOOL_DIR` directory will require maintenance (file removal) on a more frequent basis.

## Inability to Fulfill Exact Byte Range Requests

User files can become partial-state either manually or automatically. The manual method involves using the byte-range parameters on the `dmput(1)` and `dmget(1)` commands. (See the man pages for a full description of the syntax of the byte-range specifications). You can use these commands to manually control which regions of a user file should be made online or offline, subject to the restrictions of the underlying filesystem and the maximum number of regions allowed in that filesystem.

All currently supported filesystems have a restriction that punching a hole in a file (to make a region offline) must take place on a fixed boundary size, usually on a 4096-byte block boundary. If a user requested an offline region from byte 10000 to byte 20000, the resulting offline byte range would be from byte 12288 to byte 16384. Offline regions are rounded inward, which might result in fewer bytes than specified being made offline, but will never result in more bytes than specified being made offline.

When requesting online regions, the byte addresses are rounded outward. So in the 10000-20000 byte address example, the resulting online region would be from byte 8192 to byte 20480 based on the idea that it is better to bring some extra bytes online than to not bring all of the bytes that were requested online.

It is entirely possible that a `dmput` or `dmget` request that specifies a byte-range parameter will result in no action on the file taking place. This is possible if the file is already in the requested state (just like using `dmget` on a `DUALSTATE` file before the introduction of partial-state files) or if the requested state would result in more than the maximum number of regions allowed by the filesystem per file. (See the `MAX_MANAGED_REGIONS` configuration file parameter in "filesystem Object" on page 350.) Because of the general inability of DMF to deliver the exact byte ranges requested, requests that do not deliver exact byte range results do not return an error. It is up to the caller to determine the exact state of the file after the request.

## Case Study: Impact of Zone Size on Tape Performance

This appendix details an experiment with a 100 MB/s LTO4 drive, which is in the same performance class as the STK T10000A. The purpose of the test was to show the cost of having a small zone size (the `ZONE_SIZE` parameter, see "volumegroup Object" on page 410).

The `moverlog.yyyymmdd` log traces show two tests:

- In the first test, we migrated 200 512-MB files to tape using a `ZONE_SIZE` of 10g (10 GB). This resulted in 10 zones.
- In the second test, we recalled all the files, changed the `ZONE_SIZE` to 499m (499 MB), and remigrated the same 200 files. In the second test, each migrated file became its own zone (200 zones).

In the first test (with a `ZONE_SIZE` of 10g), the tape drive achieved 118-MB/s per zone. This is the drive's full streaming rate. For example, the drive spent 89.6 seconds doing I/O to the first zone and only 1.48 seconds flushing the first zone:

```
12:49:54-V 102037-dmatwc process_completed_zone: Zone 1 written, chunks=21, bytes=10752000000
12:49:54-V 102037-dmatwc stats: idle=0.00, mount=32.27, skip=0.00, io=89.60, zone=1.48
12:49:54-V 102037-dmatwc stats: total chunks=21, mb=10752.000000, rate=118.05 mb/s
```

When the first migration test was complete, the `dmatwc` final statistics showed that the drive consistently achieved 114 MB/s, and the effective rate (if you include mount/unmount/zone/close/rewind time) was 89 MB/s (line breaks shown here for readability):

```
13:06:55-I 102037-dmatwc final_stats: idle=107.66, mount=32.27, skip=0.00, io=868.54,
zone=20.84, close=81.29, unmount=34.19
13:06:55-I 102037-dmatwc final_stats: total sec = 1144.78, totalmb=101911.101562, rate=114.59 mb/s, effective
rate=89.02 mb/s
```

In the second test (with a `ZONE_SIZE` of 499m), the increased stop/start behavior of the drive meant that the drive only achieved about half of its native rate, or 67.28 MB/s (line breaks shown here for readability):

```
13:19:53-V 104013-dmatwc process_completed_zone: Req=4,6dc90 done, chunk=7, zone=4,
chunklength=512000000, bytes=512000000
13:19:53-V 104013-dmatwc process_completed_zone: Zone 4 written, chunks=1, bytes=512000000
```

```
13:19:53-V 104013-dmatwc stats: idle=0.01, mount=31.88, skip=0.00, io=23.70, zone=5.93
13:19:53-V 104013-dmatwc stats: total chunks=1, mb=512.000000, rate=67.28 mb/s
```

When the second migration test was complete, the dmatwc final statistics show that the drive was only able to achieve 66 MB/s when it was doing I/O. Furthermore, 304.58 seconds were spent just flushing data (versus 20 seconds in the first test). Thus the effective rate in the second case was only 56 MB/s (line breaks shown here for readability):

```
13:48:57-I 104013-dmatwc final_stats: idle=114.54, mount=31.88, skip=0.00, io=1237.52,
zone=304.58, close=82.74, unmount=34.09
13:48:57-I 104013-dmatwc final_stats: total sec = 1805.36, totalmb=102248.742188, rate=66.30 mb/s, effective
rate=56.64 mb/s
```

Had we done a larger test and written an entire tape in each case, the mount, unmount, and close (rewind) time would have contributed much less to the effective bandwidth, and so the numbers would be even more dramatic.

You can obtain the statistics discussed in this appendix from the following log file:

*SPOOL\_DIR/ls\_name/moverlogs/hostname/moverlog.yyyymmdd*

For more information, see:

- "Improve Drive Performance with an Appropriate VG Zone Size" on page 105
- "LS Logs" on page 539

## Historical Feature Information

This appendix contains the following:

- "End of Life for the Tape Autoloader API with DMF 2.6.3" on page 783
- "DMF Directory Structure Prior to DMF Release 2.8" on page 783
- "End of Life for the Tape MSP after DMF 3.0" on page 784
- "DMF User Library (`libdmfusr.so`) Update in DMF 3.1" on page 784
- "Downgrading and the Site-Tag Feature Introduced in DMF 3.1" on page 785
- "Downgrading and the Partial-State File Feature Introduced in DMF 3.2" on page 786
- "`dmaudit(8)` Changes in DMF 3.2" on page 787
- "Logfile Changes in DMF 3.2" on page 787
- "Possible DMF Database Lock Manager Incompatibility On Upgrades as of DMF 3.8.3" on page 788

### End of Life for the Tape Autoloader API with DMF 2.6.3

With the release of DMF 2.6.3, DMF dropped support for the tape autoloader API. DMF supports OpenVault and TMF as tape mounting services. If you have not yet acquired OpenVault or TMF, do not upgrade to any version of DMF 2.6.3 or later.

### DMF Directory Structure Prior to DMF Release 2.8

Beginning with DMF 2.8, DMF no longer supports multiple installed versions of DMF that can be made active via the `dmmain(8)` program. While it is not necessary to delete any existing pre-2.8 versions of DMF, they will not be accessible by the DMF 2.8 or later software and they can be removed at the convenience of the administrator.

The reason for this change is that the pre-2.8 DMF directory hierarchy of `/usr/dmf/dmbase` is no longer the target installation directory of DMF. Rather, DMF 2.8 and later binaries, libraries, header files, and man pages are installed directly into

the proper system locations and they are accessed directly from those locations without the use of symbolic file links.

When DMF 2.8 or later is installed, if the symbolic file link `/etc/dmf/dmbase` exists, it will be deleted. This link was used in pre-2.8 versions of DMF to access the active version of DMF, and as such, it was part of the administrators' initialization procedure to add this link to their `PATH` environment variable. Because it is no longer used in DMF 2.8 and later versions, it could cause an incorrect copy of a DMF command to be executed if an administrator's path included the link to be searched before the normal system binary locations. This way, even if the administrator neglects to remove the link from the path, it should not make any difference.

## End of Life for the Tape MSP after DMF 3.0

DMF 3.0 was the last major release cycle that contained support for the tape MSP. The `dmatmsp` command is not included as part of any DMF 3.5 or later package. When the library server (LS) was introduced in DMF 2.7, the intention was for all existing tape MSPs to be converted to LSs eventually.

It is mandatory that you complete the conversion from tape MSPs to LSs before installing DMF 4.0 or later. SGI highly recommends that you install DMF 3.0.1 for the purpose of doing the conversion because the `dmmsptols` command in that release is much more efficient in terms of time and disk space than in any earlier release.

For more information regarding converting tape MSPs to LSs, see Chapter 14, "Library Servers and Media-Specific Processes" on page 531 or contact SGI Support.

## DMF User Library (`libdmfusr.so`) Update in DMF 3.1

The DMF user library (`libdmfusr.so`) was modified significantly in DMF 3.1 and is not backwards compatible with applications written and linked with pre-3.1 versions of `libdmfusr.so`. The library's naming convention has also changed.

This change only impacts sites with site-written applications that link with `libdmfusr.so`. Any site that does have any such applications should immediately refer to Appendix B, "DMF User Library `libdmfusr.so`" on page 681 to find the steps required to keep your site applications operational.

## Downgrading and the Site-Tag Feature Introduced in DMF 3.1

DMF 3.1 introduced the site tag feature; see `dmtag(1)`. Site tags are stored in the DMF extended attribute on files. This means that if you have installed and run DMF 3.1 or later and wish to run an earlier version of DMF (pre-DMF 3.1), you must ensure that there are no nonzero site tags on files before installing the earlier version of DMF. Failure to do this will cause errors when running the earlier version of DMF.

---

**Note:** Restoring a file that had a site tag from a filesystem backup created while DMF 3.1 or later was running to a system running a pre-3.1 version of DMF is not recommended, because the attribute will appear invalid to the pre-3.1 version of DMF.

---

To ensure that there are no nonzero site tags, do the following:

1. While DMF is running, execute the following script to clear all site tags in managed filesystems:

```
# /usr/lib/dmf/support/dmcleartag
```

This command can take some time to run. If there are other DMF requests active for files whose site tags must be cleared, the request to clear the site tag may be queued behind the other request.

2. If the `dmcleartag` script completed without errors, stop DMF.
3. It is possible that a site tag was set on a file while the `dmcleartag` script was running, and so there may still be files with nonzero site tags. To verify that there are no nonzero site tags in the managed filesystems, run the following script:

```
# /usr/lib/dmf/support/dmanytag
```

The script will print a message to `stderr` if any nonzero site tags are found. If any are found, restart DMF, and repeat step 1. Otherwise, proceed to step 4.

4. Site tags may also be put on files in the DCM or disk MSP `STORE_DIRECTORY`. The `dmcleartag` script run in step 1 will clear the site tags on many of these files. However, if there are any soft-deleted files in the DCM or disk MSP `STORE_DIRECTORY` that have a non-zero site tag, they must be handled while the DMF daemon is not running. Run the following script to clear the tags on soft-deleted DCM MSP copies while `dmfdaemon` is stopped:

```
# /usr/lib/dmf/support/dmcleardcmtag
```

The DMF attributes should now be in a proper state for running a previous version of DMF.

## Downgrading and the Partial-State File Feature Introduced in DMF 3.2

DMF 3.2 introduced the partial-state file feature. Partial-state (PAR) files are not handled by earlier versions of DMF. If customers have installed and run DMF 3.2 or later and then wish to run an earlier version of DMF (pre-DMF 3.2), they must ensure that there are no partial-state files in the managed filesystems before installing the earlier version of DMF. Failure to do this will cause errors when running the earlier version of DMF.

Follow these steps to ensure that there are no partial-state files:

1. While DMF 3.2 is running, execute the following script to change all partial-state files in managed filesystems to be offline:

```
# /usr/lib/dmf/support/dmclearpartial
```

This command may take some time to run. If there are other DMF requests active for the partial-state files, the request to make them offline may be queued behind the other request.

2. If the `dmclearpartial` script completed without errors, stop DMF.
3. It is possible that a file was changed to partial-state while the `dmclearpartial` script was running, and so there may still be partial-state files. Verify that there are no partial-state files in the managed filesystems by running the following script:

```
# /usr/lib/dmf/support/manypartial
```

This script will print a message to `stderr` if any partial-state files are found. If any are found, restart DMF and repeat step 1. Otherwise, proceed to step 4.

4. The partial-state files should now be offline and in a proper state for running a previous version of DMF. If you are installing a version of DMF prior to DMF 3.1, you must also ensure that there are no site tags on managed files. See the instructions below.



---

**Note:** While site tags are being cleared, it is possible that files will be made partial-state. Before running a version of DMF prior to DMF 3.1, check (while DMF is stopped) both that there are no partial-state files and that there are no files with site tags.

---

## `dmaudit`(8) Changes in DMF 3.2

The format of some of the files that `dmaudit` writes changed in DMF 3.2. The DMF 3.2 or later version of `dmaudit` is unable to read the files written by pre-DMF 3.2 versions of `dmaudit`. This means that after upgrading DMF to version 3.2 or later from a pre-DMF 3.2 version, the first time you use `dmaudit`, you must select the `snapshot` option before you can use the `inspect` option.

## Logfile Changes in DMF 3.2

A change was made in DMF 3.2 to the way that the DMF daemon and the library server (LS) and MSPs refer to the daemon request number. This change should make it easier for administrators to extract all of the pertinent messages from the `SPOOL_DIR` logs for a particular request.

In previous releases of DMF, the string `Req=xxx` could be used to extract some log messages for daemon request number `xxx`, but there were some messages in the form `Req=xxx/nnn` that would not be found (such as by using the `grep(1)` command) with a pattern of `Req=xxx`.

A change was made to standardize all daemon and LS/MSP log messages to use the form `Req=xxx` for all messages. As a result, a log message formerly of the form `Req=xxx/nnn` would now take the form `Req=xxx, nnn` so as to be visible via the `grep` pattern `Req=xxx`. If your site uses these patterns to search DMF `SPOOL_DIR` logs, please be advised of this change and update any scripts or procedures accordingly.

## Possible DMF Database Lock Manager Incompatibility On Upgrades as of DMF 3.8.3

The DMF 3.8.3 version of DMF introduced decreased DMF database lock manager delays when processes are making simultaneous lock requests. This code also introduced a backwards incompatibility between pre-3.8.3 `dmlockmgr` processes and post-3.8.3 `dmlockmgr` clients. If DMF is stopped (as recommended) via `/etc/init.d/dmf stop` immediately before installing DMF 3.8.3 or later (in a non-HA environment), there will be no incompatibility.<sup>1</sup>

If, however, one of the DMF administrator commands (`dmdadm`, `dmvoladm`, or `dmcatadm`) is executed after DMF has been stopped and DMF 3.8.3 or later is installed, new `dmlockmgr` clients will hang when trying to request database locks from an older version of `dmlockmgr` that was executing as the result of the administrator command.

For this reason, it is important to make sure that DMF, including the `dmlockmgr` process, is stopped via `/etc/init.d/dmf stop` immediately before installing DMF 3.8.3 or later even if the DMF daemon is not running, if you are upgrading from a pre-3.8.3 version of DMF.

---

<sup>1</sup> In an HA environment, you must first remove HA control of the resource group before stopping DMF and the mounting service. See the *High Availability Guide for SGI InfiniteStorage*

## Using `dmmaint` to Install Licenses and Configure DMF

---

**Note:** The `dmmaint` command is deprecated and will be removed in a future release. The preferred tool is DMF Manager; see "Configuring DMF with DMF Manager" on page 210.

---

On DMF servers, you can use `dmmaint` to install your DMF licenses and edit the DMF configuration file. The advantage to using `dmmaint` rather than a text editor such as `vi` is that you can edit the configuration file, verify your changes, and apply your changes atomically.

This appendix discusses the following:

- "Overview of `dmmaint`" on page 789
- "Installing the DMF License" on page 791
- "Using `dmmaint` to Define the Configuration File" on page 791

### Overview of `dmmaint`

To use the `dmmaint` graphical user interface (GUI), ensure that your `DISPLAY` environment variable is defined, and then enter the following command:

```
# /usr/sbin/dmmaint &
```

---

**Note:** If `DISPLAY` is not defined, `dmmaint` reverts to line mode, which has menu selections that are equivalent to the fields and buttons on the graphic user interface. Line mode is provided for remote log in but is not recommended for general use.

---

The GUI displays the installed version of DMF. The **Help** menu provides access to the `dmmaint` and `dmf.conf` man pages.

The GUI buttons are as follows:

<b>Button</b>	<b>Description</b>
<b>Configure</b>	<p>Lets you customize the DMF configuration file for the selected version of DMF.</p> <p>If this is the first time you have configured DMF, a window appears telling you that there is no configuration file. You are asked which file you would like to use as a basis for the new configuration. You may choose an existing file or one of several sample files that are preconfigured for different types of media-specific process (MSP) or the library server (LS). See "Use Sample DMF Configuration Files" on page 101.</p> <p>If a configuration file exists, a window appears that asks if you would like to modify the existing file or use an alternate file. If you choose an alternate file, you see the same window that you would see if this were a new configuration.</p> <p>After you choose a file to use as a basis, an editing session is started (in a new window) that displays a copy of that configuration file. You can make changes as desired. After exiting from the editor, you are prompted for confirmation before the original configuration file is replaced with the edited copy.</p> <p>For more information on configuration parameters, see Chapter 7, "DMF Configuration File" on page 271, and the <code>dmf.conf(5)</code> man page (available from the <b>Help</b> button).</p>
<b>Inspect</b>	<p>Runs the <code>dmcheck(8)</code> program to report errors. You should run this program after you have created a configuration file. If there are errors, you can click the <b>Configure</b> button, make changes, and continue to alternate between <b>Configure</b> and <b>Inspect</b> until you are satisfied that the configuration is correct.</p>
<b>Release Note</b>	<p>This button displays the DMF release note that is installed in <code>/usr/share/doc/packages/sgi-issp-<i>ISSPversion</i>/README_DMF.txt</code></p>

<b>License Info</b>	Displays the hostname and unique system identifier (which you need to obtain a DMF server license), the name of the license file, and a short description of the state of any DMF license within the file.
<b>Update License</b>	Lets you make changes to the license file. An editing session is started in a new window displaying a copy of the contents of the license file. You can add or delete licenses as desired. After you exit the editor, positive confirmation is requested before the original license file is replaced by the modified copy. For more information, see Chapter 2, "DMF Licensing" on page 67.

## Installing the DMF License

To install the DMF license, do the following:

1. Select **Dependencies** to read about the hardware and software requirements that must be fulfilled before running DMF.
2. If needed, select the **Update License** button and use the mouse to copy and paste your license into the file. Close the window. Select **License Info** and examine the output to verify that the license is installed correctly.

## Using `dmmaint` to Define the Configuration File

To use `dmmaint` to configure DMF, do the following:

1. Select **Configure** to edit the configuration file.
2. Click the **Inspect** button, which runs `dmcheck` to report any errors in the configuration. If there are errors, you can click the **Configure** button, make changes, and continue to alternate between **Configure** and **Inspect** until you are satisfied that the configuration is correct.

If you do not want DMF to be automatically started and stopped, see "Starting and Stopping the DMF Environment" on page 181.



---

## Glossary

### **accelerated access to first byte**

A partial-state file feature capability that allows you to access the beginning of an offline file before the entire file has been recalled.

### **active database entry**

A daemon database entry whose BFID points to a valid file in the filesystem. See also *BFID* and *soft-deleted database entry*.

### **active metadata server**

A CXFS server-capable administration node chosen from the list of potential metadata servers. There can be only one active metadata server for any given filesystem. See also *metadata*.

### **active parallel data-mover node**

A parallel data mover node that has been enabled using `dmnode_admin(8)`, has not exceeded the number of parallel data-mover node licenses on the DMF server, and is connected to the `dmnode` service on the DMF server. See also *parallel data-mover node* and *parallel data-mover node license*.

### **ADMDIR\_IN\_ROOTFS**

The list of DMF administrative and store directories that can reside in the root (/) filesystem. See "base Object Parameters" on page 278.

### **ADMIN\_EMAIL**

The e-mail address to receive output from administrative tasks. See "base Object Parameters" on page 278.

### **administrative directories**

See *DMF administrative directories*.

### **AG**

See *allocation group*.

AGE\_WEIGHT

A floating-point constant and floating-point multiplier to use when calculating the weight given to a file's age (for MSP/VG filesystem). See "File Weighting Parameters for a Managed Filesystem" on page 371.

AGGRESSIVE\_HVfy

The parameter that specifies whether or not DMF will set the hvfy flag on volumes in the VOL database for an expanded set of error conditions. See "drivegroup Object Parameters" on page 397.

ALERT\_RETENTION

Specifies the age of alert records that will be kept. See "taskgroup Object Parameters" on page 312.

ALGORITHM

The resource scheduling algorithm to be used. See "resourcescheduler Object Parameters" on page 432.

**allocation group**

(AG) A pool of volumes that can be transferred to a VG as needed and are returned to the pool when empty, subject to VG configuration parameters. The ALLOCATION\_GROUP parameter defines a pool of volumes that have been assigned to the AG via the dmvoladm(8) command. Normally, one allocation group is configured to serve multiple VGs.

ALLOCATION\_GROUP

The parameter that defines the allocation group (AG) that serves as a source of additional volumes if a VG runs out of volumes. See "volume group Object Parameters" on page 411.

allocationgroup

The optional configuration object that defines the VOL\_MSG\_TIME parameter (required only to change the default setting). See "allocationgroup Object Parameters" on page 435.



**ALLOCATION\_MAXIMUM**

The maximum size in number of volumes to which a VG can grow by borrowing volumes from its allocation group. See "volumegroup Object Parameters" on page 411.

**ALLOCATION\_MINIMUM**

The minimum size in number of volumes to which a VG can shrink by returning volumes to its allocation group. See "volumegroup Object Parameters" on page 411.

**alternate media**

The media onto which migrated data blocks are stored, usually tapes.

**ARC**

Scality Advanced Resilience Configuration, which uses erasure code technology to provide redundancy with reduced overhead for large objects

**archive filesystem**

A POSIX filesystem (such as Lustre) configured in a `filesystem` object in the DMF configuration file to have a `MIGRATION_LEVEL` of `archive`. This filesystem cannot be DMAPI-enabled (that is, it cannot be mounted with the `dmi` mount option). You can efficiently copy files between an archive filesystem to DMF secondary storage via the `dmarchive(1)` command.

**automated space management**

The combination of utilities that allows DMF to maintain a specified level of free space on a filesystem through automatic file migration.

**BANDWIDTH\_MULTIPLIER**

(OpenVault only) A floating point number used to adjust the amount of bandwidth that the LS assumes a drive in the DG will use. See "drivegroup Object Parameters" on page 397.

**base object**

The configuration object that defines the file pathname and size parameters necessary for DMF operation. See "base Object Parameters" on page 278.

**basic DMF**

DMF without the Parallel Data-Mover Option.

**BFID**

A unique identifier, assigned to each file during the migration process, that links a migrated file to its data on alternate media.

**BFID set**

The collection of database entries and the file associated with a particular bit-file identifier.

**BFID-set state**

The sum of the states of the components that constitute a bit-file identifier set: the file state of any file and the state of any database entries (incomplete, complete, soft-deleted, or active).

**bit-file ID**

See *BFID*.

**bit-file identifier**

See *BFID*

**block**

Physical unit of I/O to and from media. The size of a block is determined by the type of device being written. A block is accompanied by a header identifying the chunk number, zone number, and its position within the chunk.

**BLOCK\_SIZE**

The maximum block size to use when writing from the beginning of a volume. See "drivegroup Object Parameters" on page 397.

**BORROW\_FROM\_DG**

Specifies a comma-separated list of one or more OpenVault drive groups and maximum drives that are owned by another application (such as DMF) from which LTFS may borrow drives. See "sgi-ltfs.conf Parameters" on page 634.

**BUFFERED\_IO\_SIZE**

The size of I/O requests when reading from a filesystem using buffered I/O. See:

- "filesystem Object Parameters" on page 351
- "m<sub>s</sub>p Object Parameters for a DCM MSP" on page 460

**CACHE\_AGE\_WEIGHT**

The floating-point constant and floating-point multiplier used to calculate the weight given to a file's age (for DCM MSP `STORE_DIRECTORY`). See "File Weighting Parameters for a DCM MSP `STORE_DIRECTORY`" on page 378.

**CACHE\_DIR**

The directory in which the VG stores chunks while merging them from sparse volumes. See "libraryserver Object Parameters" on page 393.

**CACHE\_MEMBERS**

The single VG or one or more MGs to be used as a fast-mount cache. See "fastmountcache Object Parameters" on page 390.

**CACHE\_SPACE**

The amount of disk space (in bytes) that `dmatls` can use when merging chunks from sparse volumes. See "libraryserver Object Parameters" on page 393.

**CACHE\_SPACE\_WEIGHT**

The floating-point constant and floating-point multiplier to use to calculate the weight given to a file's size (for DCM MSP `STORE_DIRECTORY`). See "File Weighting Parameters for a DCM MSP `STORE_DIRECTORY`" on page 378.

**candidate list**

A list that contains an entry for each file in a filesystem eligible for migration, or for a file or range of files that are eligible to be made offline. This list is ordered from largest file weight (first to be migrated) to smallest. This list is generated and used internally by `dmfsmon(8)`.

**capability license**

See *server capability license*.

**capacity license**

See *data capacity license*.

**CAT record**

An entry in the catalog (CAT) table of the LS database that tracks the location of migrated data on a volume. There is one CAT record for each migrated copy of a file. (If a migrated copy of a file is divided onto more than one physical media, there will be a CAT record for each portion.) See also *VOL record*.

**CAT table**

A table in the LS database that contains CAT records. See also *VOL table*.

CHECKSUM\_TYPE

The type of checksum algorithm to use when writing new tapes. See "volumegroup Object Parameters" on page 411.

CHILD\_MAXIMUM

The maximum number of child processes that the MSP is allowed to fork. See:

- "msp Object Parameters for a Cloud MSP" on page 449
- "msp Object Parameters for a DCM MSP" on page 460
- "msp Object Parameters for a Disk MSP" on page 467
- "msp Object Parameters for an FTP MSP" on page 455

**chunk**

That portion of a file that fits on the current media volume. Most small files are written as single chunks. When a migrated file cannot fit onto a single volume, the file is split into chunks.

**CIFS**

Common Internet File System

**client-only node**

A node that is installed with the `cxfs_client.sw.base` software product; it does not run cluster administration daemons and is not capable of coordinating CXFS metadata. See also *server-capable administration node*.

**CLOUD\_BACKEND**

Specifies the backend used by a given cloud instance, which determines how other cloud-specific parameters are interpreted. See "m<sub>SP</sub> Object Parameters for a Cloud MSP" on page 449.

**CLOUD\_BASE\_PATH**

(S3 *only*) Specifies a string that is prefixed to the key (separated from the key by a slash "/" character) in all requests to S3. See "m<sub>SP</sub> Object Parameters for a Cloud MSP" on page 449.

**CLOUD\_BUCKET**

Specifies the name of the existing S3 bucket to use when storing files. See "m<sub>SP</sub> Object Parameters for a Cloud MSP" on page 449.

**CLOUD\_HOST**

Specifies the domain name or IP address of one or more machines that can serve as the cloud host. See "m<sub>SP</sub> Object Parameters for a Cloud MSP" on page 449.

**CLOUD\_PASSWORD**

Specifies the file that contains the cloud password information. See "m<sub>SP</sub> Object Parameters for a Cloud MSP" on page 449.

**CLOUD\_REDUNDANCY**

Specifies the level of data redundancy that is requested from the cloud service. See "m<sub>SP</sub> Object Parameters for a Cloud MSP" on page 449.

**CLOUD\_USER**

Specifies the cloud username information. See "m<sub>SP</sub> Object Parameters for a Cloud MSP" on page 449.

COMMAND

The binary file to execute in order to initiate an MSP or LS. See:

- "libraryserver Object Parameters" on page 393
- "msp Object Parameters for a Cloud MSP" on page 449
- "msp Object Parameters for a DCM MSP" on page 460
- "msp Object Parameters for a Disk MSP" on page 467
- "msp Object Parameters for an FTP MSP" on page 455

**common arena**

A shared-memory region where various DMF processes write configuration information and metrics about DMF if `EXPORT_METRICS` is enabled. Performance Co-Pilot, DMF Manager, `dmstat`, `dmtapestat`, and `dmarenadump` make use of the common arena.

**complete daemon-database entry**

An entry in the daemon database whose `path` field contains a key returned by its MSP or VG, indicating that the MSP or VG maintains a valid copy of the file.

**compression**

The mechanism by which data is reduced as it is written to secondary storage.

COMPRESSION\_TYPE

Specifies the compression type level to be used with COPAN MAID when writing from the beginning of the volume. See "drivegroup Object Parameters" on page 397.

**configuration object**

A series of parameter definitions in the DMF configuration file that controls the way in which DMF operates. By changing the parameters associated with objects, you can modify the behavior of DMF.

**configuration parameter**

A string in the DMF configuration file that defines a part of a configuration object. By changing the values associated with these parameters, you can modify the behavior of

DMF. The parameter serves as the name of the line. Some parameters are reserved words, some are supplied by the site.

**configuration stanza**

A sequence of configuration parameters that define a configuration object.

**COPAN MAID**

Power-efficient long-term data storage based on an enterprise massive array of idle disks (MAID) platform.

**COPAN VTL**

Power-efficient long-term data storage based on an enterprise MAID platform using a virtual tape library (VTL).

**COPAN\_VSNS**

A parameter that specifies that the fourth character of the volume serial number (VSN) indicates the RAID in the COPAN VTL or COPAN MAID that contains the volume. This specification applies for all VSNs in this library server. See "libraryserver Object Parameters" on page 393.

**CXFS**

Clustered XFS, a parallel-access shared clustered filesystem for high-performance computing environments.

**daemon**

A program that is run automatically by the system for a specific purpose.

**daemon database**

A database maintained by the DMF daemon. This database contains information such as the bit-file identifier, the MSP or VG name, and MSP or VG key for each copy of a migrated file.

**DASD**

See *direct-access storage device*.

**data capacity license**

One or more cumulative DMF licenses that permit DMF migration, corresponding to the amount of data that DMF is currently managing. See also *server capability license*.

**data integrity validation**

See *logical block protection*.

**DATA\_LIMIT**

The maximum amount of data (in bytes) that should be selected for merging at one time. See "taskgroup Object Parameters" on page 312.

**DATABASE\_COPIES**

One or more directories into which a copy of the DMF databases will be placed. See "taskgroup Object Parameters" on page 312.

**data mover**

A node running *data-mover processes* to migrate and recall data to secondary storage, either a *DMF server* or a *parallel data-mover node*.

**data-mover processes**

The individual processes that migrate data (using the *write child*) and recall data (using the *read child*).

**data-pointer area**

The portion of the inode that points to the file's data blocks.

**device object**

The configuration object that defines parameters for the DMF backup scripts' use of tape devices other than those defined by a DG. See "device Object Parameters" on page 348.

**DCM MSP**

The *disk cache manager* MSP is the disk MSP configured for *n*-tier capability by using a dedicated filesystem as a cache. DMF can manage the disk MSP's storage filesystem



and further migrate it to tape or MAID, thereby using a slower and less-expensive dedicated filesystem as a cache to improve the performance when recalling files.

## **DG**

See *drive group*.

### `DIRECT_IO_MAXIMUM_SIZE`

The maximum size of I/O requests when using `O_DIRECT` I/O to read from any managed filesystem or when migrating files down the hierarchy from the `STORE_DIRECTORY` of a DCM MSP. See "base Object Parameters" on page 278.

### `DIRECT_IO_SIZE`

The size of I/O requests when reading from this filesystem using direct I/O. See:

- "filesystem Object Parameters" on page 351
- "msp Object Parameters for a DCM MSP" on page 460

## **Disaster-recovery bundle**

A component produced during integrated backups that contains configuration information, the XFS inventory, a dump of the backup filesystem, and the disaster-recovery database (containing the DMF database entries that correspond to the backup filesystem)

### `DISCONNECT_TIMEOUT`

Specifies the number of seconds after which the LS will consider a mover process to have exited if it cannot communicate with the process. See "libraryserver Object Parameters" on page 393.

## **disk backups**

Traditional (nonintegrated) backups to disk using `xfsdump`. See also *integrated backups* and *tape backups*.

## **disk cache**

Data on secondary storage.

**disk cache manager**

See *DCM MSP*.

**DMAPI**

Data Management Application Programming Interface.

**DMF administrative and store directories**

The set of directories in which DMF stores databases, log and journal files, and temporary files. The DMF configuration file specifies these directories using the following parameters:

HOME\_DIR  
JOURNAL\_DIR  
SPOOL\_DIR  
TMP\_DIR  
MOVE\_FS  
CACHE\_DIR

**dmdaemon object**

The configuration object that defines parameters necessary for `dmfdaemon(8)` operation. See "dmdaemon Object Parameters" on page 290.

**DMF daemon**

The program that accepts requests to migrate data, communicates with the operating system kernel in order to maintain a file's migration state, determines the destination of migrated data, and requests the return of offline copies.

**DMF direct archiving**

The DMF feature that lets users manually archive files from an unmanaged POSIX filesystem directly to secondary storage via the `dmarchive(1)` command. See "Direct Archiving" on page 13.

**DMF server**

A node running the required DMF server software that provides DMF administration, configuration, and data mover functionality. (When using the Parallel DMF, data mover functionality is optional on the DMF server.) See *Parallel Data-Mover Option*.

**DMF state**

See *file state*.

**DMMIGRATE\_MINIMUM\_AGE**

The minimum file age to migrate in minutes (the `dmmigrate -m minutes` option). See "taskgroup Object Parameters" on page 312.

**DMMIGRATE\_MIN\_OFFLINE\_AGE**

The value used for the `-p` option (in minutes) when `dmmigrate` is executed by the `run_dmmigrate.sh` task. This value is a file's minimum age in order for its data blocks to be released, making the file offline. See "taskgroup Object Parameters" on page 312.

**DMMIGRATE\_MIN\_OFFLINE\_SIZE**

The value used for the `-s` option (in bytes) when `dmmigrate` is executed by the `run_dmmigrate.sh` task. This value is a file's minimum size in order for its data blocks to be released, making the file offline. See "taskgroup Object Parameters" on page 312.

**DMMIGRATE\_QUEUE\_MAX**

The parameter that specifies the maximum number of `dmmigrate` requests that can be outstanding in the DMF daemon queue at any given time when `dmmigrate` is executed by the `run_dmmigrate.sh` task; when this threshold is reached, the command waits before issuing more requests. See "taskgroup Object Parameters" on page 312.

**DMMIGRATE\_TRICKLE**

The parameter that specifies whether or not `dmmigrate` limits the rate at which an individual `dmmigrate` command issues requests so that it will not dominate the DMF daemon (that is, the same behavior as using the `dmmigrate -t` option). See "taskgroup Object Parameters" on page 312.

**DMMIGRATE\_UNACK**

The maximum number of unacknowledged requests that can be outstanding at any given time in. See "taskgroup Object Parameters" on page 312.

DMMIGRATE\_VERBOSE

The parameter that specifies whether or not `dmmigrate` will display how many files and bytes are migrating (the `dmmigrate -v` option). See "taskgroup Object Parameters" on page 312.

DMMIGRATE\_WAIT

The parameter that specifies whether or not `dmmigrate` will wait for all migrations to complete before exiting (the `dmmigrate -w` option). See "taskgroup Object Parameters" on page 312.

**DR bundle**

Disaster-recovery bundle

**drive**

A hardware device that reads and writes data to media.

**drive group**

(DG) One of the components of an LS. The drive group is responsible for the management of a group of interchangeable drives located in the library. These drives can be used by multiple VGs and by non-DMF processes, such as backups and interactive users. The main tasks of the DG are to monitor I/O for errors, to attempt to classify them (as volume, drive, or mounting service problems), and to take preventive action. When this document refers to *DG*, it indicates the *DMF drive group*. See also *OpenVault drive group*.

**drivegroup object**

The configuration object that defines a DG, one for each pool of interchangeable drives in a single library. See "drivegroup Object Parameters" on page 397.

DRIVE\_GROUPS

One or more DGs containing drives that the LS can use for mounting and unmounting volumes. See "libraryserver Object Parameters" on page 393.

**DRIVE\_MAXIMUM**

The maximum number of drives that the DG or an individual VG is allowed to attempt to use simultaneously. See:

- "drivegroup Object Parameters" on page 397
- "volumegroup Object Parameters" on page 411

**DRIVE\_SCHEDULER**

The resource scheduler that the DG should run for the scheduling of drives. See:

- "drivegroup Object Parameters" on page 397
- "volumegroup Object Parameters" on page 411

**DRIVES\_TO\_DOWN**

An integer value that controls the number of "bad" drives the DG is allowed to try to configure down. See "drivegroup Object Parameters" on page 397.

**DRIVETAB**

This optional parameter provides the name of a file that is used with the `tsreport --drivetab` option, which causes the `run_daily_drive_report` and `run_daily_tsreport` output to contain the more readable drive name instead of the device name. See "taskgroup Object Parameters" on page 312.

**DSK\_BUFSIZE**

The transfer size in bytes used when reading from and writing to files within the disk MSP's `STORE_DIRECTORY`. See:

- "msp Object Parameters for a DCM MSP" on page 460
- "msp Object Parameters for a Disk MSP" on page 467

DUALRESIDENCE\_TARGET

The percentage of DCM MSP cache capacity that DMF maintains as a reserve of dual-state files whose online space can be freed if free space reaches or falls below FREE\_SPACE\_MINIMUM (for DCM MSP STORE\_DIRECTORY). See:

- "Automated Space-Management Parameters for a DCM MSP STORE\_DIRECTORY" on page 376
- "msp Object Parameters for a DCM MSP" on page 460

**dual-resident file**

A file whose data resides online and offline in both in cache and tape/MAID (analogous to a *dual-state file*), for DMF using a DCM MSP.

**dual-state file**

A file whose data resides both online and offline.

DUL

See *dual-state file*

DUMP\_COMPRESS

(*disk and integrated backups only*) The compression type and level to be used with backups. See:

- "dumpgroup Object Parameters" on page 343
- "filesystem Object Parameters" on page 351
- "taskgroup Object Parameters" on page 312

DUMP\_CONCURRENCY

(*disk and integrated backups only*) The maximum number of filesystems that will be dumped simultaneously. See "taskgroup Object Parameters" on page 312.

DUMP\_DATABASE\_COPY

(*third-party backups only*) The path to a directory where a snapshot of the DMF databases will be placed when do\_predump.sh is run. See "DUMP\_DATABASE\_COPY Configuration File Parameter in the taskgroup Object" on page 768.

**DUMP\_DESTINATION**

*(disk and integrated backups only)* The directory in which to store backups. See "taskgroup Object Parameters" on page 312.

**DUMP\_DEVICE**

*(tape backups only)* The name of the DG in the configuration file that defines how to mount the tapes that the backup tasks will use. See "taskgroup Object Parameters" on page 312.

**DUMP\_DR\_EMAIL**

*(integrated backups only)* Specifies one or more email addresses to which the disaster-recovery bundle is sent. See "taskgroup Object Parameters" on page 312.

**DUMP\_DR\_EMAIL\_MAX\_SIZE**

*(integrated backups only)* Specifies the maximum size of the disaster-recovery bundle that will be attached to the email sent to the addresses specified by **DUMP\_DR\_EMAIL**. See "taskgroup Object Parameters" on page 312.

**DUMP\_DR\_MINIMAL**

*(integrated backups only)* Specifies whether or not the backup process produces a disaster-recovery bundle of the smallest possible size. See "taskgroup Object Parameters" on page 312.

**DUMP\_DR\_MIRRORS**

*(integrated backups only)* Specifies one or more directories in which to place a copy of the disaster-recovery bundle. See "taskgroup Object Parameters" on page 312.

**DUMP\_FILE\_SYSTEMS**

*(disk, tape, and integrated backups)* One or more filesystems to back up. See:

- "dumpgroup Object Parameters" on page 343
- "taskgroup Object Parameters" on page 312

DUMP\_FLUSH\_DCM\_FIRST

*(disk, tape, and integrated backups)* Specifies whether or not the `dmigrate` command is run before the backups are done to ensure that all non-dual-resident files in the DCM MSP caches are migrated to tape/MAID. See:

- "msp Object Parameters for a DCM MSP" on page 460
- "taskgroup Object Parameters" on page 312

DUMP\_GROUPS

*(integrated backups only)* Specifies a list of `dumpgroup` objects separated by spaces. See "taskgroup Object Parameters" on page 312.

`dumpgroup` **object**

*(integrated backups only)* The configuration object that defines dump parameters that apply to a specific subset of filesystems.

DUMP\_INVENTORY\_COPY

*(tape backups only)*The pathnames of one or more directories into which are copied the XFS inventory files for the backed-up filesystems. See "taskgroup Object Parameters" on page 312.

DUMP\_MAX\_FILESPACE

*(disk, tape, and integrated backups)* The maximum disk space used for files to be dumped, which may be larger or smaller than the length of the file. See:

- "dumpgroup Object Parameters" on page 343
- "filesystem Object Parameters" on page 351
- "taskgroup Object Parameters" on page 312

DUMP\_MIGRATE\_FIRST

*(disk, tape, and integrated backups)* The parameter that specifies whether or not the `dmigrate` command is run before the backups are done to ensure that all



migratable files in the managed filesystems are migrated, thus reducing the amount of media space needed for the dump and making it run much faster. See:

- "dumpgroup Object Parameters" on page 343
- "filesystem Object Parameters" on page 351
- "taskgroup Object Parameters" on page 312

#### DUMP\_MIRRORS

*(disk and integrated backups only)* One or more directories in which to place a copy of nonintegrated disk backups. See "taskgroup Object Parameters" on page 312.

#### DUMP\_MISC\_LOCATIONS

*(integrated backups only)* Specifies one or more full pathnames that must be included in the dump. See "taskgroup Object Parameters" on page 312.

#### DUMP\_POST\_BACKUP\_SCRIPT

*(integrated backups only)* Specifies the full pathname to a user script that is run just before the disaster-recovery bundle is created (after the filesystem dumps, database snapshots, and so on are complete) . See "taskgroup Object Parameters" on page 312.

#### DUMP\_POST\_DR\_SCRIPT

*(integrated backups only)* Specifies the full pathname to a user script that is run just after the disaster-recovery bundle is created. See "taskgroup Object Parameters" on page 312.

#### DUMP\_PRE\_BACKUP\_SCRIPT

*(integrated backups only)* Specifies the full pathname to a user script that is run just before the backup is performed. See "taskgroup Object Parameters" on page 312.

#### DUMP\_RETENTION

*(disk, tape, and integrated backups)*The length of time that the backups of the filesystem will be kept before the backup space is reused. See "taskgroup Object Parameters" on page 312.

DUMP\_STREAMS

*(disk and integrated backups only)* The number of `xfsdump` streams (threads) to use when backing up a filesystem. See:

- "dumpgroup Object Parameters" on page 343
- "filesystem Object Parameters" on page 351
- "taskgroup Object Parameters" on page 312

DUMP\_TAPES

*(tape backups only)* The path of a file that contains VSNs, one per line, for the backup tasks to use. See "taskgroup Object Parameters" on page 312.

DUMP\_VSNS\_USED

*(tape backups only)* A file in which the VSNs of tapes that are used are written. See "taskgroup Object Parameters" on page 312.

DUMP\_WORKSPACE

*(disk and integrated backups only)* Specifies a local directory used to store temporary files created during a dump process before moving them to the `DUMP_DESTINATION` filesystem. See "taskgroup Object Parameters" on page 312.

DUMP\_XFSDUMP\_PARAMS

*(disk, tape, and integrated backups)* Passes parameters to the `xfsdump` program.

- "dumpgroup Object Parameters" on page 343
- "filesystem Object Parameters" on page 351
- "taskgroup Object Parameters" on page 312

**EOT**

End-of-volume marker (historically known as *EOT* for *end-of-tape*)

**EXPORT\_METRICS**

Enables DMF's use of the common arena for use by Performance Co-Pilot (PCP), `dmstat(8)`, `dmarenadump(8)`, and other commands. See "base Object Parameters" on page 278.

**EXPORT\_QUEUE**

Instructs the daemon to export details of its internal request queue to `SPOOL_DIR/daemon_exports` every two minutes, for use by `dmstat(8)` and other utilities. See "dmdaemon Object Parameters" on page 290.

**FADV\_SIZE\_MAID**

Specifies when to call `posix_fadvise()` with advice `POSIX_FADV_DONTNEED` for COPAN MAID volumes. See "drivegroup Object Parameters" on page 397.

**FADV\_SIZE\_MSP**

Specifies the size of files in the MSP's `STORE_DIRECTORY` for which `posix_fadvise()` will be called with advice `POSIX_FADV_DONTNEED`. See:

- "msp Object Parameters for a DCM MSP" on page 460
- "msp Object Parameters for a Disk MSP" on page 467

**fast-mount cache**

A migration target with fast mount/position characteristics (such as COPAN MAID) that is used in conjunction with another target (such as physical tape). In a fast-mount cache configuration, DMF simultaneously migrates data to a copy on the cache target and to secondary-storage copies on the other targets. This configuration provides similar functionality to a DCM MSP but does not migrate data from the cache to tier-3, so volumes on the cache can be freed immediately when the fullness threshold is reached and volume merging is avoided. A `taskgroup` object is required to empty full volumes in the cache after a specified threshold is reached.

**FC**

Fibre Channel.

**fhandle**

See *file handle*.

**file**

An inode and its associated data blocks; an empty file has an inode but no data blocks.

**file handle**

The DMAPI identification for a file. You can use the `dmscanfs(8)`, `dmattr(1)`, and `dmfind(1)` commands to find file handles.

**file state**

The migration state of a file as indicated by the `dmattr(1)` command. A file can be regular (not migrated), migrating, dual-state, offline, partial-state, unmigrating, never-migrated, or have an invalid DMF state.

**file tag**

A site-assigned 32-bit integer associated with a specific file, allowing the file to be identified and acted upon.

`FILE_RETENTION_DAYS`

The age (in days) of a file that must not be deleted from the fast-mount cache. See "taskgroup Object Parameters" on page 312.

`filesystem` **object**

The configuration object that defines parameters necessary for migrating files in that filesystem. See "filesystem Object Parameters" on page 351.

`FMC_MOVEFS`

The specific scratch `MOVE_FS` filesystem to be used when moving files to be retained in the fast-mount cache. See "taskgroup Object Parameters" on page 312.

`FMC_NAME`

The name of a `fastmountcache` object. See "taskgroup Object Parameters" on page 312.

**FORWARD\_RECALLS**

The parameter that specifies whether or not a recall should be directed to another VG or MSP if the volume required for the recall is busy because it is being written to. See "volumegroup Object Parameters" on page 411.

**FREE\_DUALRESIDENT\_FIRST**

Specifies whether `dmdskfree` will first free dual-resident files before freeing files it must migrate (for DCM MSP `STORE_DIRECTORY`). See "Automated Space-Management Parameters for a DCM MSP `STORE_DIRECTORY`" on page 376.

**FREE\_DUALSTATE\_FIRST**

Specifies whether or not `dmfsfree` will first free dual-state and partial-state files before freeing files it must migrate (for MSP/VG filesystem). See "Automated Space-Management Parameters for a Managed Filesystem" on page 369.

**FREE\_SPACE\_DECREMENT**

The percentage of filesystem space by which `dmfsmon` or `dmdskmsp` will decrement `FREE_SPACE_MINIMUM` (if it cannot find enough files to migrate) so that the value is reached. The decrement is applied until a value is found that `dmfsmon` can achieve. See:

- "Automated Space-Management Parameters for a DCM MSP `STORE_DIRECTORY`" on page 376
- "Automated Space-Management Parameters for a Managed Filesystem" on page 369

**FREE\_SPACE\_MINIMUM**

The minimum integer percentage of the total filesystem space that `dmfsmon` tries to maintain as free. See:

- "Automated Space-Management Parameters for a DCM MSP `STORE_DIRECTORY`" on page 376
- "Automated Space-Management Parameters for a Managed Filesystem" on page 369

`FREE_SPACE_TARGET`

The integer percentage of total filesystem space that `dmfsfree` or `dmdskfree` tries to maintain as free if free space reaches or falls below the `FREE_SPACE_MINIMUM` threshold. See:

- "Automated Space-Management Parameters for a DCM MSP `STORE_DIRECTORY`" on page 376
- "Automated Space-Management Parameters for a Managed Filesystem" on page 369

`FREE_VOLUME_MINIMUM`

The minimum percentage of free volumes in the COPAN MAID or COPAN VTL fast-mount cache that will cause `run_fmc_free.sh` to begin freeing full volumes in order to meet the percentage set for `FREE_VOLUME_TARGET`. See "taskgroup Object Parameters" on page 312.

`FREE_VOLUME_TARGET`

The percentage of volumes in the COPAN MAID or COPAN VTL fast-mount cache that `run_fmc_free.sh` tries to free when the `FREE_VOLUME_MINIMUM` threshold is reached. See "taskgroup Object Parameters" on page 312.

**freed file**

A file that has been migrated and whose data blocks have been released.

**FTP**

File Transfer Protocol

`FTP_ACCOUNT`

The account ID to use when migrating files to the remote system. See "msp Object Parameters for an FTP MSP" on page 455.

`FTP_COMMAND`

Additional commands to send to the remote system. See "msp Object Parameters for an FTP MSP" on page 455.

**FTP\_DIRECTORY**

The directory to use on the remote system. See "m<sub>sp</sub> Object Parameters for an FTP MSP" on page 455.

**FTP\_HOST**

The Internet hostname of the remote machine on which files are to be stored. See "m<sub>sp</sub> Object Parameters for an FTP MSP" on page 455.

**FTP MSP**

The daemon-like media-specific process (MSP) that copies data blocks onto alternate media and assigns keys to identify the location of the migrated data using the File Transfer Protocol (FTP) to transfer to and from disks of another system on the network.

**FTP\_PASSWORD**

The file containing the password to use when migrating files to the remote system. This file must be owned by `root` and be only accessible by `root`. See "m<sub>sp</sub> Object Parameters for an FTP MSP" on page 455.

**FTP\_PORT**

The port number of the FTP server on the remote system. See "m<sub>sp</sub> Object Parameters for an FTP MSP" on page 455.

**FTP\_USER**

The user name to use when migrating files to the remote system. See "m<sub>sp</sub> Object Parameters for an FTP MSP" on page 455.

**FULL\_ZONE**

The parameter that limits when requests are flushed to a mounted volume that is not writing to a zone. See "volume<sub>group</sub> Object Parameters" on page 411.

**FULL\_THRESHOLD\_BYTES**

The parameter that determines whether or not the disk MSP will tell the DMF daemon when it is full. See "m<sub>sp</sub> Object Parameters for a Disk MSP" on page 467.

GET\_WAIT\_TIME

The parameter that limits the amount of time (in seconds) that DMF will continue writing to a volume after receiving a recall request for that volume. See "volumegroup Object Parameters" on page 411.

GROUP\_MEMBERS

The list of VGs and/or MSPs that will be a member of the migrate group. See "migrategroup Object Parameters" on page 427.

GUARANTEED\_DELETES

The number of child processes that are guaranteed to be available for processing delete requests. See:

- "msp Object Parameters for a Cloud MSP" on page 449
- "msp Object Parameters for a DCM MSP" on page 460
- "msp Object Parameters for a Disk MSP" on page 467
- "msp Object Parameters for an FTP MSP" on page 455

GUARANTEED\_GETS

The number of child processes that are guaranteed to be available for processing `dmget(1)` requests. See:

- "msp Object Parameters for a Cloud MSP" on page 449
- "msp Object Parameters for a DCM MSP" on page 460
- "msp Object Parameters for a Disk MSP" on page 467
- "msp Object Parameters for an FTP MSP" on page 455

**HA**

High availability

**HA resource**

A service, associated with an IP address, that is managed by SUSE Linux Enterprise High Availability Extension (HA). Also see *resource* for DMF Manager.



**HAE**

SUSE Linux Enterprise High Availability Extension.

**hard-delete**

The action of removing a soft-deleted database entry. See also *soft-deleted database entry*.

## HBA\_BANDWIDTH

(*OpenVault only*) The I/O bandwidth capacity of an HBA port that is connected to tape drives on a node. See:

- "base Object Parameters" on page 278
- "node Object Parameters" on page 294

## HFREE\_TIME

The minimum number of seconds that a tape no longer containing valid data must remain unused before the VG overwrites it. See "volumegroup Object Parameters" on page 411.

## HOME\_DIR

The base pathname for directories in which DMF databases and related files reside. See "base Object Parameters" on page 278.

## HTML\_REFRESH

The refresh rate (in seconds) of the generated HTML pages. See "resourcewatcher Object Parameters" on page 434.

**HTTPS**

Hypertext Transfer Protocol Secure

## IMMUTABLE\_BFIDS

Specifies whether or not DMF should restrict operations that change BFIDs of the migrated files in this filesystem. See "filesystem Object Parameters" on page 351.

IMPORT\_DELETE

A parameter that specifies whether the MSP should honor hard-delete requests from the DMF daemon. See:

- "m<sub>s</sub>p Object Parameters for a Disk MSP" on page 467
- "m<sub>s</sub>p Object Parameters for an FTP MSP" on page 455

IMPORT\_ONLY

A parameter that specifies whether the VG/MSP is used only for recalling files. See:

- "m<sub>s</sub>p Object Parameters for a Disk MSP" on page 467
- "m<sub>s</sub>p Object Parameters for an FTP MSP" on page 455
- "volumegroup Object Parameters" on page 411

**incomplete daemon-database entry**

An entry in the daemon database for an MSP or VG that has not finished copying the data, and therefore has not yet returned a key. The `path` field in the database entry is `NULL`.

**incompletely migrated file**

A file that has begun the migration process, but for which one or more copies on alternate media have not yet been made.

**inode**

The portion of a file that contains the bit-file identifier, the state field, and the data pointers.

**integrated backups**

*(integrated backups)* The backup method using `xfsdump` that copies backup data to a filesystem that is managed by DMF. See also *disk backups*, *tape backups*, *third-party backups*.

**integrated data-mover functionality**

The ability of the DMF server to move data. See also *parallel data-mover node*.

**INTERFACE**

The IP address or associated name of this node to be used for communication between DMF components. See "node Object Parameters" on page 294.

**IP**

Internet Protocol

**JOURNAL\_DIR**

The base pathname for directories in which the daemon database and LS journal files will be written. See "base Object Parameters" on page 278.

**JOURNAL\_RETENTION**

The length of time to keep journals. See "taskgroup Object Parameters" on page 312.

**JOURNAL\_SIZE**

The maximum size (in bytes) of the database journal file before DMF closes it and starts a new file. See "base Object Parameters" on page 278.

**KILL\_WC\_IF\_DEMAND**

The parameter that specifies whether or not an idle write child will be terminated immediately if there is demand for the drive.

**LABEL\_TYPE**

The label type used when writing volumes from the beginning. See "drivegroup Object Parameters" on page 397.

**LCP**

Library control program

**library server**

(LS) A daemon-like process by which data blocks are copied onto secondary storage and that maintains the location of the migrated data. Each LS has an associated LS database with catalog (CAT) and volume (VOL) records. An LS can be configured to contain one or more DGs.

`libraryserver` **object**

The configuration object that defines parameters relating to a tape library for an LS. See "libraryserver Object Parameters" on page 393.

`LICENSE_FILE`

The full pathname of the file containing the license used by DMF. See "base Object Parameters" on page 278.

`LOG_RETENTION`

Specifies the age of files that will be kept when the `run_remove_logs.sh` task is run. See "taskgroup Object Parameters" on page 312.

**logical block protection**

A mechanism provided by tape drive manufactures to provide a checksum for data validation at the end of each tape block (also known as *data integrity validation*).

`LOGICAL_BLOCK_PROTECTION`

Specifies whether *logical block protection* should be turned on when reading and writing tapes. See "volume group Object Parameters" on page 411.

**LS**

See *library server*.

**LS database**

The database containing catalog (CAT) and volume (VOL) records associated with a library server (LS). See also *CAT record* and *VOL record*.

`LS_NAMES`

The library servers used by the DMF daemon. See "dmdaemon Object Parameters" on page 290.

`LTFS_CART_GROUP`

Specifies the single OpenVault cartridge group to be reserved for use by LTFS. The default is `ltfs_carts`. See "sgi-ltfs.conf Parameters" on page 634.

**LTFS\_DRIVE\_GROUP**

Specifies the single OpenVault drive group to be reserved for use by LTFS. See "sgi-ltfs.conf Parameters" on page 634.

**LTFS\_MAX\_DRIVES**

Specifies the maximum number of drives that can be in the drive group specified by `LTFS_DRIVE_GROUP` at any given time. See "sgi-ltfs.conf Parameters" on page 634.

**LTFS\_MOUNT\_ROOT**

Specifies the path that will be added to the tape name to form the mount point of the LTFS filesystem. See "sgi-ltfs.conf Parameters" on page 634.

**LTFS\_OV\_KEYFILE**

Specifies the path to the keyfile used by LTFS when connecting to the OpenVault server. See "sgi-ltfs.conf Parameters" on page 634.

**MAID**

Massive array of idle disks.

**managed filesystem**

A DMAPAPI-mounted XFS or CXFS filesystem, configured in a `filesystem` object in the DMF configuration file, on which DMF can migrate or recall files. (When using Parallel DMF, it must be CXFS.) See *Parallel Data-Mover Option*.

**MAX\_ALERTDB\_SIZE**

Specifies the maximum size of the alerts database. See "taskgroup Object Parameters" on page 312.

**MAX\_CACHE\_FILE**

The largest chunk (in bytes) that will be merged using the merge disk cache. See "libraryserver Object Parameters" on page 393.

MAX\_CHUNK\_SIZE

The size (in bytes) of the chunk into which the VG should break up large files as it writes data to secondary storage. See "volumegroup Object Parameters" on page 411.

MAX\_IDLE\_PUT\_CHILDREN

The maximum number of idle write child (dmatwc) processes that will be allowed simultaneously for a VG. See "volumegroup Object Parameters" on page 411.

MAX\_DRIVES\_PER\_NODE

(This parameter has been deprecated and will be ignored.)

MAX\_MANAGED\_REGIONS

The maximum number of managed regions that DMF will assign to a file on a per-filesystem basis. You can set MAX\_MANAGED\_REGIONS to any number that is less than the actual number of regions that will fit in a filesystem attribute. See "filesystem Object Parameters" on page 351.

MAX\_MS\_RESTARTS

The maximum number of times DMF can attempt to restart the mounting service (TMF or OpenVault) without requiring administrator intervention. See "drivegroup Object Parameters" on page 397.

MAX\_PERFDB\_SIZE

Specifies the maximum size of the performance records database. See "taskgroup Object Parameters" on page 312.

MAX\_PUT\_CHILDREN

The maximum number of write child (dmatwc) processes that will be scheduled simultaneously for the DG or an individual VG. See:

- "drivegroup Object Parameters" on page 397
- "volumegroup Object Parameters" on page 411

**media-specific process**

(MSP) The daemon-like process by which data blocks are copied onto alternate media and that assigns keys to identify the location of the migrated data.

**MERGE\_CUTOFF**

A limit at which the VG will stop scheduling tapes for merging. See "volumegroup Object Parameters" on page 411.

**MERGE\_INTERFACE**

The IP address or associated name on this node to be used when merging sparse volumes via sockets. See "node Object Parameters" on page 294.

**MERGE\_THRESHOLD**

The integer percentage of active data on a volume less than which DMF will consider a volume to be sparse and allow merging. See "volumegroup Object Parameters" on page 411.

**merging**

See *volume merging*.

MESSAGE\_LEVEL

The highest message level that will be written to a log file (the higher the number, the more messages written). See:

- "dmdaemon Object Parameters" on page 290
- "filesystem Object Parameters" on page 351
- "libraryserver Object Parameters" on page 393
- "msp Object Parameters for a Cloud MSP" on page 449
- "msp Object Parameters for a DCM MSP" on page 460
- "msp Object Parameters for a Disk MSP" on page 467
- "msp Object Parameters for an FTP MSP" on page 455
- "services Object Parameters" on page 300
- Chapter 10, "Message Log Files" on page 507

**metadata**

Information that describes a file, such as the file's name, size, location, and permissions.

**metadata server**

The CXFS server-capable administration node that coordinates updating of metadata on behalf of all nodes in a cluster. There can be multiple potential metadata servers, but only one is chosen to be the active metadata server for any one filesystem.

METRICS\_RETENTION

Specifies the retention time for the DMF cumulative (totals and averages) metrics. See "base Object Parameters" on page 278.

**migrated file**

A file that has one or more complete offline copies and no pending or incomplete offline copies.



**migrate group**

A logical collection of VGs or MSPs that you combine into a set in order to have a single destination for a migrate request. See `migrategroup`.

`migrategroup`

The configuration object that combines a set of VGs and MSPs so that they can be used as a single destination for a migrate request. See "migrategroup Object Parameters" on page 427.

**migrating file**

A file that has a bit-file identifier but whose offline copies are in progress.

`MIGRATION_LEVEL`

The highest level of migration service allowed. See:

- "dmdaemon Object Parameters" on page 290
- "filesystem Object Parameters" on page 351
- "msp Object Parameters for a DCM MSP" on page 460
- "msp Object Parameters for a Disk MSP" on page 467

`MIGRATION_TARGET`

The integer percentage of total filesystem space that `dmfsmon` tries to maintain as a reserve of space that is free or occupied by dual-state files (whose online space can be freed quickly) if free space reaches or falls below `FREE_SPACE_MINIMUM`. See "Automated Space-Management Parameters for a Managed Filesystem" on page 369.

`MIN_ARCHIVE_SIZE`

Determines whether direct or buffered I/O is used when reading from this filesystem. See "filesystem Object Parameters" on page 351.

MIN\_DIRECT\_SIZE

Determines whether direct or buffered I/O is used when reading from this filesystem. See:

- "filesystem Object Parameters" on page 351
- "msp Object Parameters for a DCM MSP" on page 460
- `open(2)` man page for a description of direct I/O

MIN\_VOLUMES

The minimum number of unused volumes that can exist in the LS database for this VG without operator notification. See "volume group Object Parameters" on page 411.

**monitored filesystem**

A filesystem configured in the DMF configuration file such that DMF will monitor its fullness and run user-specified tasks, but for which it will not migrate or recall data.

MOUNT\_BLOCKED\_TIMEOUT

The maximum number of minutes to wait for a volume to be mounted when another process is using the drive. See "drivegroup Object Parameters" on page 397.

MOUNT\_SERVICE

The mounting service. See:

- "device Object Parameters" on page 348
- "drivegroup Object Parameters" on page 397

MOUNT\_SERVICE\_GROUP

The name by which the object's devices are known to the mounting service. See:

- "device Object Parameters" on page 348
- "drivegroup Object Parameters" on page 397

MOUNT\_TIMEOUT

The maximum number of minutes to wait for a volume to be mounted. See "drivegroup Object Parameters" on page 397.

**MOVE\_FS**

One or more scratch filesystems used by `dmmove(8)` to move files between MSPs or VGs. See "dmdaemon Object Parameters" on page 290.

**MSG\_DELAY**

The number of seconds that all drives in the DG can be down before DMF sends an e-mail message to the administrator and logs an error message. See "drivegroup Object Parameters" on page 397

**MSP**

The media-specific process (MSP), a daemon-like process by which data blocks are copied onto alternate media and that assigns keys to identify the location of the migrated data. See also: *cloud MSP*, *disk MSP*, *DCM MSP*, *FTP MSP*, and *non-cache MSP*.

**MSP database entry**

The daemon database entry for a file that contains the path or key that is used to inform a particular media-specific process (MSP) where to locate the copy of the file's data.

**MSP\_NAMES**

Names the media-specific processes (MSPs) used by the DMF daemon. See "dmdaemon Object Parameters" on page 290.

**m<sub>sp</sub> object**

The configuration object that defines parameters necessary for the operation of a media-specific process. There is one `msp` object for each MSP. See:

- "m<sub>sp</sub> Object Parameters for a DCM MSP" on page 460
- "m<sub>sp</sub> Object Parameters for a Disk MSP" on page 467
- "fastmountcache Object Parameters" on page 390

**MULTIPLIER**

The amount of data to be sent to a group member relative to the other members listed in `GROUP_MEMBERS` when using the `ROUND_ROBIN_BY_BYTES` or

`ROUND_ROBIN_BY_FILES` for `ROTATION_STRATEGY`. See "migrategroup Object Parameters" on page 427.

`MULTITAPE_NODES`

*(Parallel DMF and OpenVault only)*. The parameter that restricts the recall of a file that involves multiple tapes to one of the specified mover nodes. See "drivegroup Object Parameters" on page 397.

`MVS_UNIT`

The storage device type on an MVS system. See "msp Object Parameters for an FTP MSP" on page 455.

`NAME_FORMAT`

The substitution strings that form a template for filenames used in secondary storage. See:

- "msp Object Parameters for a Cloud MSP" on page 449
- "msp Object Parameters for a DCM MSP" on page 460
- "msp Object Parameters for a Disk MSP" on page 467
- "msp Object Parameters for an FTP MSP" on page 455

**near-line storage**

Storage in which tapes are mounted by robot.

**NFS**

Network File System

`NODE_ANNOUNCE_RATE`

The rate in seconds at which a node will contact the `dmnode_service` on the DMF server to announce its presence. See "services Object Parameters" on page 300.

**NODE\_BANDWIDTH**

(*OpenVault only*) The I/O bandwidth capacity of the node. See:

- "base Object Parameters" on page 278
- "node Object Parameters" on page 294

**NODE\_TIMEOUT**

The number of seconds after which the data mover functionality on the DMF server or on a parallel data-mover node will be considered inactive if it has not contacted the `dmnode_service` on the DMF server. See "services Object Parameters" on page 300.

**non-cache MSP**

Cloud MSP, disk MSP, or FTP MSP.

**nonintegrated backups**

Traditional backup methods using disk or tape that were in place prior to the introduction of the integrated-backup method. See also *integrated backups*

**nonmigrated file**

A file that does not have a bit-file identifier or any offline copies. See *regular file*.

**offline file**

A file whose inode contains a bit-file identifier but whose disk blocks have been removed. The file's data exists elsewhere in copies on alternate media.

**offline pointer**

In MSP and VG processing, a character string that the MSP or VG returns to the daemon to indicate how a file is to be retrieved.

**OpenVault**

A storage library management facility that improves how applications can manage, store, and retrieve removable media.

**OpenVault drive group**

A group of interchangeable devices. See also DMF *drive group*.

**orphan chunk**

An unused area in an LS catalog (CAT) database entry resulting from the removal of migrated files.

**orphan database entry**

An unused daemon database entry resulting from the removal of a migrated file during a period in which the DMF daemon is not running.

OV\_ACCESS\_MODES

*(OpenVault only)* The OpenVault access mode. See:

- "device Object Parameters" on page 348
- "drivegroup Object Parameters" on page 397

OV\_INTERCHANGE\_MODES

*(OpenVault only)* A list of interchange mode names that control how data is written to secondary storage. See:

- "device Object Parameters" on page 348
- "drivegroup Object Parameters" on page 397

OV\_KEY\_FILE

*(OpenVault only)* The file containing the OpenVault keys used by DMF. See "base Object Parameters" on page 278.

OV\_SERVER

*(OpenVault only)* Specifies the name associated with the IP address on which the OpenVault server is listening. See:

- "base Object Parameters" on page 278
- "sgi-ltfs.conf Parameters" on page 634

**oversubscribe**

A ratio of offline space to the total amount of space for a given DMF filesystem (including space that is free, space that is occupied by regular files, space that is occupied by files that are migrated, including dual-state files).

**parallel data-mover node**

A node, installed with DMF data mover software and underlying CXFS client-only software, that provides dedicated data mover functionality in addition to the DMF server, increasing data throughput and enhancing resiliency.

**parallel data-mover node license**

A DMF license installed on the DMF server that permits one parallel data-mover node to be active when using Parallel DMF. There can be multiple licenses installed, one for each parallel data-mover node that is active at any one time. See also *parallel data-mover node* and *Parallel Data-Mover Option*.

**Parallel Data-Mover Option**

Optional software and licenses available for purchase that allow you to run parallel data-mover nodes in order to increase data throughput and enhance resiliency.

**Parallel DMF**

DMF using the Parallel Data-Mover Option. See *Parallel Data-Mover Option*.

**parameter**

See *configuration parameter*.

**partial-state file**

A file that has more than one region. DMF allows a file to include up to four distinct file regions. See also *region*.

**partial-state file online retention**

A partial-state file feature capability that allows you to keep a specific region of a file online while freeing the rest of it (for example, if you wanted to keep just the beginning of a file online). See also *partial-state file*.

**partial-state file recall**

A partial-state file feature capability that allows you to recall a specific region of a file without recalling the entire file. For more information, see the `dmput(1)` and `dmget(1)` man pages. See also *partial-state file*.

PARTIAL\_STATE\_FILES

Enables or disables the DMF daemon's ability to produce partial-state files. See "dmdaemon Object Parameters" on page 290.

PENALTY

A parameter used to reduce the priority of requests from a VG that is not the next one preferred by the round-robin algorithm. See "resourcescheduler Object Parameters" on page 432.

PERF\_RETENTION

The length of time to keep performance records. See "taskgroup Object Parameters" on page 312.

PERFTRACE\_METRICS

Enables or disables collection of performance tracking information from DMF. See "base Object Parameters" on page 278.

**persistent drive reservation**

The locking of a given drive to a given path until the lock is dropped, which helps protect against data loss due to rewind or write requests from other paths.

POLICIES

The names of the configuration objects defining policies for this filesystem. See:

- "filesystem Object Parameters" on page 351
- "msp Object Parameters for a DCM MSP" on page 460

**policy**

Rules that tell DMF how to determine MSP or VG selection, automated space-management policies, and/or file weight calculations.



**policy object**

The configuration object that specifies parameters to determine MSP or VG selection, automated space management policies, and/or file weight calculations in automated space management. See "policy Object" on page 364.

## POSITIONING

How the volume should be positioned. See "drivegroup Object Parameters" on page 397.

## POSITION\_RETRY

The level of retry in the event of a failure during zone positioning. See "drivegroup Object Parameters" on page 397.

## POSIX\_FADVISE\_SIZE

Specifies the number of bytes after which DMF will call `posix_fadvise()` with advice `POSIX_FADV_DONTNEED` when recalling files. See "filesystem Object Parameters" on page 351.

## PRIORITY\_PERIOD

Specifies the number of minutes after which a migrating file gets special treatment. See "msp Object Parameters for a DCM MSP" on page 460.

**primary filesystem**

See *managed filesystem*.

## PUT\_IDLE\_DELAY

The number of seconds that an idle `dmatwc` (write child) process will be allowed to stay alive. See "volumegroup Object Parameters" on page 411.

## PUTS\_TIME

The minimum number of seconds a VG waits after it has requested a drive for a write child before it tells a lower priority child to go away. See "volumegroup Object Parameters" on page 411.

**RAID**

Redundant array of independent disks.

**raw time**

The time in seconds since January 1, 1970.

**read child**

A data-mover process that recalls data from tape.

**READ\_ERR\_MAXIMUM**

The maximum number of I/O errors that will be tolerated when recalling a file. See "drivegroup Object Parameters" on page 397.

**READ\_ERR\_MINIMUM**

The minimum number of I/O errors that will be tolerated when recalling a file. See "drivegroup Object Parameters" on page 397.

**READ\_ERR\_TIMEOUT**

The elapsed number of seconds since the first I/O error was seen. See "drivegroup Object Parameters" on page 397.

**READ\_IDLE\_DELAY**

The number of seconds an idle read child (`dmatrix`) can wait before being told to exit. See:

- "drivegroup Object Parameters" on page 397
- "volumegroup Object Parameters" on page 411

**READ\_TIME**

The interval, in seconds, after which the VG will evaluate whether a read child should be asked to go away (even if it is in the middle of recalling a file) so that a higher priority child can be started. See "volumegroup Object Parameters" on page 411.

**recall a file**

To request that a migrated file's data be moved back (unmigrated) onto the filesystem disk, either by explicitly entering the `dmget(1)` command or by executing another command that will open the file, such as the `vi(1)` command.

**RECALL\_NOTIFICATION\_RATE**

The approximate rate, in seconds, at which regions of a file being recalled are put online. This allows for access to part of a file before the entire file is recalled. See "dmdaemon Object Parameters" on page 290.

**REDIRECT\_TIME\_DG\_DOWN**

Specifies the number of seconds that DMF will wait before redirecting recalls; after all drives have been down for *REDIRECT\_TIME\_DG\_DOWN* seconds, DMF will start forwarding every recall to the VG that holds the secondary copy. See "drivegroup Object Parameters" on page 397.

**region**

A contiguous range of bytes that have the same residency state. The range state can be migrating (MIG), dual-state (DUL), offline (OFL), or unmigrating (UNM).

**regular file**

A file with no bit-file identifier and no offline copies.

**REINSTATE\_DRIVE\_DELAY**

The number of minutes after which a drive that was configured down by the DG will be automatically reinstated and made available for use again. See "drivegroup Object Parameters" on page 397.

**REINSTATE\_VOLUME\_DELAY**

The number of minutes after which a volume that had its `HLOCK` flag set by DMF will be automatically reinstated and made available for use again. See "drivegroup Object Parameters" on page 397.

RELEASETHREADS

The number of threads in the DMF daemon that will be created to handle requests to release filesystem blocks when files are made offline (OFL). See "filesystem Object Parameters" on page 351.

REMALEERT\_PARAMS

Parameters to be executed by `run_remove_alerts.sh`. See "taskgroup Object Parameters" on page 312.

REMPERF\_PARAMS

Parameters to be executed by `run_remove_perf.sh`. See "taskgroup Object Parameters" on page 312.

RESERVED\_VOLUMES

Defines the number of volumes that the VG will reserve for volume merging or that will trigger selection of another volume within a migrate group. See "volume group Object Parameters" on page 411.

**resource**

A *resource* is a filesystem or hardware component used by DMF. Also see *HA resource*

**resource group**

A service, associated with an IP address, that is managed by SUSE Linux Enterprise High Availability Extension.

`resourcescheduler` **object**

The configuration object that defines parameters relating to scheduling of devices in a DG when requests from VGs exceed the number of devices available. See "resourcewatcher Object Parameters" on page 434.

`resourcewatcher` **object**

The configuration object that defines parameters relating to the production of files informing the administrator about the status of the LS and its components. See "resourcewatcher Object Parameters" on page 434.

**REST**

Representational state transfer

**REWIND\_DELAY**

The number of seconds that an idle read child (`dmatrc`) can wait before rewinding.  
See:

- "drivegroup Object Parameters" on page 397
- "volume group Object Parameters" on page 411

**ROTATION\_STRATEGY**

The method in which migration requests will rotate through the VGs and MSPs that are members of this group. See "migrategroup Object Parameters" on page 427.

**ROUND\_ROBIN\_BY\_BYTES**

The `ROTATION_STRATEGY` value specifying that a certain number of bytes (defined by `MULTIPLIER`) are sent to each VG/MSP member specified in `GROUP_MEMBERS`. See "migrategroup Object Parameters" on page 427.

**ROUND\_ROBIN\_BY\_FILES**

The `ROTATION_STRATEGY` value specifying that a certain number of files (defined by `MULTIPLIER`) are sent to each VG/MSP member specified in `GROUP_MEMBERS`. See "migrategroup Object Parameters" on page 427.

**RRR**

S3 Reduced Redundancy Storage

RUN\_TASK

A DMF maintenance command to be executed. See:

- "Automated Maintenance Tasks" on page 175
- "drivegroup Object Parameters" on page 397
- "libraryserver Object Parameters" on page 393
- "taskgroup Object Parameters" on page 312
- "volumegroup Object Parameters" on page 411

SCAN\_FILESYSTEMS

The parameter that specifies for the `run_filesystem_scan.sh` script the filesystems that `dmscanfs` will scan. See "taskgroup Object Parameters" on page 312.

SCAN\_FOR\_DMSTAT

The parameter that specifies for the `run_filesystem_scan.sh` script whether additional output files (`bfiid2path` and/or `fhandle2bfiid+path`) are created, also depending upon the setting for `SCAN_PARAMS`. See "taskgroup Object Parameters" on page 312.

SCAN\_OUTPUT

The parameter that specifies for the `run_filesystem_scan.sh` script the name of the file into which `dmscanfs` will place output. See "taskgroup Object Parameters" on page 312.

SCAN\_PARALLEL

The parameter that specifies for the `run_filesystem_scan.sh` script whether `dmscanfs` will scan filesystems in parallel. See "taskgroup Object Parameters" on page 312.

SCAN\_PARAMS

The parameter that specifies additional `dmscanfs` parameters for the `run_filesystem_scan.sh` task. See "taskgroup Object Parameters" on page 312.

**secondary storage**

The offline media onto which file data is migrated. See also *managed filesystem*.

**SELECT\_LOWER\_VG**

Defines which VGs should maintain secondary-storage copies of files in the cache, and under what conditions that would define dual-residence. (It is not used for defining which VG to use for recalls; for that, see the definitions of the `LS_NAMES`, `MSP_NAMES`, `DRIVE_GROUPS`, and `VOLUME_GROUPS` parameters.) See "VG Selection Parameters for a DCM MSP `STORE_DIRECTORY`" on page 380.

**SELECT\_MSP**

The media-specific processes (MSPs) to use for migrating a file. See "MSP/VG Selection Parameters for a Managed Filesystem" on page 374.

**SELECT\_VG**

The volume groups (VGs) to use for migrating a file. See "MSP/VG Selection Parameters for a Managed Filesystem" on page 374.

**SEQUENTIAL**

The `ROTATION_STRATEGY` value specifying that each COPAN shelf will be filled before advancing to the next shelf.

**server capability license**

The DMF license that permits DMF migrations to exceed 1 TB when installed in conjunction with one or more DMF data capacity licenses. See also *data capacity licenses*.

**SERVER\_NAME**

Hostname of the machine on which the DMF server is running (used for HA configurations or configurations using Parallel DMF). See "base Object Parameters" on page 278.

**SERVICES**

The name of the `services` object used to configure DMF services on a node when using Parallel DMF. See "node Object Parameters" on page 294.

`SERVICES_PORT`

The port number on which DMF starts a locator service, which DMF uses to locate other DMF services. See "services Object Parameters" on page 300.

**site-defined policy**

A site-specific library of C++ functions that DMF will consult when making decisions about its operation.

`SITE_SCRIPT`

The site-specific script to execute when `dmfsfree`, `dmdskfree`, or `dmfsmon` is run. See:

- "Automated Space-Management Parameters for a DCM MSP `STORE_DIRECTORY`" on page 376
- "Automated Space-Management Parameters for a Managed Filesystem" on page 369
- "`mSP` Object Parameters for a DCM MSP" on page 460

**SMB**

Server Message Block

**snapshot**

The information about all bit-file identifier sets that is collected and analyzed by `dmaudit(8)`. The snapshot analysis is available from the `report` function.

**soft-delete**

The action of adding a time stamp to the `delete` field of a daemon database entry. See also *active database entry* and *soft-deleted database entry*.

**soft-deleted database entry**

A daemon database entry whose `BFID` points to a file that is no longer present in the managed filesystem (because it has been modified or removed) but might still reside on backup media. See also *active database entry*, *BFID*, and *soft-delete*.



**SPACE\_WEIGHT**

The floating-point constant and floating-point multiplier to use to calculate the weight given to a file's size (for MSP/VG managed filesystem). See "File Weighting Parameters for a Managed Filesystem" on page 371.

**sparse volume**

A volume containing only a small amount of active information.

**special file**

A device file in UNIX or Linux. (DMF never migrates special files.)

**SPOOL\_DIR**

The base pathname for directories in which DMF log files are kept. See "base Object Parameters" on page 278.

**SSL**

Secure Sockets Layer

**standby metadata server node**

A CXFS server-capable administration node that is configured as a potential metadata server for a given filesystem, but does not currently run any applications that will use that filesystem.

**state field**

The field in the inode that shows the current migration state of a file.

**STORE\_DIRECTORY**

The directory used to hold files for a DCM or disk MSP. See:

- "msp Object Parameters for a DCM MSP" on page 460
- "msp Object Parameters for a Disk MSP" on page 467

**tape backups**

Traditional (nonintegrated) backups to tape using `xfsdump`. See also *disk backups* and *integrated backups*.

**tape block**

See *block*.

**tape drive**

See *drive*.

**tape chunk**

See *chunk*.

**tape merging**

See *volume merging*.

**task**

A process initiated by the DMF event mechanism. Configuration tasks that allow certain recurring administrative duties to be automated are defined with configuration parameters.

`taskgroup`

A configuration object that defines parameters necessary for the automatic completion of specific maintenance tasks. See "dmdaemon Object Parameters" on page 290.

**TASK\_GROUPS**

The objects containing tasks that the daemon or LS should run. See:

- "dmdaemon Object Parameters" on page 290
- "drivegroup Object Parameters" on page 397
- "filesystem Object Parameters" on page 351
- "libraryserver Object Parameters" on page 393
- "msp Object Parameters for a Cloud MSP" on page 449
- "msp Object Parameters for a DCM MSP" on page 460
- "msp Object Parameters for a Disk MSP" on page 467
- "msp Object Parameters for an FTP MSP" on page 455
- "services Object Parameters" on page 300
- "taskgroup Object Parameters" on page 312
- "volumegroup Object Parameters" on page 411

**third-party backups**

Backups scheduled through a third-party application, rather than `xfsdump`. See also *disk backups*, *integrated backups*, and *tape backups*.

**THRESHOLD**

The percentage of active data on a volume. DMF will consider a volume to be sparse when it has less than this percentage of data that is still active. See "taskgroup Object Parameters" on page 312.

**TIMEOUT\_FLUSH**

The number of minutes after which the VG will flush files to tape. See "volumegroup Object Parameters" on page 411.

TMF\_TMMNT\_OPTIONS

Command options that should be added to the `tmmnt` command when mounting a tape. See:

- "device Object Parameters" on page 348
- "drivegroup Object Parameters" on page 397

TMP\_DIR

The base pathname for DMF directories in which DMF puts temporary files such as pipes. See "base Object Parameters" on page 278.

TSREPORT\_OPTIONS

Additional options that the `run_daily_tsreport.sh` script will add to the end of the `tsreport` command line. See "taskgroup Object Parameters" on page 312.

**TYPE**

The required name for the object. See:

- "allocationgroup Object Parameters" on page 435
- "base Object Parameters" on page 278
- "device Object Parameters" on page 348
- "dmdaemon Object Parameters" on page 290
- "drivegroup Object Parameters" on page 397
- "dumpgroup Object Parameters" on page 343
- "fastmountcache Object Parameters" on page 390
- "filesystem Object Parameters" on page 351
- "libraryserver Object Parameters" on page 393
- "migrategroup Object Parameters" on page 427
- "msp Object Parameters for a Cloud MSP" on page 449
- "msp Object Parameters for a DCM MSP" on page 460
- "msp Object Parameters for a Disk MSP" on page 467
- "msp Object Parameters for an FTP MSP" on page 455
- "node Object Parameters" on page 294
- "policy Object" on page 364
- "resourcescheduler Object Parameters" on page 432
- "resourcewatcher Object Parameters" on page 434
- "services Object Parameters" on page 300
- "taskgroup Object Parameters" on page 312
- "volumegroup Object Parameters" on page 411

**unmigratable file**

A file that the daemon will never select as a migration candidate.

**unmanaged archive filesystem**

See *archive filesystem*.

**unmigrate**

See *recall*.

UPDATE\_CTIME

The parameter that specifies whether or not the `st_ctime` value of files in this filesystem should be changed when certain operations are performed. See "filesystem Object Parameters" on page 351.

USE\_AS\_DUMP\_DEST

Determines if this filesystem can be used for storing integrated-backup dumps. See "filesystem Object Parameters" on page 351/

USE\_UNIFIED\_BUFFER

Determines how DMF manages its buffers when recalling files on this filesystem. See "filesystem Object Parameters" on page 351.

VALID\_ROOT\_HOSTS

Hosts where the `root` user can perform certain functions similar to the `root` user on the DMF server. See "base Object Parameters" on page 278.

VERIFY\_POSITION

A parameter that specifies whether the LS write child should (prior to writing) verify that the volume is correctly positioned and that the volume was properly terminated by the last use. See "drivegroup Object Parameters" on page 397.

**VG**

See *volume group*.

**VG database entry**

The daemon database entry for a file that contains the path or key that is used to inform a particular VG where to locate the copy of the file's data.

**VOL\_MSG\_TIME**

Specifies, in seconds, the minimum interval between operator notifications for low-volume and no-volume conditions. See:

- "allocationgroup Object Parameters" on page 435
- "volumegroup Object Parameters" on page 411

**volume**

In DMF, a logical area of physical tape, virtual tape, or disk such as COPAN MAID that is used for migrating data.

**volume group**

A volume group is a component of an LS that is responsible for managing pool of volumes capable of storing single copies of files. Multiple copies of the same files require the use of multiple VGs. See also *LS*.

**VOLUME\_GROUPS**

The VGs containing volumes that can be mounted on any of the drives within this DG. See "drivegroup Object Parameters" on page 397.

**voided BFID-set state**

A BFID set state that consists of one or more soft-deleted daemon database entries, either incomplete or complete. There is no file. See also *bit-file identifier* and *soft-deleted database entry*.

**voiding the BFID**

The process of removing the BFID from the file inode and soft-deleting all associated database entries. See also *bit-file identifier* and *soft-deleted database entry*.

**VOL record**

An entry in the volume (VOL) table of the LS database that contains information about a volume. There is one VOL record for each volume. See also *CAT record*, *VOL table*.

**VOL table**

A table in the LS database that contains VOL records. See also *CAT table*, *VOL record*.

volumegroup

The configuration object that defines parameters relating to a pool of volumes mountable on the drives of a specific DG that are capable of holding, at most, one copy of files. See "volumegroup Object Parameters" on page 411.

**volume-based media**

Physical tape, COPAN MAID, or COPAN VTL

VOLUME\_LIMIT

The maximum number of volumes that can be selected for merging at one time. See "taskgroup Object Parameters" on page 312.

**volume merging**

The mechanism provided by the LS for copying active data from volumes that contain largely obsolete data to volumes that contain mostly active data.

**volume serial number**

A label that uniquely identifies a specific volume.

**VSN**

See *volume serial number*

**VTL**

Virtual tape library.

WATCHER

The resource watcher that the LS should run. See "libraryserver Object Parameters" on page 393.

WEIGHT

The parameter that assigns a weighting to one or more VGs. See "resourcescheduler Object Parameters" on page 432.



**WRITE\_CHECKSUM**

The parameter that specifies that a block should be checksummed before writing. See:

- "drivegroup Object Parameters" on page 397
- "msp Object Parameters for a Cloud MSP" on page 449
- "msp Object Parameters for a DCM MSP" on page 460
- "msp Object Parameters for a Disk MSP" on page 467
- "msp Object Parameters for an FTP MSP" on page 455

**write child**

A data-mover process that migrates data to secondary storage.

**zone**

A logical grouping of chunks. Zones are separated by file marks. The target size of a zone is configurable by media type.

**ZONE\_SIZE**

The parameter that specifies about how much data the write child should put in a zone. See "volumegroup Object Parameters" on page 411.



---

## Index

- ??                      ??
- 1PB+ license, 68  
8-character barcodes, 119  
10TB+ license, 68  
100TB+ license, 68  
256b-byte inodes, 104
- A**
- About panel in DMF Manager, 194  
absolute block positioning, 42  
accelerated access to first byte, 6  
active parallel data-mover node, 74  
Activity panel in DMF Manager, 193  
ADMDIR\_IN\_ROOTFS, 102, 279  
Admin Guide panel in DMF Manager, 194  
Admin mode functionality, 196  
admin state and fencing, 178  
ADMIN\_EMAIL, 280  
\$ADMINDIR, 329  
administrative directories, 44  
administrative directory permission requirements, 45  
administrative tasks  
    automated maintenance tasks, 175  
    best practices, 123  
    daemon configuration, 304  
    filesystem backups, 54, 309  
    maintenance and recovery, 585  
    overview, 52, 53  
    tape management, 443
- age expression, 381  
AGE\_WEIGHT, 147, 372, 381, 383, 510, 750  
AGGRESSIVE\_HVIFY, 397  
alert records  
    remove, 306  
ALERT\_RETENTION, 118, 312  
alerts database size, 117  
Alerts panel in DMF Manager, 193, 222  
ALGORITHM, 433  
allocation group, 41  
ALLOCATION\_GROUP, 411, 423  
ALLOCATION\_MAXIMUM, 412  
ALLOCATION\_MINIMUM, 412  
allocationgroup  
    allocationgroup object overview, 274  
Amazon S3  
    See "cloud MSP", 569  
AMPEX DIS/DST, 276  
API commands, 130  
application support, 8  
architecture, 38  
architecture requirements, 48  
archive file requests, 712  
archive filesystem and archiving, 119  
archives for DMF Manager monitoring, 130  
archiving, 5  
    overview, 13  
    See "DMF direct archiving", 119  
archiving files, 15  
ASG-Time Navigator, 769  
attr, 171  
attr2, 171  
autolog file, 507  
autolog log file, 513  
automated maintenance tasks  
    daemon configuration, 304

- overview, 175
- automated space management
  - administration duties, 53
  - candidate list generation, 510
  - commands overview, 62
  - file exclusion, 510
  - log, 507
  - log file, 513
  - parameters, 369, 376
  - relationship of targets, 512
  - selection of migration candidates, 511
- automated space management procedure, 385
- automatic monitoring, 2
- automatic start after reboot, 182
- automounters, 42
- averages, 242
- aware backup packages, 767

## B

- backup package configuration, 767
- backup packages, 767
- backups
  - consistent completion times, 147
  - COPAN MAID reserved space, 145
  - databases, 137
  - DMF configuration file, 102
  - dump scripts, 141
  - filesystems, 137
  - incremental, 148
  - integrated-backup method, 149
  - migrate files first, 146
  - of daemon database, 339
  - optimizing, 145
  - other methods, 161
  - physical tapes, 144
  - requirement for, 141
  - run\_full\_dump.sh, 142
  - run\_partial\_dump.sh, 143
  - SGI 400 VTL tapes, 144

- site-specific factors, 144
- VTL tapes, 144
- balance data among libraries, 139
- bandwidth and socket merges, 128
- BANDWIDTH\_MULTIPLIER, 398
- barcodes, 119
- base data-capacity license, 67
- base metrics, 242
- base object
  - icon in DMF Manager, 213
  - overview, 272
  - parameters, 278
- basic DMF, 33
- basic DMF product, 33
- best practices
  - administrative, 123
  - configuration, 87
  - installation, upgrade, and downgrade, 81
  - LTFS, 632
- bfid, 524
- bit-file identifier (BFID), 38
- black clock symbol, 669
- BLOCK\_SIZE, 398
- blocks, 534
- blocksize, 679
- blocksize keyword, 558
- BOF/bof, 383
- borrow a DMF drive for LTFS use, 631
- BORROW\_FROM\_DG, 634
- bottlenecks, 134
- BUFFERED\_IO\_SIZE, 352, 461
- burst\_size, 134
- byte range requests and partial-state files, 780

## C

- CACHE\_AGE\_WEIGHT, 378, 381
- CACHE\_DIR, 46, 102, 163, 393, 486
- CACHE\_MEMBERS, 391
- CACHE\_SPACE, 106, 394

- CACHE\_SPACE\_WEIGHT, 379, 381
- CANCEL message
  - FTP MSP, 576
- canceling a request, 613
- cancelling changes, 219
- candidate list
  - creation, 509
  - generation, 510
  - terminology, 53
- capability license, 67
- capacity
  - determination, 72
  - DMF software, 42
  - license, 67
  - overhead and, 42
- case study on zone size, 781
- CAT records
  - backup, 646
  - definition, 37
  - dmats database and, 532
  - messages, 677
  - records and LS database directories, 536
- cflags, 548
- change notification suppression, 133
- chattr, 140
- checkage, 520
- CHECKSUM\_TYPE, 412
- checktime, 521, 524
- child-process constraints, 122
- CHILD\_MAXIMUM, 122, 449, 456, 461, 468
- chkconfig, 165, 181–183
- chkconfig for dmfsop, 601
- chunk table, 622, 624
- chunkdata, 548
- chunklength, 548
- chunknumber, 548
- chunkoffset, 548
- chunkpos, 548
- chunks, 534
- chunksleft, 679
- chunksleft keyword, 558
- CIFS, 9
- client port specification, 188
- clients
  - commands, 57
  - installation, 168
  - OS supported, 12
- cloud MSP
  - log files, 571
  - msp object for, 449
  - request processing, 569
  - terminology, 16
- CLOUD\_BACKEND, 450
- CLOUD\_BASE\_PATH, 450
- CLOUD\_BUCKET, 450
- CLOUD\_HOST, 450
- CLOUD\_PASSWORD, 151, 451
- CLOUD\_REDUNDANCY, 451
- collecting information for problem analysis, 126
- COMMAND, 394, 452, 456, 461, 468
- commands, 56, 59
- commands that are undocumented, 130
- commands to run on a copy of the DMF
  - database, 125
- comments and DMF Manager configuration, 211
- communication, 91
- COMPRESSION\_TYPE, 398
- configuration
  - allocationgroup object, 435
  - automated space management, 369, 376
  - backup of, 102
  - base object, 278
  - best practices, 87
  - cloud MSP, 449
  - command overview, 58
  - considerations, 169
  - daemon object configuration, 290
  - DCM, 460
  - DCM MSP, 464
  - device object, 348
  - disk MSP, 467
  - DMF Manager and, 210

- dmmaint and, 791
- drivegroup object, 397
- dump\_tasks, 309
- fastmountcache object, 390
- file weighting, 371, 378, 386
- filesystem object, 351
- FTP MSP, 455
- initial, 791
- libraryserver object, 393
- LS objects, 392
- LS setup, 444
- migrategroup object, 427
- msp object
  - cloud MSP, 449
  - DCM, 460
  - DCM MSP, 464
  - disk MSP, 467
  - FTP MSP, 455
- MSP/VG selection, 374, 380, 388
- MSP/VG selection for integrated backups, 389
- node object, 294
- objects, 58, 272
- OpenVault, 502
- overview, 165
- parameters, 58, 472
  - See also "parameters", 278
- policy object, 364
- resourcescheduler object, 432
- resourcewatcher object, 434
- services object, 300
- space management parameters, 511
- SPOOL\_DIR, 525
- stanza, 274
- stanza format, 274
- taskgroup object, 442
- verifying, 487
- volumegroup object, 411

configuration file samples, 101

Configuration menu in DMF Manager, 193

configuration pending message, 170

Configuration tab in DMF Manager, 193

- Configure button, 790
- context manipulation subroutines, 705
- converting data from other HSMs, 189
- COPAN
  - configuration best practices, 109
- COPAN MAID
  - fast-mount cache and, 112
- COPAN MAID VSN, 64
- COPAN RAID set, 8
- COPAN VTL stopping, 595
- COPAN\_VSNS, 102, 394
- copy file requests, 710
- count directive, 518, 545, 555
- cpio file recall, 643
- create directive, 518, 545, 555
- ctime, 358
- current metrics, 242
- custom I/O performance charts, 248
- customizable policies
  - See "site-defined policies", 188
- customizing DMF, 186
- CXFS
  - basic DMF figure, 33
  - DMF and, 104
  - parallel data-mover nodes and, 35
  - RECALL\_NOTIFICATION\_RATE and, 107
  - support for, 8
- cxfs\_admin, 486
- cxfs\_recovery\_timeout\_stalled, 119

## D

- daemon
  - commands overview, 59
  - configuration parameters, 290
  - configuring automated maintenance tasks, 304
  - dmd\_db.dbd, 647
  - log, 507
  - logs and journals, 525
  - object

- See "dmdaemon object", 272
  - processing, 515
  - shutdown, 516
  - startup, 515
  - tasks, 304
- data integrity, 38
  - administrative tasks and, 54
  - copying filesystem data, 309
  - overview, 38
- data reduction process and DMF Manager, 130
- data reliability
  - administrative tasks and, 54
  - copying daemon database, 339
  - copying filesystem data, 309
- data-capability license, 67
- data-mover process, 33
- DATA\_LIMIT, 307, 313, 443
- database daemon, 37
- database journal files, 527
- database loading and journaling, 128
- database lock manager incompatibility, 788
- DATABASE\_COPIES, 305, 313, 339
- databases, 37
  - audit, 305
  - automated verification task, 337
  - automating copying for reliability, 339
  - back up, 305
  - backup, 646
  - configuring automated tasks, 339
  - directory location, 517
  - dmcatadm, 677
  - dmdadm and, 517
  - dmvoladm message, 679
  - record length, 173
  - recovery, 649
  - See "daemon database", 173
  - selection, 646
  - size of databases, 97
- dataleft, 679
- dataleft keyword, 558
- datalimit, 560
- datawritten keyword, 558
- DB\_SERVER\_BIN, 280
- DB\_SERVER\_HOST, 280
- DB\_SERVER\_PORT, 280
- dbrec.dat file, 647
- dbrec.keys file, 647
- DCM
  - administration, 307
  - configuration, 460
- DCM disk caches, 246
- DCM MSP
  - child-process constraints, 122
  - commands, 63
  - configuration, 464
  - disk MSP and, 579
  - filesystems and, 161
  - terminology, 16
- DCM STORE\_DIRECTORY rules, 367
- DCP disabling, 590
- dd, 135
- delay icon on Windows systems, 127
- delay in accessing files, 668
- delete directive, 518, 545, 555
- deleeteage, 521
- deletetime, 521, 524
- delimiter in configuration file, 275
- device block-size defaults and bandwidth, 276
- device object
  - overview, 273
  - parameters, 348
- DHCP and YAST, 83
- direct archiving
  - See "DMF direct archiving", 13, 119
- DIRECT\_IO\_MAXIMUM\_SIZE, 280
- DIRECT\_IO\_SIZE, 352, 461
- directory structure prior to DMF 2.8, 783
- dirsnc and STORE\_DIRECTORY, 46
- disable components
  - COPAN VTL, 595
  - DCP, 590
  - library, 592

- OpenVault drive, 591
- TMF drive, 594
- disaster recovery
  - DMF Manager and, 651
  - DR bundle, 150
  - DR database, 151
  - HA and, 657
  - integrated backups and, 651
  - overview, 89, 650
  - Parallel DMF and, 655
  - See also "DR bundle", 154
- DISCONNECT\_TIMEOUT, 394
- disk cache manager
  - See "DCM MSP", 579
- disk MSP
  - command, 64
  - configuration, 467
  - local, 121
  - log files, 578
  - overview, 577
  - request processing, 577
  - terminology, 16
  - verification, 579
- disk space capacity, 7
- DISPLAY environment variable, 789
- DLT, 276
- DmaConfigStanzaExists(), 752
- DmaContext\_t, 739
- DmaFrom\_t, 740
- DmaGetConfigBool(), 753
- DmaGetConfigFloat(), 754
- DmaGetConfigInt(), 755
- DmaGetConfigList(), 756
- DmaGetConfigStanza(), 757
- DmaGetConfigString(), 758
- DmaGetContextFlags(), 759
- DmaGetCookie(), 759
- DmaGetDaemonMigGroups, 760
- DmaGetDaemonVolAndMigGroups(), 760
- DmaGetDaemonVolGroups(), 761
- DmaGetMigGroupMembers, 761
- DmaGetProgramIdentity(), 762
- DmaGetUserIdentity(), 762
- DmaIdentity\_t, 740
- DmaLogLevel\_t, 742
- dmanytag, 785
- DMAPI
  - automatically enabled, 105
  - kernel interface, 39
  - requirement, 48
- DMAPI on SLES 10, 660
- DMAPI\_PROBE, 670
- dmarchive, 13, 50, 57, 119, 351, 708
- dmarchive.php, 601
- DmaRealm\_t, 742
- DmaRecallType\_t, 743
- DmaSendLogFmtMessage(), 763
- DmaSendUserFmtMessage(), 764
- DmaSetCookie(), 765
- dmats
  - journal files, 538
  - library server terminology, 16
  - log files, 539
  - LS operations, 532
  - VOL records, 537
- dmatrc, 42, 532
- dmatread, 63, 533, 567
- dmatsnf, 63, 533, 568
- dmattr, 57
- dmattr.php, 601
- dmatvfy, 63
- dmatwc, 42, 532
- dmaudit, 51
  - changes in DMF 3.2, 787
  - summary, 60
  - verifymsp, 568
- dmcancel, 263, 606
- dmcapacity, 57
- dmcatadm
  - directives, 545
  - example of list directive, 552
  - field keywords, 548



- interface, 544
- keywords, 548
- limit keywords, 550
- summary, 63
- text field order, 553
- dmcheck, 60, 487, 658
- dmclearcmtag, 785
- dmclearpartial, 786
- dmcleartag, 785
- dmcloudmsp, 16, 452
- dmclrpc, 64
- dmcollect, 64, 126, 675
- dmconfig, 59
- dmcopan, 64
- dmcopy, 57
- dmd\_db journal file, 525
- dmd\_db.dbd, 647
- dmdadm
  - directives, 517, 518
  - example of list directive, 523
  - field keywords, 520
  - format keyword, 522
  - format keywords, 520
  - limit keywords, 522
  - selection expression, 519
  - summary, 60
  - text field order, 524
- dmdadm -j, 128
- dmdaemon (use service command), 124
- dmdaemon object
  - associated task scripts, 305
  - icon in DMF Manager, 213
  - overview, 272
  - parameters, 290
- dmdate, 64
- dmdbcheck, 56, 60, 63, 125
- dmdbrecover, 60, 647
- dmdidle, 60
- dmdlog log, 507
- dmdlog log file, 515, 525
- dmdskfree, 63
- dmdskmsp, 16, 577
- dmdskvfy, 64, 579
- dmdstat, 60
- dmdstop, 60, 516
- dmdstop (use service command), 124
- dmdu, 57
- dmdump
  - run only on a copy of the DMF database, 125
  - summary, 64
  - text field order, 563
- dmdumpj, 64
- DMF Activity panel in DMF Manager, 193
- DMF administrative directories, 44
- DMF administrative directory permission requirements, 45
- DMF direct archiving
  - API subroutines, 712
  - archive file requests, 712
  - configuration file and, 351
  - DmuFilesysInfo(), 708
  - filesystem object and, 351
  - overview, 119
  - requirements, 50
  - SiteArchiveFile() policy subroutine, 743
- DMF file properties, 12
- DMF I/O panel in DMF Manager, 193
- DMF Manager
  - About panel, 194
  - access password, 192
  - accessing the GUI, 192
  - acknowledge a command, 233
  - Activity panel, 193, 235
  - Admin Guide panel, 194
  - Admin mode functionality, 196
  - admin password, 198
  - Alerts panel, 193, 222
  - archives, 130, 235
  - Backups tab, 193
  - browser support, 49
  - checkpoint a command, 233
  - configuration file parameter display, 219

- Configuration menu, 193
- Configuration tab, 193
- configuring DMF, 210
  - creating a new object, 217
  - deleting an object, 218
  - exiting configuration mode, 219
  - limitations, 211
  - new configuration file, 212
  - object menu, 212
  - saving changes, 218
  - show all objects, 211
  - templates, 212
  - validating changes, 218
- copying an object, 215
- DCM MSP monitoring, 246
- disaster recovery, 262
- DMF Activity panel, 193, 234
- DMF I/O panel, 193
- DMF Manager Tasks panel, 193
- DMF Resources panel, 193, 234
- drive state, 242
- error messages, 666
- filesystem monitoring, 239
- Getting Started, 201
- Getting Started panel, 193
- help, 198
- Help menu, 194
- hold flags, 231
- I/O panel, 193
- I/O statistics, 248
- installing/deleting licenses, 203
- introduction, 9
- key to symbols, 199
- kill a command, 233
- library management, 232
- Library panel, 193
- library usage, 242
- license capacity, 205
- Licenses panel, 193
- login, 198
- menu bar, 192
- Messages tab, 193
- metrics, 130, 235
- modifying an object, 217
- monitoring performance, 233
- node state, 252
- OpenVault library is missing, 668
- Overview panel, 10, 192, 193
- Parameters panel, 193, 220
- password to access the GUI, 192
- password to make administrative changes, 198
- preferences, 201
- problem discovery, 221
- queue viewing, 263, 605
- quick start, 201
- Recovery panel, 193
- refreshing the view, 202
- relationships among DMF components, 10, 227
- Reports panel, 193, 225
- requirements, 49
- Resources panel, 193
- resources statistics, 238
- resume a command, 233
- starting/stopping DMF, 220
- starting/stopping the mounting service, 220
- statistics, 666
- Statistics menu, 234
- Statistics tab, 193
- Storage tab, 193
- tasks, 233
- tips for using, 192
- troubleshooting, 666
- URLs for, 192
- user-generated activity, 235
- Volumes panel, 193, 229
- “what is” help, 201
- DMF Manager Tasks panel in DMF Manager, 193
- DMF mover service, 487
- DMF Resources panel in DMF Manager, 193
- DMF SOAP
  - See "SOAP", 597
- DMF software

- archiving overview, 19
- cycle, 2
- migration, 7
- DMF statistics are unavailable, 666
- DMF user library
  - See "user library (libdmfusr.so)", 681
- dmf.conf
  - See "'configuration" and "parameters"', 59
- dmf.conf.cloud, 101
- dmf.conf.copan\_maid, 101
- dmf.conf.copan\_vtl, 101
- dmf.conf.dcm, 101
- dmf.conf.dsk, 101
- dmf.conf.fmc, 101
- dmf.conf.ftp, 101
- dmf.conf.jbfs, 101
- dmf.conf.ls, 101
- dmf.conf.parallel, 102
- dmf\_client\_ports, 188
- dmfdaemon, 61, 515
- dmfill, 65, 587
- dmfind, 57
- dmflicense, 58, 77
- dmfsfree, 62, 509
- dmfsmon, 62, 369, 376, 509–511
- dmfsoap, 600
- dmfsoap stop, 601
- dmftpmisp, 16, 449, 455, 573
- dmfusr.so, 785
- dmget, 57
- dmget.php, 601
- dmhdelete, 61
- dmi, 105, 660
- dmi mount option, 105
- DMIG, 39
- dmlocklog log, 507
- dmlockmgr
  - abort, 529
  - communication and log files, 527
  - continuous execution, 527
  - database journal files, 527
  - interprocess communication, 528
  - log, 507
  - overview, 65
  - transaction log files, 527, 529
- dmls, 57
- dmmaint
  - configuration file definition, 791
  - Configure button, 790
  - GUI, 789
  - Inspect button, 790
  - License Info button, 791
  - multiple active versions of DMF, 783
  - overview, 789
  - Release Note button, 790
  - Update License button, 791
- dmmigrate
  - file backup, 643
  - summary, 61
- dmmigrate periodic task, 116
- DMMIGRATE\_MIN\_OFFLINE\_AGE, 313
- DMMIGRATE\_MIN\_OFFLINE\_SIZE, 314
- DMMIGRATE\_MINIMUM\_AGE, 117, 313
- DMMIGRATE\_QUEUE\_MAX, 314
- DMMIGRATE\_TRICKLE, 117, 314
- DMMIGRATE\_UNACK, 314
- DMMIGRATE\_VERBOSE, 117, 314
- DMMIGRATE\_WAIT, 117, 314
- dmmove, 65, 136, 292, 579, 580, 642
- dmmvtree, 65
- dmn\_connect table, 622, 625
- dmn\_request table, 622, 626
- dmnode\_admin, 488
- dmoper, 57, 185
- dmoper.php, 602
- dmov\_keyfile, 65, 498
- dmov\_loadtapes, 65, 505
- dmov\_makecarts, 65, 504
- dmprojid, 65
- dmprojid.php, 602
- dmpu, 57
- dmpu.php, 602

- dmqview, 66, 605
- dmrepri, 64, 66, 263, 606
- dmrestore, 66
- dmrestore.php, 602
- dmscanfs, 62, 306, 511
- dmselect, 66, 580
- dmsnap, 61
- dmsort, 66
- dmstat, 66
- dmtag, 57, 358, 785
- dmtag.php, 602
- dmtapestat, 66
- DMU\_DEF\_PRIORITY, 701
- DMU\_MAX\_PRIORITY, 701
- DMU\_MIN\_PRIORITY, 701
- DmuAllErrors\_t, 686
- DmuArchiveAsync(), 712
- DmuArchiveSync(), 712
- DmuAttr\_t, 687
- DmuAwaitReplies(), 728
- DmuByteRange\_t, 688
- DmuByteRanges\_t, 689
- DmuChangedDirectory(), 707
- DmuCompletion\_t, 692
- DmuCopyAsync\_2(), 710
- DmuCopyRange\_t, 693
- DmuCopyRanges\_t, 693
- DmuCopySync\_2(), 710
- DmuCreateContext(), 705
- DmuDestroyContext(), 707
- DmuErrHandler\_f, 694
- DmuErrInfo\_t, 695
- DmuError\_t, 695
- DmuEvents\_t, 696
- DmuFhandle\_t, 696
- DmuFilesysInfo(), 708
- DmuFsysInfo\_t, 696
- DmuFullRegbuf\_t, 697
- DmuFullRegion\_t, 698
- DmuFullstat\_2\_t, 699
- DmuFullstat\_t, 698
- DmuFullstatByFhandleAsync(), 714
- DmuFullstatByFhandleSync(), 714
- DmuFullstatByPathAsync(), 714
- DmuFullstatByPathSync(), 714
- DmuFullstatCompletion(), 729
- DmuGetByFhandleAsync\_2(), 720
- DmuGetByFhandleSync\_2(), 720
- DmuGetByPathAsync\_2(), 720
- DmuGetByPathSync\_2(), 720
- DmuGetNextReply(), 730
- DmuGetThisReply(), 732
- dmunput, 66
- DmuOperandType\_t, 700
- DmuPriority\_t, 701
- DmuPutByFhandleAsync(), 717, 748
- DmuPutByFhandleSync(), 717, 748
- DmuPutByPathAsync(), 717, 748
- DmuPutByPathSync(), 717, 748
- DmuRegion\_t, 701
- DmuRegionbuf\_t, 701
- DmuReplyOrder\_t, 702
- DmuReplyType\_t, 702
- dmusage, 58, 72
- DmuSettagByFhandleAsync(), 725
- DmuSettagByFhandleSync(), 725
- DmuSettagByPathAsync(), 725
- DmuSettagByPathSync(), 725
- DmuSeverity\_t, 702
- DmuVolGroup\_t, 703
- DmuVolGroups\_t, 703
- dmversion, 58
- dmversion.php, 602
- dmvoladm
  - directives, 555
  - examples of list directive, 564
  - field keywords, 558
  - format keywords, 561
  - limit keywords, 560
  - select directive, 543
  - summary, 63
  - text field order, 563

- VOL records and, 538
- dmxfsrestore, 66
- DNS, 92, 93
- do\_predump.sh
  - snapshot location, 768
  - summary, 768
  - Time Navigator, 770
- domain name service, 93
- downgrade
  - best practices, 81, 87
  - partial-state file feature and, 786
- DR bundle, 154
  - See "disaster recovery", 150
- DR database
  - See "disaster recovery", 151
- drive disabling, 591
- drive does not exist, 661
- drive entry error, 660
- drive group
  - object, 273
  - OpenVault and, 502
  - terminology, 40
  - TMF tapes and, 505
- drive visibility, 49
- drive-group names, 121
- DRIVE\_GROUPS, 102, 116, 394
- DRIVE\_MAXIMUM, 99, 399, 413
- DRIVE\_SCHEDULER, 400
- drivegroup, 116
- drivegroup object
  - overview, 273
  - parameters, 397
- drives
  - performance improvements, 105
  - zone size and, 105
- DRIVES\_TO\_DOWN, 400
- DRIVETAB, 315
- DSK\_BUFSIZE, 461, 468
- DSO, 41
- dual-residence, 367
- dual-resident state, 579
- dual-state file, 19, 28
  - file migration and, 3
  - terminology, 15
  - xfsdump and, 643
- DUALRESIDENCE\_TARGET, 377
- dump directive, 518, 545, 555
- dump utilities, 55
- DUMP\_COMPRESS, 315, 343, 352
- DUMP\_CONCURRENCY, 316
- DUMP\_DATABASE\_COPY, 768, 769
- DUMP\_DESTINATION, 150, 316
- DUMP\_DEVICE, 317
- DUMP\_DR\_EMAIL, 317
- DUMP\_DR\_EMAIL\_MAX\_SIZE, 317
- DUMP\_DR\_MINIMAL, 317
- DUMP\_DR\_MIRRORS, 317
- DUMP\_FILE\_SYSTEMS, 318, 344, 768
- DUMP\_FLUSH\_DCM\_FIRST, 163, 319, 462, 768
- DUMP\_GROUPS, 319
- DUMP\_INVENTORY\_COPY, 319
- DUMP\_MAX\_FILESPACE, 148, 320, 344, 354
- DUMP\_MIGRATE\_FIRST, 137, 146, 163, 320, 345, 354, 768
- DUMP\_MIRRORS, 177, 321
- DUMP\_MISC\_LOCATIONS, 151, 321
- DUMP\_POST\_BACKUP\_SCRIPT, 321
- DUMP\_POST\_DR\_SCRIPT, 322
- DUMP\_PRE\_BACKUP\_SCRIPT, 322
- DUMP\_RETENTION, 143
  - ASG-Time Navigator, 770
  - run\_hard\_deletes.sh, 306
  - summary, 323
- DUMP\_STREAMS
  - summary, 323, 345, 354
- DUMP\_TAPES, 186, 324
- dump\_tasks, 309
- DUMP\_VSNS\_USED, 324
- DUMP\_WORKSPACE
  - summary, 324
- DUMP\_XFSDUMP\_PARAMS, 324, 345, 354
- dumps.db, 149

Dynamic Shared Object library, 41

## E

empty damaged volume in DMF Manager, 232

empty graphs, 668

end of life

    tape autoloader API, 783

    tape MSP, 784

enhanced-NFS RPC corruption, 131

entitlement ID, 74

entries keyword, 551

EOF, 384

EOT error, 660

eotblockid keyword, 558

eotchunk, 679

eotchunk keyword, 558

eotpos, 679

eotpos keyword, 559

eotzone, 680

eotzone keyword, 559

error messages in DMF Manager, 193

error reports and tapes, 443

    /etc/dmf/dmbase, 784

    /etc/dmf/dmf.conf, 472, 667

    /etc/hosts, 91

    /etc/hosts file, 92

    /etc/lk/keys.dat, 75

    /etc/nsswitch.conf, 92

    /etc/resolv.conf, 93

    /etc/sgi-ltfs.conf, 633

    /etc/tmf/tmf.config, 126

    /etc/xinetd.conf, 108

    /etc/xinetd.d/auth, 166, 167

    /etc/xinetd.d/pidentd, 166, 167

    /etc/xinetd.d/tcpmux, 108

examples

    /etc/hosts file, 92

    /etc/inet/hosts file, 92

    name services, 92

explicit start, 183

explicit start dmfsop, 601

explicit stop, 184

EXPORT\_METRICS, 102, 280, 667

EXPORT\_QUEUE, 290

extended attribute structure, 171

extension records, 104

## F

fabric, 49

FADV\_SIZE\_MAID, 400

FADV\_SIZE\_MSP, 462, 468

fast-mount cache

    configuration best practices, 112

    definition, 16

    diagrams, 24

    merging and, 113

    multiple migration copies and, 100

    overview, 30

    requirements, 50

fastmountcache, 112

fastmountcache object

    overview, 273

    parameters, 390

feature history, 783

file concepts, 14

file hard deletion, 306

file migration

    See "migration", 3, 510

file ranking, 53

file recall, 28

file regions, 5

file request subroutines, 709

file tagging, 186

file weighting, 365, 371, 378, 386

FILE\_RETENTION\_DAYS, 114, 307, 308, 325

filesize keyword, 549

filesys table, 622, 627

filesystem errors, 658

filesystem information subroutine, 708  
 filesystem object  
   overview, 273  
   parameters, 351  
 filesystems  
   back up, 306  
   conversion, 462, 469  
   DCM MSP and, 161  
   dmdskmsp, 462, 469  
   dmftpmmsp, 452, 457  
   migrate, 305, 307  
   mount options, 83  
   report on, 306  
   scan, 306  
 filters, 225  
 FINISH message  
   FTP MSP, 576  
 Firefox and DMF Manager, 10, 49  
 flag keywords, 561  
 FLUSHALL message  
   FTP MSP, 576  
 FMC  
   See "fast-mount cache", 50  
 FMC\_MOVEFS, 114, 307, 308, 325  
 FMC\_NAME, 325  
 force migration, 107  
 format keyword, 523, 551  
 FORWARD\_RECALLS, 140, 185, 413  
 free space management, 7, 53  
 free-space minimum threshold, 2, 7  
 FREE\_DUALRESIDENT\_FIRST, 377  
 FREE\_DUALSTATE\_FIRST, 369  
 FREE\_SPACE\_DECREMENT, 369, 377, 512  
 FREE\_SPACE\_MINIMUM, 369, 377, 511  
 FREE\_SPACE\_TARGET, 370, 378  
 FREE\_VOLUME\_MINIMUM, 113, 307, 308, 325  
 FREE\_VOLUME\_TARGET, 113, 307, 308, 326  
 FTP, 8  
 FTP MSP  
   log files, 575  
   messages, 576

  msp object for, 455  
   overview, 573  
   request processing, 573  
   terminology, 16  
 FTP\_ACCOUNT, 456  
 FTP\_COMMAND, 456  
 FTP\_DIRECTORY, 456  
 FTP\_HOST, 456  
 FTP\_PASSWORD, 151, 457  
 FTP\_PORT, 457  
 FTP\_USER, 457  
 FULL\_THRESHOLD\_BYTES, 468  
 FULL\_ZONE, 414  
 fullstat requests, 714

## G

get file requests, 720  
 GET\_WAIT\_TIME, 140, 414  
 Getting Started panel in DMF Manager, 193  
 gid expression, 381  
 globals table, 622  
 gmgrd, 668  
 gray background in DMF Manager, 213  
 GROUP\_MEMBERS, 102, 428  
 GUARANTEED\_DELETES, 122, 452, 457, 462, 469  
 GUARANTEED\_GETS, 122, 452, 457, 462, 469  
 GUI  
   See "DMF Manager", 9

## H

h1, 562  
 HA  
   differences in administration and  
     configuration, 125  
   DMF support, 13  
   license requirements, 68  
 HA cluster and DNS, 93

- hard-deleted files
  - maintenance/recovery, 586
  - run\_hard\_deletes.sh task, 306
- hardware requirements, 43
- HBA drivers, 107
- HBA\_BANDWIDTH, 280, 295
- he, 561
- help directive, 518, 545, 555
- Help menu in DMF Manager, 194
- helper subroutines for sitelib.so, 752
- herr, 561
- hexadecimal number, 384
- hextern, 186, 561
- hf, 559
- hflags, 559, 562
- hfree, 562
- HFREE\_TIME, 415
- hfull, 562
- hierarchical storage management, 5
- high availability
  - See "HA", 13
- historical feature information, 783
- hl, 562
- hlock, 562
- ho, 562
- hoa, 562
- hold flags, 231, 558
- HOME\_DIR, 45, 97, 281, 486, 533
- host port speeds and tape drives, 134
- hostname mapping, 91
- hosts file, 92
- HP ULTRIUM, 276
- hr, 562
- hro, 562
- hs, 562
- hsite\*, 562
- HSM conversion to DMF, 189
- HSM data import, 189
- hsparse, 562
- HTML\_REFRESH, 434
- hu, 562

- hv, 562
- HVD disk, 8
- hvfy, 562
- hx, 561

## I

- I/O panel in DMF Manager, 193
- IBM 03590, 276
- IBM TS1140, 276
- IBM ULT3580, 276
- IBM ULTRIUM, 276
- ident service, 47, 166
- immutable bit, 140
- IMMUTABLE\_BFIDS, 354
- IMPORT\_DELETE, 457, 469
- IMPORT\_ONLY, 415, 457, 469
- importing data from other HSMs, 189
- incremental backups, 148
- incremental data-capacity license, 67
- initial configuration, 791
- initial planning, 52
- initrd, 107
- INITRD\_MODULES, 107
- inode, 15
- inode size, 171
- inode-resident extended attributes, 104
- inodes, 5
- Inspect button, 790
- inst, 183, 184, 601
- installation, 170
  - best practices, 81
  - client installers on DMF server, 169
  - considerations, 169
  - ISSP release, 169
  - overview, 165
  - procedure, 165
- installation source, 52
- instances parameter, 108
- integrated backups



- pruning files, 142
  - See "backups", 141
- integrated data-mover functionality, 35
- INTERFACE, 121, 295
- Internet Explorer and DMF Manager, 10, 49
- interoperability, 8
- interprocess communication (IPC), 175, 527, 528
- introduction, 1
- IOStreamGuard, 179
- IPv4, 91, 93
- IPv6, 91, 93
- IRIX
  - client platform, 12
- IRIX conversion, 773

**J**

- JBFS, 8
- joining of byte ranges, 385
- journal files
  - configuring automated task for retaining, 338
  - database, 527
  - dmfdaemon, 525
  - LS, 538
  - remove, 306
  - retaining, 586
  - summary, 56
- JOURNAL\_DIR, 45, 98, 163, 281, 525, 533, 538
- JOURNAL\_RETENTION, 306, 326, 526, 539
- JOURNAL\_SIZE, 282, 526, 538, 539
- journaling and database loading, 128

**K**

- keys.dat, 75
- KILL\_WC\_IF\_DEMAND, 412
- Knowledgebase, 675

**L**

- label keyword, 559
- LABEL\_TYPE, 400
- LCP and COPAN, 110
- libdmfadm.H, 739
- libdmfcom.H, 739
- libdmfusr.so, 58, 187
  - See "user library (libdmfusr.so)", 681
- libraries, 242
  - See "site-defined policy library", 735
  - See "user library (libdmfusr.so)", 681
- library disabling, 592
- Library panel in DMF Manager, 193
- library server
  - See "LS", 392
- library slot usage, 242
- library versioning, 684
- libraryserver, 116
- libraryserver object
  - associated task scripts, 307
  - overview, 273
  - parameters, 393
- libsrv\_db journal file, 538
- libsrv\_db.dbd, 537, 538, 647
- license capacity, 205
- License Info button, 791
- License Keys (LK), 67
- LICENSE\_FILE, 102, 282
- Licenses panel in DMF Manager, 193
- licensing, 67
  - capability license, 67
  - capacity determination, 72
  - commands, 58
  - data-capacity license, 67
  - dmflicense, 58, 77
  - dmusage, 58
  - entitlement ID, 74
  - /etc/lk/keys.dat, 282
  - file, 282
  - HA and, 68

- host information, 74
- installation, 75
- keys, 75
- License Keys (LK), 67
- LICENSE\_FILE, 282
- lk\_hostid, 74
- lk\_verify, 77
- mounting services and, 74
- obtaining from SGI, 75
- OpenVault and, 74
- Parallel Data-Mover Option and, 74
- requirements, 48
- SGI webpage, 79
- stored capacity and, 67
- TMF and, 74
- types, 67
- verification, 75
- lights-out operations, 52
- limit keywords
  - dmcatadm, 550
  - dmvoladm command, 560
- Linux
  - partial-state files and, 779
- list directive, 518, 545, 555
- LK license, 67
- lk\_hostid, 74
- lk\_verify, 77
- load directive, 518, 545, 555
- LOCAL\_, 125
- lock manager, 527
- log files
  - automated space management, 513
  - automated task for retaining, 338–340
  - changes in DMF 3.2, 787
  - cloud MSP, 571
  - disk MSP, 578
  - dmfdaemon, 525
  - dmlckmgr communication and, 527
  - FTP MSP, 575
  - LS, 539
  - remove, 306
  - retaining, 585
  - scan for errors, 307
  - transaction log files, 529
- LOG\_RETENTION, 306, 308, 326
- LOGICAL\_BLOCK\_PROTECTION, 416
- login for DMF Manager, 198
- logs
  - general format, 507
- low-voltage differential (LVD) tapes, 8
- LS
  - architecture, 39
  - CAT records, 532, 536
  - commands, 57
  - configuration example, 436
  - database, 538
  - database recovery, 649
  - directories, 533
  - dmatread, 567
  - dmatsnf, 568
  - dmaudit verifymsp, 568
  - dmcatadm, 544
  - dmvoladm, 554
  - drive scheduling, 582
  - error analysis and avoidance, 580
  - journals, 538
  - log files, 539
  - objects, 273, 393
  - operations, 532
  - process, 40
  - setup, 392
  - status monitoring, 582
  - tape operations, 532
  - tape setup, 444
  - terminology, 15
  - VOL records, 533, 537
  - volume merging, 543
- LS commands, 63
- LS database, 37
- LS\_NAMES, 102, 116, 290
- LSI FC ports and N-port technology, 133
- lsiutil, 134

## LTFS

- best practices, 632
- configuration, 633
- features, 631
- requirements, 632
- LTFS and DMF Manager, 263
- LTFS\_CART\_GROUP, 634
- LTFS\_DRIVE\_GROUP, 634
- LTFS\_MAX\_DRIVES, 635
- LTFS\_MOUNT\_ROOT, 635
- LTFS\_OV\_KEYFILE, 635
- LTO-5, 631
- LTO-6, 631
- Lustre filesystem and DMF archiving, 13, 119
- LVD tapes, 8

## M

Mac OS X, 12

## MAID

- configuration best practices, 109
- maintenance and recovery
  - automated, 175
  - cleaning up journal files, 586
  - cleaning up log files, 585
  - daemon configuration, 304
  - database backup, 646
  - databases , 649
  - dmfill, 587
  - dmmaint, 789
  - hard-deletes, 586
  - soft-deletes, 586
- maintenance task configuration, 442
- managed filesystem policy parameters in DMF
  - configuration file, 368
- managed filesystem rules, 366
- managing the DMF environment
  - See "DMF Manager", 9
- manypartial, 786
- MAX\_ALERTDB\_SIZE, 118, 326

- MAX\_CACHE\_FILE, 395
- MAX\_CHUNK\_SIZE, 416
- MAX\_IDLE\_PUT\_CHILDREN, 417
- MAX\_MANAGED\_REGIONS, 122, 355
- MAX\_MS\_RESTARTS, 170, 401
- MAX\_PERFDB\_SIZE, 118, 306, 327
- MAX\_PUT\_CHILDREN, 99, 401, 417
- maximum burst size, 134
- media, 52
- media concepts, 534
- media transports, 42
- media-specific processes
  - See "MSP", 15
- Mediaflux requirements, 51
- memory-mapping issues, 131
- MERGE\_CUTOFF, 418
- MERGE\_INTERFACE, 121, 295
- MERGE\_THRESHOLD, 113, 418
- merging and fast-mount cache, 113
- merging sparse tapes
  - run\_merge\_mgr.sh, 307
  - run\_tape\_merge.sh, 443
- merging sparse volumes
  - DMF Manager and, 232
  - run\_merge\_stop.sh, 443
- MESSAGE\_LEVEL, 291, 300, 356, 395, 452, 458, 462, 469
- messages
  - dmcatadm, 677
  - dmvoladm, 679
  - FTP MSP, 576
  - log, 507
- Messages tab in DMF Manager, 193
- metrics in DMF Manager monitoring, 130, 235
- METRICS\_RETENTION, 282
- MG
  - objects, 273
- MiB vs MB and DMF Manager, 234, 236
- migrate files via Windows client, 12
- migrate group
  - configuration best practices, 111

- COPAN and, 110
- migrated data movement between MSPs, 579
- migrated file, 3
- migrategroup object
  - overview, 273
  - parameters, 428
- migrating data from other HSMs, 189
- migration
  - automated file selection, 511
  - file exclusion, 510
  - file selection, 511
  - frequency, 7
  - MSP/VG, 388, 389
  - MSP/VG selection, 374, 380
  - multiple copies of a file, 100
  - overview, 5, 27
  - policies, 7
  - real-time partitions and, 513
  - recalling, 28
  - relationship of space management targets, 512
  - target, 509
  - terminology, 15
  - triggers, 7
  - weighting of files, 371, 378, 386
- migration policies, 7
- migration targets, 7
- MIGRATION\_LEVEL, 291, 356, 366, 367, 462
- MIGRATION\_TARGET, 371
- MIN\_ARCHIVE\_SIZE, 356
- MIN\_DIRECT\_SIZE, 357, 463
- MIN\_VOLUMES, 419
- mkfs.xfs, 136, 171
- modification prevention, 140
- modifications to the DMF configuration, 102
- monitoring DMF, 125
- monitoring performance, 233
- mount errors, 671
- mount options, 83
- MOUNT\_BLOCKED\_TIMEOUT, 402
- MOUNT\_SERVICE, 348, 402
- MOUNT\_SERVICE\_GROUP, 349, 402
- MOUNT\_TIMEOUT, 403
- mounting service tasks
  - OpenVault, 491
  - TMF, 505
- mounting services
  - See “OpenVault” or “TMF”, 13
- MOVE\_FS, 46, 98, 163, 291, 292, 486
- mover table, 623, 628
- MSG\_DELAY, 403
- MSGMAX, 175
- MSGMNI, 175
- MSP
  - automated maintenance tasks, 338
  - CAT records, 536
  - commands, 57
  - configuration, 388, 389
  - disk, 577
  - dmatread, 567
  - dmcatadm message, 677
  - dmfdaemon, 532
  - dmvoladm message, 679
  - FTP, 573
  - log files, 338
  - log files and automated maintenance tasks, 442
  - logs, 507
  - moving migrated data between MSPs, 579
  - msp object
    - cloud MSP, 449
    - DCM, 460
    - DCM MSP, 464
    - disk MSP, 467
    - FTP MSP, 455
    - overview, 274
  - selection for migrating files, 374, 380
  - tape setup, 444
  - tasks, 443
  - terminology, 15
  - types, 17
- MSP objects, 446
- MSP/VG selection, 366
- MSP\_NAMES, 102, 290

msp\_request table, 623, 629  
 msp\_tasks, 442  
 mspkey, 521, 524  
 msplog  
   message format, 507  
 msplog file  
   disk MSP, 578  
   dmatls, 541  
   LS logs, 539  
   LS statistics messages, 541  
 mspname, 521, 524  
 MULTIPLIER, 102, 428  
 MULTITAPE\_NODES, 404  
 MVS\_UNIT, 458

## N

N-port technology, 133  
 n-tier capability, 16  
 NAME\_FORMAT, 116, 173, 453, 458, 463, 470  
 Network Information Service, 91  
 network service configuration and YAST, 83  
 NFS, 8  
 nfsd\_workaround, 132  
 NIS, 91, 92  
 node object  
   overview, 272  
   parameters, 294  
 node status in DMF manager, 252  
 NODE\_ANNOUNCE\_RATE, 300  
 NODE\_BANDWIDTH, 283, 295  
 NODE\_TIMEOUT, 300  
 NTP, 124  
 number of copies, 7

## O

objects in DMF configuration file  
   allocationgroup object parameters, 435

base object, 278  
 device object, 348  
 dmdaemon object, 290  
 drivegroup object, 397  
 fastmountcache object, 390  
 filesystem object, 351  
 libraryserver object, 393  
 migrategroup object, 427  
 msp object  
   cloud MSP, 449  
   DCM, 460  
   DCM MSP, 464  
   disk MSP, 467  
   FTP MSP, 455  
 node object, 294  
 overview, 272  
 policy object, 364  
 resourcescheduler object, 432  
 resourcewatcher object parameters, 434  
 services object, 300  
 stanza format, 274  
 taskgroup object, 304, 442  
 volumeobject object, 411  
 offline data management, 54  
 offline file, 3, 15, 19, 28  
 online access, 5  
 only\_from, 166, 167  
 OpenVault, 121  
   availability, 170  
   considerations, 170  
   downgrade from DMF 4.0, 87  
   key file, 283  
   license, 74  
   OV\_KEY\_FILE, 283  
   OV\_SERVER, 283  
   parameters, 283  
   server  
     DMF parameter, 283  
     parameter for LTFS, 635  
   support for, 13  
   YAST and, 83

- OpenVault configuration tasks
  - add the dmf application, 494
  - DMF and OpenVault servers differ, 502
  - drive groups, 502
  - initial server configuration, 492
  - parallel data-mover node configuration, 498
- OpenVault drive disabling, 591
- OpenVault libraries, 242
- OpenVault library disabling, 592
- OpenVault server , 122
- operations timeout on Windows, 669
- operative\_flags, 745
- operative\_priority, 745
- operative\_volgrps, 745
- origage, 521
- origdevice, 521, 524
- origin file error, 669
- originode, 521, 524
- origname, 521, 524
- origsize, 521, 524
- origtime, 521, 524
- origuid, 521, 524
- orphaned inventory entries, 142
- out-of-library tapes, 14
- out-of-library tapes, 185
- OV\_ACCESS\_MODES, 349, 404
- ov\_admin, 83
- ov\_dcp, 590
- ov\_drive, 591, 595
- ov\_dumptable, 671
- OV\_INTERCHANGE\_MODES, 349, 405
- OV\_KEY\_FILE, 102, 283, 487, 498
- ov\_library, 185, 592
- OV\_SERVER, 102
  - DMF parameter, 283
  - LTFS parameters, 635
- ov\_start, 595
- ov\_stat, 592, 593
- overhead of DMF software, 42
- oversubscription, 5
- Overview panel in DMF Manager, 192, 193

## P

- Parallel Data Mover Option
  - private network, 121
- parallel data-mover node
  - requirements, 48
- Parallel Data-Mover Option
  - active node, 74
  - configuration, 485
  - CXFS and, 105
  - disabling/reenabling nodes, 489
  - installation, 168
  - license, 67
  - node state, 488
  - overview, 33
  - terminology, 33
- Parallel DMF, 6
- parameters
  - DMF configuration parameters, 472
  - SGI LTFS configuration parameters, 634
- Parameters panel in DMF Manager, 193, 220
- partial state, 122
- partial-state file
  - CACHE\_SPACE\_WEIGHT, 379
  - considerations, 779
  - enable/disable feature, 292
  - file regions and, 5
  - Linux kernel support lacking, 779
  - online retention, 6
  - performance cost, 779
  - recall, 6
  - SPACE\_WEIGHT, 373
  - terminology, 15
- partial-state filed
  - exact byte range requests, 780
- PARTIAL\_STATE\_FILES, 122, 292
- passwords for DMF manager
  - GUI access, 192
- passwords in DMF Manager
  - admin, 198
- path segment extension record, 173

path segment extension records, 104  
 pathseg, 173  
 pathseg.dat file, 647  
 pathseg.keys file, 647  
 PCP, 667  
 pcp-storage, 130  
 PENALTY, 433  
 PERF\_RETENTION, 118, 251, 306, 327  
 performance archives, 130  
 Performance Co-Pilot, 130, 235  
 performance monitoring, 233  
 performance records, 117  
 performance statistics  
   remove, 306  
 PERFTRACE\_METRICS, 284  
 periodic maintenance tasks, 304  
 permission requirements, 45  
 persistent reservation, 671  
 pg\_data, 47  
 pg\_tmp, 47  
 pg\_xlog, 47  
 pglogs, 47  
 php-curl, 602  
 php5-openssl, 602  
 php5-soap, 602  
 pidentd, 166  
 pipes, 27  
 pminfo, 667  
 POLICIES, 357, 366, 463  
 policies, 186  
 policy object  
   overview, 273  
   parameters, 364  
 poor migration performance, 669  
 port speeds and tape drives, 134  
 POSITION\_RETRY, 406  
 POSITIONING, 405  
 POSIX\_FADVISE\_SIZE, 357  
 postgres, 280  
 postgres user, 47  
 PostgreSQL

requirements, 47  
   updates, 136  
 precedence of objects for integrated backups, 154  
 preconfigured samples in DMF Manager, 212  
 preferences in DMF Manager, 201  
 prevent file modification, 140  
 prevent recalls, 140  
 preventing automatic start, 181, 183  
 preventing automatic start of dmsoap, 601  
 PRIORITY\_PERIOD, 463  
 private filesystem of DMF and backups, 163  
 private network, 121  
 project ID via Windows client, 12  
 projid, 381  
 prune-files, 142  
 prune-inv, 142  
 prune-only, 143  
 purge records, 117  
 put file requests, 717  
 PUT\_IDLE\_DELAY, 419  
 PUTS\_TIME, 419

## Q

QLogic FC switch, 178  
 QUANTUM, 276  
 queue viewing  
   canceling a request, 613  
   database tables and fields, 620  
   dmqview, 605  
   modifying report output, 615  
   overview, 605  
   QView tab, 605  
   reports, 606  
   reprioritizing, 615  
   snapshot, 606  
 quit directive, 518, 545, 555  
 QView tab, 263, 605

**R**

- RAID set, 8
- range tokens
  - RECALL\_NOTIFICATION\_RATE and, 107
- ranges clause, 383
- ranking of files, 53
- RDM lock manager, 527
- READ\_ERR\_MAXIMUM, 406
- READ\_ERR\_MINIMUM, 407
- READ\_ERR\_TIMEOUT, 407
- READ\_IDLE\_DELAY, 407, 419
- READ\_TIME, 420
- readage, 549
- readcount, 549
- readdate, 549
- recall files via Windows client, 12
- recall of migrated files, 28
- RECALL\_NOTIFICATION\_RATE, 107, 292
- record length, 173
- recordlimit, 522, 550, 561
- recordorder, 522, 550, 561
- recovery
  - databases, 649
- Red Hat Enterprise Linux, 48
- Red Hat Enterprise Linux (RHEL), 12
- REDIRECT\_TIME\_DG\_DOWN, 407
- regions, 5
- regular file, 15, 28
- REINSTATE\_DRIVE\_DELAY, 408, 581
- REINSTATE\_VOLUME\_DELAY, 408
- relationships in DMF Manager, 227
- Release Note button, 790
- RELEASETHREADS, 358
- reliability, 339
- REMALENT\_PARAMS, 118, 306, 327
- remote connection failures, 670
- REMPERF\_PARAMS, 118, 307, 328
- repair directive, 555
- replace bad copy with good copy, 642
- reporting problems to SGI, 675
- Reports Panel in DMF Manager, 225
- Reports panel in DMF Manager, 193
- reprioritizing a request, 615
- request completion subroutines, 727
- request processing
  - disk MSP, 577
  - FTP MSP, 573
- requirements
  - direct archiving, 50
  - DMAPI, 49
  - DMF Manager, 49
  - DMF SOAP, 50
  - fast-mount cache, 50
  - hardware, 48
  - ksh, 48
  - licensing, 48
  - mounting service, 48
  - OpenVault, 48
  - parallel data-mover node, 48
  - server-node, 48
  - software, 48
  - TMP, 48
- RESERVED\_VOLUMES, 420
- resource scheduler
  - algorithm, 41
  - configuration, 273
  - object overview, 273
  - object parameters, 432
  - resourcescheduler object, 273
  - terminology, 41
  - weighted\_roundrobin, 433
- resource watcher
  - resourcewatcher object overview, 273
  - terminology, 41
- Resources panel in DMF Manager, 193
- retention of journal files, 338
- retention of log files, 338–340
- REWIND\_DELAY, 408, 421
- RHEL, 48
- robotic library, 16
- root squashing, 154



ROTATION\_STRATEGY, 102, 429  
 ROUND\_ROBIN\_BY\_FILES, 429  
 rounding of byte ranges, 385  
 rpm, 183, 184  
 rpm dmfsoap, 601  
 RRS, 451  
 RSCN, 178  
 rules for policy parameters in DMF configuration file, 366  
 run\_audit.sh, 305, 337  
 run\_compact\_tape\_report.sh, 852  
 run\_copy\_databases.sh, 56, 137, 305, 339  
 run\_daily\_drive\_report.sh, 305  
 run\_daily\_tsreport.sh, 305, 338  
 run\_dcm\_admin.sh, 307  
 run\_dmmigrate.sh, 116, 305, 307  
 run\_filesystem\_scan.sh, 306, 337  
 run\_fmc\_free.sh, 113, 307, 308  
 run\_full\_dump.sh, 55, 142, 306, 333, 334  
 run\_hard\_deletes.sh, 56, 131, 306, 333, 334  
 run\_merge\_mgr.sh, 307  
 run\_merge\_stop.sh, 307, 443  
 run\_partial\_dump.sh, 55, 143, 148, 306, 333, 334  
 run\_remove\_alerts.sh, 117  
 run\_remove\_journals.sh, 56, 306, 338, 442  
 run\_remove\_logs.sh, 56, 251, 306, 308, 338–340, 442  
 run\_remove\_perf.sh, 306  
 run\_scan\_logs.sh, 307, 338  
 run\_tape\_merge.sh, 307, 442, 443  
 run\_tape\_report.sh, 852  
 run\_tape\_stop.sh, 442  
 RUN\_TASK, 113, 328, 395, 409, 421

## S

S3  
     See "cloud MSP", 569  
 safe modifications to the DMF configuration, 102  
 safety, 6  
 SAM, 189

sample configuration files, 101  
 sample DMF SOAP client files, 601  
 sample\_sitelib.C, 736  
 sample\_sitelib.mk, 736  
 samples in DMF Manager, 212  
 SAN switch zoning or separate SAN fabric, 49  
 scalability, 6  
 Scality  
     See "cloud MSP", 569  
 SCAN\_FILESYSTEMS, 329  
 SCAN\_FOR\_DMSTAT, 329  
 SCAN\_OUTPUT, 330  
 SCAN\_PARALLEL, 330  
 SCAN\_PARAMS, 330  
 script names, 104  
 SCSI low-voltage differential (LVD) tapes, 8  
 sdparm, 134  
 SEAGATE ULTRIUM, 276  
 secondary storage  
     See also "migration", 5  
 select directive, 555  
 select system call, 516  
 SELECT\_LOWER\_VG, 380, 381  
 SELECT\_MSP, 374, 381, 750  
 SELECT\_VG, 139, 147, 374, 381, 750  
 selection expression, 556  
 SELinux, 136  
 separate SAN fabric, 49  
 SEQUENTIAL, 429  
 serial ATA, 16  
 server capability license, 67  
 server node functionality, 32  
 server\_args, 166  
 SERVER\_NAME, 284, 488  
 SERVICES, 296  
 services object  
     associated task scripts, 308  
     overview, 272  
     parameters, 300  
 SERVICES\_PORT, 102, 301, 488  
 SessTimeout, 127

- set directive, 518, 545, 555
- Setprojid file requests, 723
- Settag file requests, 725
- SGI 400 VTL
  - disable drives before stopping, 129
- SGI InfiniteStorage Software Platform (ISSP), 166
- SGI Knowledgebase, 675
- SGI LTFS
  - See "LTFS", 632
- SGI x86\_64 hardware, 48
- sgi-dmapi, 105
- sgi-ltfs, 631
- sgi-ltfs.conf, 633
- sgi-xfsplogs, 105
- sgi\_ltfs, 66
- sginfo, 135
- shutdown, 183, 184, 529
- shutdown of dmfsop, 601
- silo, 16
- site tag feature, 785
- site tags via Windows client, 12
- site-defined policies
  - considerations, 738
  - customizing DMF, 186
  - DmaConfigStanzaExists(), 752
  - DmaContext\_t, 739
  - DmaFrom\_t, 740
  - DmaGetConfigBool(), 753
  - DmaGetConfigFloat(), 754
  - DmaGetConfigInt(), 755
  - DmaGetConfigList(), 756
  - DmaGetConfigStanza(), 757
  - DmaGetConfigString(), 758
  - DmaGetContextFlags(), 759
  - DmaGetCookie(), 759
  - DmaGetDaemonMigGroups, 760
  - DmaGetDaemonVolAndMigGroups(), 760
  - DmaGetDaemonVolGroups(), 761
  - DmaGetMigGroupMembers, 761
  - DmaGetProgramIdentity(), 762
  - DmaGetUserIdentity(), 762
  - DmaIdentity\_t, 740
  - DmaLogLevel\_t, 742
  - DmaRealm\_t, 742
  - DmaRecallType\_t, 743
  - DmaSendLogFmtMessage(), 763
  - DmaSendUserFmtMessage(), 764
  - DmaSetCookie(), 765
  - getting started, 736
  - SiteArchiveFile(), 743
  - SiteCreateContext(), 745
  - SiteDestroyContext(), 746
  - SiteFncMap\_t, 743
  - SiteKernRecall(), 746
  - sitelib.so data types, 739, 742
  - SitePutFile(), 748
  - SiteWhen(), 750
  - subroutines overview, 735
  - terminology, 188
- site-specific configuration parameter and stanza names, 125
- site-specific objects and parameters
  - DMF Manager and, 211
- SITE\_SCRIPT, 371, 378
- SiteArchiveFile() sitelib.so subroutine, 743
- SiteCreateContext() sitelib.so subroutine, 745
- SiteDestroyContext() sitelib.so subroutine, 746
- sitefn expression, 381
- SiteFncMap variable, 737
- SiteFncMap\_t object, 743
- SiteKernRecall() sitelib.so subroutine, 746
- SITELIB parameter, 737
- sitelib.so
  - See "site-defined policy library", 735
- SitePutFile() sitelib.so subroutine, 748
- sitetag, 358
- sitetag expression, 381
- SiteWhen() sitelib.so subroutine, 750
- size expression, 381
- size of DMF database filesystems, 97
- SLES, 48
- slot usage, 242

- small files, 107
- small files and DMF, 146
- SMB, 9
- SMB request timeouts, 127
- SMB/CIFS network share, 668
- .so file, 41
- SOAP, 50
  - accessing the GUI, 599
  - dmfsoap service, 601
  - sample client files, 601
  - security/authentication, 601
  - See "", 597
  - starting, 601
  - stopping, 601
  - URLs for, 599
- SOAP web service, 13
- socket merges, 128
- soft-deleted files
  - maintenance/recovery, 586
- softdeleted expression, 381
- software mix, 81
- software requirements, 43
- Solaris, 13
- SONY SDX, 276
- SONY SDZ, 276
- space expression, 381
- space management
  - commands overview, 62
  - DCM MSP and, 513
- SPACE\_WEIGHT, 147, 373, 381, 383, 510, 750
- sparse tapes
  - configuration of automated merging, 443
  - merging, 307, 443
- sparse volumes
  - automated merging, 443
  - merging, 543
  - terminology, 54
- special files, 27
- SPOOL\_DIR, 45, 98, 102, 163, 284, 486, 513, 525, 533
- st\_time, 358
- stalled-recovery timeout, 118

- start DMF, 124
- starting the DMF environment, 181
- Statistics tab in DMF Manager, 193
- stdin, stdout, stderr and sitelib.so, 738
- STK, 276
- stop DMF, 124
- stopping the DMF environment, 181
- Storage tab in DMF Manager, 193
- STORE\_DIRECTORY, 46, 464, 470, 486, 579
- STORE\_DIRECTORY and dirsync, 46
- SUSE Linux Enterprise Server (SLES), 12, 48
- swdn, 134
- switch
  - QLogic, 178
- switch zoning, 49

## T

- T10000C, 631
- T10000D, 631
- T10000T2, 631
- tape autoloader API end of life, 783
- tape barcodes, 119
- tape drivers
  - ts, 66, 107, 337, 338, 660
- tape drives
  - host port speeds and, 134
  - reports on, 305
- tape ejection in DMF Manager, 232
- tape management
  - error reports, 443
  - merging sparse tapes, 443
  - merging sparse volumes, 543
- Tape Management Facility
  - See "TMF", 13
- tape merging, 307
  - See "volume merging", 543
- tape mounting services
  - See "OpenVault" or "TMF", 13
- tape MSP end of life, 784

- tape MSP/LS and dmatread, 567
  - tape performance, 781
  - tape recall, 185
  - tapesize keyword, 559
  - tar file recall, 643
  - task, 53
  - TASK\_GROUPS, 176, 293, 301, 358, 395, 409, 422, 453, 458, 464, 470
  - taskgroup, 113
  - taskgroup object
    - overview, 272
    - parameters, 304, 442
  - Tasks panel in DMF Manager, 193
  - tcpmux, 108
  - tcpmux service\_limit error, 670
  - terminology, 14
  - theory of archiving, 19
  - third-party backup package configuration, 767
  - THRESHOLD, 307, 331, 443
  - threshold keyword, 559
  - tiered-storage management, 5
  - Time Navigator, 769
  - time synchronization, 124
  - time\_expression configuration, 328
  - TIMEOUT\_FLUSH, 107, 422
  - tmcollect, 675
  - tmconfig, 594
  - TMF
    - availability, 170
    - considerations, 170
    - license, 74
    - LS drive groups and, 505
    - support for, 13
    - tracing, 126
  - TMF drive disabling, 594
  - TMF\_TMMNT\_OPTIONS, 350, 409
  - TMP\_DIR, 45, 102, 163, 285, 486
  - tmstat, 594
  - tools, 56
  - totals, 242
  - tpcrdm.dat, 647
  - tpcrdm.dat file, 537, 647
  - tpcrdm.key1.keys, 647
  - tpcrdm.key1.keys file, 537, 647
  - tpcrdm.key2.keys, 647
  - tpcrdm.key2.keys file, 537, 647
  - tpvrdm, 537
  - tpvrdm.dat, 538, 647
  - tpvrdm.dat file, 647
  - tpvrdm.vsn.keys, 538, 647
  - tpvrdm.vsn.keys file, 647
  - trace\_directory, 126
  - trace\_file\_size, 126
  - trace\_save\_directory, 126
  - tracing and TMF, 126
  - trailing scaling character, 275, 385
  - transaction processing, 38
  - transports, 42
  - trickle mode, 314
  - troubleshooting, 641
    - reporting problems to SGI, 675
  - ts tape driver, 337, 338
    - drives not claimed, 660
    - HBA drivers and initrd, 107
  - tsreport, 66
  - tsmt, 671
  - tsreport, 305, 338
  - TSREPORT\_OPTIONS, 331
  - tsset, 671
  - TYPE, 279, 290, 295, 300, 312, 343, 348, 352, 366, 367, 391, 393, 397, 411, 428, 433–435, 449, 456, 461, 468
- ## U
- uid expression, 382
  - ULTRIUM, 276
  - Ultrium5-1500, 631
  - Ultrium6-2500, 631
  - undocumented commands, 130
  - unit measures and DMF Manager, 234, 236

- UNIX special files, 27
- unknown mount option, 660
- unmigrating file, 15
- unsupported commands, 130
- upage keyword, 559
- update directive, 518, 545, 555
- update keyword, 559
- Update License button, 791
- UPDATE\_CTIME, 148, 358
- updateage, 521
- updatetime, 521, 524
- upgrade best practices, 84
- URL for DMF Manager, 10
- USE\_AS\_DUMP\_DEST, 359
- USE\_UNIFIED\_BUFFER, 359
- user interface commands, 57
- user library (libdmfus.so)
  - archive file requests, 712
  - context manipulation subroutines, 705
  - copy file requests, 710
  - distributed commands, 681
  - DmuAllErrors\_t, 686
  - DmuAttr\_t, 687
  - DmuAwaitReplies(), 728
  - DmuByteRange\_t, 688
  - DmuByteRanges\_t, 689
  - DmuChangedDirectory(), 707
  - DmuCompletion\_t, 692
  - DmuCopyAsync\_2(), 710
  - DmuCopyRange\_t, 693
  - DmuCopyRanges\_t, 693
  - DmuCopySync\_2(), 710
  - DmuCreateContext(), 705
  - DmuDestroyContext(), 707
  - DmuErrHandler\_f, 694
  - DmuErrInfo\_t, 695
  - DmuError\_t, 695
  - DmuEvents\_t, 696
  - DmuFhandle\_t, 696
  - DmuFilesysInfo(), 708
  - DmuFsysInfo\_t, 696
  - DmuFullRegbuf\_t, 697
  - DmuFullRegion\_t, 698
  - DmuFullstat\_2\_t, 699
  - DmuFullstat\_t, 698
  - DmuFullstatByFhandleAsync(), 714
  - DmuFullstatByFhandleSync(), 714
  - DmuFullstatByPathAsync(), 714
  - DmuFullstatByPathSync(), 714
  - DmuFullstatCompletion(), 729
  - DmuGetByFhandleAsync\_2(), 720
  - DmuGetByFhandleSync\_2(), 720
  - DmuGetByPathAsync\_2(), 720
  - DmuGetByPathSync\_2(), 720
  - DmuGetNextReply(), 730
  - DmuGetThisReply(), 732
  - DmuOperandType\_t, 700
  - DmuPriority\_t, 701
  - DmuPutByFhandleAsync(), 717
  - DmuPutByFhandleSync(), 717
  - DmuPutByPathAsync(), 717
  - DmuPutByPathSync(), 717
  - DmuRegion\_t, 701
  - DmuRegionbuf\_t, 701
  - DmuReplyOrder\_t, 702
  - DmuReplyType\_t, 702
  - DmuSetprojidByPathAsync, 725
  - DmuSettagByFhandleAsync(), 725
  - DmuSettagByFhandleSync(), 725
  - DmuSettagByPathAsync(), 725
  - DmuSettagByPathSync(), 725
  - DmuSeverity\_t, 702
  - DmuVolGroup\_t, 703
  - DmuVolGroups\_t, 703
  - file request subroutines, 709
  - fullstat requests, 714
  - get file requests, 720
  - IRIX considerations, 684
  - library versioning, 684
  - put file requests, 717
  - request completion subroutines, 727
  - Setprojid file requests, 723

- Settag file requests, 725
- sitelib.so and, 739
- update in DMF 3.1, 784
- user-accessible API subroutines for
  - libdmfusr.so.2, 705
- /usr/dmf/dmbase, 783
- /usr/lib/dmf/dmf\_client\_ports, 188
- /usr/lib/dmf/support/dmanytag, 785
- /usr/lib/dmf/support/dmclearcmtag, 785
- /usr/lib/dmf/support/dmclearpartial, 786
- /usr/lib/dmf/support/dmcleartag, 785
- /usr/lib/dmf/support/manypartial, 786
- /usr/sbin/lk\_hostid, 74
- /usr/share/doc/dmf-\*/info/sample, 736

## V

- VALID\_ROOT\_HOSTS, 285
- /var/lib/pcp-storage/archives, 130
- /var/lib/pcp-storage/archives directory, 130
- /var/log/xinetd.log, 670
- verification
  - automated task, 337
  - daemon database integrity, 337
  - dmmaint and, 789
  - License Info, 791
  - license keys, 75
  - run\_audit.sh, 337
- verify
  - disk MSPs, 579
- verify directive, 545, 555
- VERIFY\_POSITION, 409
- version keyword, 559
- VG, 244
  - configuration, 388, 389
  - objects, 273
  - selection for migrating files, 374, 380
  - terminology, 41
- VG and COPAN, 110
- vgnames, 551

- vista.taf file, 530
- VOL record
  - messages, 679
- VOL records, 37, 533, 537
  - backup, 646
- VOL\_MSG\_TIME, 422, 435
- volgrp, 549
- volgrp keyword, 559
- volume group, 244
- volume merge stopping, 307
- volume merging
  - configuration of automated task, 443
  - LS, 543
  - stopping automatically, 443
  - terminology, 38
- volume-to-volume merging, 543
- VOLUME\_GROUPS, 102, 409
- VOLUME\_LIMIT, 307, 332, 443
- volumegroup, 116, 140
- volumegroup object
  - associated task scripts, 308
  - overview, 273
  - parameters, 411
- volumes, 244
- Volumes panel in DMF Manager, 193, 229
- vsn, 549
- VSN on COPAN MAID, 64
- vsnlist expression, 556
- VTL
  - configuration best practices, 109
  - See "SGI 400 VTL", 109

## W

- WATCHER, 395
- web service definition language, 600
- web-based tool, 10
- WEIGHT, 433
- weighting of files for migration, 371, 378, 386
- wfage keyword, 560

wfdate keyword, 560  
What Is help, 201  
when clause, 380  
Windows client, 12  
Windows Explorer, 12  
Windows Explorer delay icon, 127  
Windows Explorer hangs, 669  
WRITE\_CHECKSUM, 409, 453, 458, 464, 470  
writeage, 549  
writedate, 549  
WSDL, 600

## **X**

XDSM standard, 39  
XFS, 8  
XFS immutable bit, 140  
xfsdump, 643  
xfsrestore, 643

xinetd, 108, 165, 166  
XVM failover, 49

## **Y**

YAST and configuring network services, 83

## **Z**

zone size and performance, 105  
ZONE\_SIZE, 105, 107, 423, 781  
zoneblockid, 549  
zonenumber, 549  
zonepos, 549  
zones, 534  
zonesize, 680  
zoning of the SAN switch, 49